

hypr  
2.24.0

Generated by Doxygen 1.9.8



<b>1 Topic Index</b>	<b>1</b>
1.1 Topics	1
<b>2 File Index</b>	<b>3</b>
2.1 File List	3
<b>3 Topic Documentation</b>	<b>5</b>
3.1 Struct System Interface	5
3.1.1 Detailed Description	7
3.1.2 Typedef Documentation	7
3.1.2.1 HYPRE_StructGrid	7
3.1.2.2 HYPRE_StructMatrix	7
3.1.2.3 HYPRE_StructStencil	7
3.1.3 Function Documentation	7
3.1.3.1 HYPRE_StructGridAssemble()	7
3.1.3.2 HYPRE_StructGridCreate()	7
3.1.3.3 HYPRE_StructGridDestroy()	8
3.1.3.4 HYPRE_StructGridSetExtents()	8
3.1.3.5 HYPRE_StructGridSetNumGhost()	8
3.1.3.6 HYPRE_StructGridSetPeriodic()	8
3.1.3.7 HYPRE_StructMatrixAddToBoxValues()	8
3.1.3.8 HYPRE_StructMatrixAddToBoxValues2()	9
3.1.3.9 HYPRE_StructMatrixAddToConstantValues()	9
3.1.3.10 HYPRE_StructMatrixAddToValues()	9
3.1.3.11 HYPRE_StructMatrixAssemble()	9
3.1.3.12 HYPRE_StructMatrixCreate()	9
3.1.3.13 HYPRE_StructMatrixDestroy()	10
3.1.3.14 HYPRE_StructMatrixGetBoxValues()	10
3.1.3.15 HYPRE_StructMatrixGetBoxValues2()	10
3.1.3.16 HYPRE_StructMatrixGetValues()	10
3.1.3.17 HYPRE_StructMatrixInitialize()	10
3.1.3.18 HYPRE_StructMatrixMatvec()	11
3.1.3.19 HYPRE_StructMatrixPrint()	11
3.1.3.20 HYPRE_StructMatrixSetBoxValues()	11
3.1.3.21 HYPRE_StructMatrixSetBoxValues2()	11
3.1.3.22 HYPRE_StructMatrixSetConstantEntries()	12
3.1.3.23 HYPRE_StructMatrixSetConstantValues()	12
3.1.3.24 HYPRE_StructMatrixSetNumGhost()	12
3.1.3.25 HYPRE_StructMatrixSetSymmetric()	12
3.1.3.26 HYPRE_StructMatrixSetValues()	13
3.1.3.27 HYPRE_StructStencilCreate()	13
3.1.3.28 HYPRE_StructStencilDestroy()	13
3.1.3.29 HYPRE_StructStencilSetElement()	13

3.1.3.30 HYPRE_StructVectorAddToBoxValues()	13
3.1.3.31 HYPRE_StructVectorAddToBoxValues2()	14
3.1.3.32 HYPRE_StructVectorAddToValues()	14
3.1.3.33 HYPRE_StructVectorAssemble()	14
3.1.3.34 HYPRE_StructVectorCreate()	14
3.1.3.35 HYPRE_StructVectorDestroy()	14
3.1.3.36 HYPRE_StructVectorGetBoxValues()	15
3.1.3.37 HYPRE_StructVectorGetBoxValues2()	15
3.1.3.38 HYPRE_StructVectorGetValues()	15
3.1.3.39 HYPRE_StructVectorInitialize()	15
3.1.3.40 HYPRE_StructVectorPrint()	15
3.1.3.41 HYPRE_StructVectorSetBoxValues()	16
3.1.3.42 HYPRE_StructVectorSetBoxValues2()	16
3.1.3.43 HYPRE_StructVectorSetValues()	16
3.2 SStruct System Interface	17
3.2.1 Detailed Description	19
3.2.2 Macro Definition Documentation	19
3.2.2.1 HYPRE_SSTRUCT_VARIABLE_CELL	19
3.2.2.2 HYPRE_SSTRUCT_VARIABLE_NODE	20
3.2.2.3 HYPRE_SSTRUCT_VARIABLE_UNDEFINED	20
3.2.2.4 HYPRE_SSTRUCT_VARIABLE_XEDGE	20
3.2.2.5 HYPRE_SSTRUCT_VARIABLE_XFACE	20
3.2.2.6 HYPRE_SSTRUCT_VARIABLE_YEDGE	20
3.2.2.7 HYPRE_SSTRUCT_VARIABLE_YFACE	20
3.2.2.8 HYPRE_SSTRUCT_VARIABLE_ZEDGE	20
3.2.2.9 HYPRE_SSTRUCT_VARIABLE_ZFACE	20
3.2.3 Typedef Documentation	20
3.2.3.1 HYPRE_SStructGraph	20
3.2.3.2 HYPRE_SStructGrid	21
3.2.3.3 HYPRE_SStructMatrix	21
3.2.3.4 HYPRE_SStructStencil	21
3.2.3.5 HYPRE_SStructVariable	21
3.2.3.6 HYPRE_SStructVector	22
3.2.4 Function Documentation	22
3.2.4.1 HYPRE_SStructGraphAddEntries()	22
3.2.4.2 HYPRE_SStructGraphAssemble()	22
3.2.4.3 HYPRE_SStructGraphCreate()	22
3.2.4.4 HYPRE_SStructGraphDestroy()	22
3.2.4.5 HYPRE_SStructGraphSetDomainGrid()	23
3.2.4.6 HYPRE_SStructGraphSetFEM()	23
3.2.4.7 HYPRE_SStructGraphSetFEMSparsity()	23
3.2.4.8 HYPRE_SStructGraphSetObjectType()	23

3.2.4.9 HYPRE_SStructGraphSetStencil()	24
3.2.4.10 HYPRE_SStructGridAddUnstructuredPart()	24
3.2.4.11 HYPRE_SStructGridAddVariables()	24
3.2.4.12 HYPRE_SStructGridAssemble()	24
3.2.4.13 HYPRE_SStructGridCreate()	24
3.2.4.14 HYPRE_SStructGridDestroy()	25
3.2.4.15 HYPRE_SStructGridSetExtents()	25
3.2.4.16 HYPRE_SStructGridSetFEMOrdering()	25
3.2.4.17 HYPRE_SStructGridSetNeighborPart()	26
3.2.4.18 HYPRE_SStructGridSetNumGhost()	26
3.2.4.19 HYPRE_SStructGridSetPeriodic()	26
3.2.4.20 HYPRE_SStructGridSetSharedPart()	27
3.2.4.21 HYPRE_SStructGridSetVariables()	27
3.2.4.22 HYPRE_SStructMatrixAddFEMValues()	28
3.2.4.23 HYPRE_SStructMatrixAddToBoxValues()	28
3.2.4.24 HYPRE_SStructMatrixAddToBoxValues2()	28
3.2.4.25 HYPRE_SStructMatrixAddToValues()	29
3.2.4.26 HYPRE_SStructMatrixAssemble()	29
3.2.4.27 HYPRE_SStructMatrixCreate()	29
3.2.4.28 HYPRE_SStructMatrixDestroy()	29
3.2.4.29 HYPRE_SStructMatrixGetBoxValues()	30
3.2.4.30 HYPRE_SStructMatrixGetBoxValues2()	30
3.2.4.31 HYPRE_SStructMatrixGetFEMValues()	30
3.2.4.32 HYPRE_SStructMatrixGetObject()	30
3.2.4.33 HYPRE_SStructMatrixGetValues()	31
3.2.4.34 HYPRE_SStructMatrixInitialize()	31
3.2.4.35 HYPRE_SStructMatrixPrint()	31
3.2.4.36 HYPRE_SStructMatrixSetBoxValues()	31
3.2.4.37 HYPRE_SStructMatrixSetBoxValues2()	32
3.2.4.38 HYPRE_SStructMatrixSetNSSymmetric()	32
3.2.4.39 HYPRE_SStructMatrixSetObjectType()	32
3.2.4.40 HYPRE_SStructMatrixSetSymmetric()	33
3.2.4.41 HYPRE_SStructMatrixSetValues()	33
3.2.4.42 HYPRE_SStructStencilCreate()	33
3.2.4.43 HYPRE_SStructStencilDestroy()	33
3.2.4.44 HYPRE_SStructStencilSetEntry()	34
3.2.4.45 HYPRE_SStructVectorAddFEMValues()	34
3.2.4.46 HYPRE_SStructVectorAddToBoxValues()	34
3.2.4.47 HYPRE_SStructVectorAddToBoxValues2()	34
3.2.4.48 HYPRE_SStructVectorAddToValues()	35
3.2.4.49 HYPRE_SStructVectorAssemble()	35
3.2.4.50 HYPRE_SStructVectorCreate()	35

3.2.4.51 HYPRE_SStructVectorDestroy()	35
3.2.4.52 HYPRE_SStructVectorGather()	35
3.2.4.53 HYPRE_SStructVectorGetBoxValues()	36
3.2.4.54 HYPRE_SStructVectorGetBoxValues2()	36
3.2.4.55 HYPRE_SStructVectorGetFEMValues()	36
3.2.4.56 HYPRE_SStructVectorGetObject()	36
3.2.4.57 HYPRE_SStructVectorGetValues()	37
3.2.4.58 HYPRE_SStructVectorInitialize()	37
3.2.4.59 HYPRE_SStructVectorPrint()	37
3.2.4.60 HYPRE_SStructVectorSetBoxValues()	37
3.2.4.61 HYPRE_SStructVectorSetBoxValues2()	38
3.2.4.62 HYPRE_SStructVectorSetObjectType()	38
3.2.4.63 HYPRE_SStructVectorSetValues()	38
3.3 IJ System Interface	39
3.3.1 Detailed Description	40
3.3.2 Typedef Documentation	40
3.3.2.1 HYPRE_IJMatrix	40
3.3.2.2 HYPRE_IJVector	40
3.3.3 Function Documentation	40
3.3.3.1 HYPRE_IJMatrixAddToValues()	40
3.3.3.2 HYPRE_IJMatrixAddToValues2()	41
3.3.3.3 HYPRE_IJMatrixAssemble()	41
3.3.3.4 HYPRE_IJMatrixCreate()	41
3.3.3.5 HYPRE_IJMatrixDestroy()	41
3.3.3.6 HYPRE_IJMatrixGetLocalRange()	42
3.3.3.7 HYPRE_IJMatrixGetObject()	42
3.3.3.8 HYPRE_IJMatrixGetObjectType()	42
3.3.3.9 HYPRE_IJMatrixGetRowCounts()	42
3.3.3.10 HYPRE_IJMatrixGetValues()	42
3.3.3.11 HYPRE_IJMatrixInitialize()	43
3.3.3.12 HYPRE_IJMatrixInitialize_v2()	43
3.3.3.13 HYPRE_IJMatrixPrint()	43
3.3.3.14 HYPRE_IJMatrixRead()	43
3.3.3.15 HYPRE_IJMatrixSetConstantValues()	43
3.3.3.16 HYPRE_IJMatrixSetDiagOffdSizes()	44
3.3.3.17 HYPRE_IJMatrixSetMaxOffProcElmts()	44
3.3.3.18 HYPRE_IJMatrixSetObjectType()	44
3.3.3.19 HYPRE_IJMatrixSetOMPFlag()	44
3.3.3.20 HYPRE_IJMatrixSetPrintLevel()	45
3.3.3.21 HYPRE_IJMatrixSetRowSizes()	45
3.3.3.22 HYPRE_IJMatrixSetValues()	45
3.3.3.23 HYPRE_IJMatrixSetValues2()	45

3.3.3.24 HYPRE_IJVectorAddToValues()	46
3.3.3.25 HYPRE_IJVectorAssemble()	46
3.3.3.26 HYPRE_IJVectorCreate()	46
3.3.3.27 HYPRE_IJVectorDestroy()	46
3.3.3.28 HYPRE_IJVectorGetLocalRange()	46
3.3.3.29 HYPRE_IJVectorGetObject()	47
3.3.3.30 HYPRE_IJVectorGetObjectType()	47
3.3.3.31 HYPRE_IJVectorGetValues()	47
3.3.3.32 HYPRE_IJVectorInitialize()	47
3.3.3.33 HYPRE_IJVectorInitialize_v2()	47
3.3.3.34 HYPRE_IJVectorPrint()	48
3.3.3.35 HYPRE_IJVectorRead()	48
3.3.3.36 HYPRE_IJVectorSetMaxOffProcElmts()	48
3.3.3.37 HYPRE_IJVectorSetObjectType()	48
3.3.3.38 HYPRE_IJVectorSetPrintLevel()	48
3.3.3.39 HYPRE_IJVectorSetValues()	49
3.4 Struct Solvers	49
3.4.1 Detailed Description	55
3.4.2 Macro Definition Documentation	56
3.4.2.1 HYPRE_MODIFYPC	56
3.4.2.2 HYPRE_SOLVER_STRUCT	56
3.4.3 Typedef Documentation	56
3.4.3.1 HYPRE_PtrToModifyPCFcn	56
3.4.3.2 HYPRE_PtrToStructSolverFcn	56
3.4.3.3 HYPRE_Solver	56
3.4.3.4 HYPRE_StructSolver	56
3.4.4 Function Documentation	56
3.4.4.1 HYPRE_StructBiCGSTABCreate()	56
3.4.4.2 HYPRE_StructBiCGSTABDestroy()	57
3.4.4.3 HYPRE_StructBiCGSTABGetFinalRelativeResidualNorm()	57
3.4.4.4 HYPRE_StructBiCGSTABGetNumIterations()	57
3.4.4.5 HYPRE_StructBiCGSTABGetResidual()	57
3.4.4.6 HYPRE_StructBiCGSTABSetAbsoluteTol()	57
3.4.4.7 HYPRE_StructBiCGSTABSetLogging()	57
3.4.4.8 HYPRE_StructBiCGSTABSetMaxIter()	57
3.4.4.9 HYPRE_StructBiCGSTABSetPrecond()	58
3.4.4.10 HYPRE_StructBiCGSTABSetPrintLevel()	58
3.4.4.11 HYPRE_StructBiCGSTABSetTol()	58
3.4.4.12 HYPRE_StructBiCGSTABSetup()	58
3.4.4.13 HYPRE_StructBiCGSTABsolve()	58
3.4.4.14 HYPRE_StructCycRedCreate()	58
3.4.4.15 HYPRE_StructCycRedDestroy()	58

3.4.4.16 HYPRE_StructCycRedSetBase()	59
3.4.4.17 HYPRE_StructCycRedSetTDim()	59
3.4.4.18 HYPRE_StructCycRedSetup()	59
3.4.4.19 HYPRE_StructCycRedSolve()	59
3.4.4.20 HYPRE_StructDiagScale()	59
3.4.4.21 HYPRE_StructDiagScaleSetup()	60
3.4.4.22 HYPRE_StructFlexGMRESCreate()	60
3.4.4.23 HYPRE_StructFlexGMRESDestroy()	60
3.4.4.24 HYPRE_StructFlexGMRESGetFinalRelativeResidualNorm()	60
3.4.4.25 HYPRE_StructFlexGMRESGetNumIterations()	60
3.4.4.26 HYPRE_StructFlexGMRESGetResidual()	60
3.4.4.27 HYPRE_StructFlexGMRESSetAbsoluteTol()	60
3.4.4.28 HYPRE_StructFlexGMRESSetKDim()	61
3.4.4.29 HYPRE_StructFlexGMRESSetLogging()	61
3.4.4.30 HYPRE_StructFlexGMRESSetMaxIter()	61
3.4.4.31 HYPRE_StructFlexGMRESSetModifyPC()	61
3.4.4.32 HYPRE_StructFlexGMRESSetPrecond()	61
3.4.4.33 HYPRE_StructFlexGMRESSetPrintLevel()	61
3.4.4.34 HYPRE_StructFlexGMRESSetTol()	61
3.4.4.35 HYPRE_StructFlexGMRESSetup()	62
3.4.4.36 HYPRE_StructFlexGMRESSolve()	62
3.4.4.37 HYPRE_StructGMRESCreate()	62
3.4.4.38 HYPRE_StructGMRESDestroy()	62
3.4.4.39 HYPRE_StructGMRESGetFinalRelativeResidualNorm()	62
3.4.4.40 HYPRE_StructGMRESGetNumIterations()	62
3.4.4.41 HYPRE_StructGMRESGetResidual()	62
3.4.4.42 HYPRE_StructGMRESSetAbsoluteTol()	63
3.4.4.43 HYPRE_StructGMRESSetKDim()	63
3.4.4.44 HYPRE_StructGMRESSetLogging()	63
3.4.4.45 HYPRE_StructGMRESSetMaxIter()	63
3.4.4.46 HYPRE_StructGMRESSetPrecond()	63
3.4.4.47 HYPRE_StructGMRESSetPrintLevel()	63
3.4.4.48 HYPRE_StructGMRESSetTol()	63
3.4.4.49 HYPRE_StructGMRESSetup()	64
3.4.4.50 HYPRE_StructGMRESSolve()	64
3.4.4.51 HYPRE_StructHybridCreate()	64
3.4.4.52 HYPRE_StructHybridDestroy()	64
3.4.4.53 HYPRE_StructHybridGetDSCGNumIterations()	64
3.4.4.54 HYPRE_StructHybridGetFinalRelativeResidualNorm()	64
3.4.4.55 HYPRE_StructHybridGetNumIterations()	65
3.4.4.56 HYPRE_StructHybridGetPCGNumIterations()	65
3.4.4.57 HYPRE_StructHybridGetRecomputeResidual()	65



3.4.4.58 HYPRE_StructHybridGetRecomputeResidualP()	65
3.4.4.59 HYPRE_StructHybridSetConvergenceTol()	65
3.4.4.60 HYPRE_StructHybridSetDSCGMaxIter()	65
3.4.4.61 HYPRE_StructHybridSetKDim()	66
3.4.4.62 HYPRE_StructHybridSetLogging()	66
3.4.4.63 HYPRE_StructHybridSetPCGAbsoluteTolFactor()	66
3.4.4.64 HYPRE_StructHybridSetPCGMaxIter()	66
3.4.4.65 HYPRE_StructHybridSetPrecond()	66
3.4.4.66 HYPRE_StructHybridSetPrintLevel()	66
3.4.4.67 HYPRE_StructHybridSetRecomputeResidual()	67
3.4.4.68 HYPRE_StructHybridSetRecomputeResidualP()	67
3.4.4.69 HYPRE_StructHybridSetRelChange()	67
3.4.4.70 HYPRE_StructHybridSetSolverType()	67
3.4.4.71 HYPRE_StructHybridSetStopCrit()	67
3.4.4.72 HYPRE_StructHybridSetTol()	68
3.4.4.73 HYPRE_StructHybridSetTwoNorm()	68
3.4.4.74 HYPRE_StructHybridSetup()	68
3.4.4.75 HYPRE_StructHybridSolve()	68
3.4.4.76 HYPRE_StructJacobiCreate()	68
3.4.4.77 HYPRE_StructJacobiDestroy()	69
3.4.4.78 HYPRE_StructJacobiGetFinalRelativeResidualNorm()	69
3.4.4.79 HYPRE_StructJacobiGetMaxIter()	69
3.4.4.80 HYPRE_StructJacobiGetNumIterations()	69
3.4.4.81 HYPRE_StructJacobiGetTol()	69
3.4.4.82 HYPRE_StructJacobiGetZeroGuess()	69
3.4.4.83 HYPRE_StructJacobiSetMaxIter()	70
3.4.4.84 HYPRE_StructJacobiSetNonZeroGuess()	70
3.4.4.85 HYPRE_StructJacobiSetTol()	70
3.4.4.86 HYPRE_StructJacobiSetup()	70
3.4.4.87 HYPRE_StructJacobiSetZeroGuess()	70
3.4.4.88 HYPRE_StructJacobiSolve()	70
3.4.4.89 HYPRE_StructLGMRESCreate()	71
3.4.4.90 HYPRE_StructLGMRESDestroy()	71
3.4.4.91 HYPRE_StructLGMRESGetFinalRelativeResidualNorm()	71
3.4.4.92 HYPRE_StructLGMRESGetNumIterations()	71
3.4.4.93 HYPRE_StructLGMRESGetResidual()	71
3.4.4.94 HYPRE_StructLGMRESSetAbsoluteTol()	71
3.4.4.95 HYPRE_StructLGMRESSetAugDim()	71
3.4.4.96 HYPRE_StructLGMRESSetKDim()	72
3.4.4.97 HYPRE_StructLGMRESSetLogging()	72
3.4.4.98 HYPRE_StructLGMRESSetMaxIter()	72
3.4.4.99 HYPRE_StructLGMRESSetPrecond()	72

3.4.4.100 HYPRE_StructLGMRESSetPrintLevel()	72
3.4.4.101 HYPRE_StructLGMRESSetTol()	72
3.4.4.102 HYPRE_StructLGMRESSetup()	72
3.4.4.103 HYPRE_StructLGMRESSolve()	73
3.4.4.104 HYPRE_StructPCGCreate()	73
3.4.4.105 HYPRE_StructPCGDestroy()	73
3.4.4.106 HYPRE_StructPCGGetFinalRelativeResidualNorm()	73
3.4.4.107 HYPRE_StructPCGGetNumIterations()	73
3.4.4.108 HYPRE_StructPCGGetResidual()	73
3.4.4.109 HYPRE_StructPCGSetAbsoluteTol()	73
3.4.4.110 HYPRE_StructPCGSetLogging()	74
3.4.4.111 HYPRE_StructPCGSetMaxIter()	74
3.4.4.112 HYPRE_StructPCGSetPrecond()	74
3.4.4.113 HYPRE_StructPCGSetPrintLevel()	74
3.4.4.114 HYPRE_StructPCGSetRelChange()	74
3.4.4.115 HYPRE_StructPCGSetTol()	74
3.4.4.116 HYPRE_StructPCGSetTwoNorm()	74
3.4.4.117 HYPRE_StructPCGSetup()	75
3.4.4.118 HYPRE_StructPCGSolve()	75
3.4.4.119 HYPRE_StructPFMGCreate()	75
3.4.4.120 HYPRE_StructPFMGDestroy()	75
3.4.4.121 HYPRE_StructPFMGGetFinalRelativeResidualNorm()	75
3.4.4.122 HYPRE_StructPFMGGetJacobiWeight()	75
3.4.4.123 HYPRE_StructPFMGGetLogging()	76
3.4.4.124 HYPRE_StructPFMGGetMaxIter()	76
3.4.4.125 HYPRE_StructPFMGGetMaxLevels()	76
3.4.4.126 HYPRE_StructPFMGGetNumIterations()	76
3.4.4.127 HYPRE_StructPFMGGetNumPostRelax()	76
3.4.4.128 HYPRE_StructPFMGGetNumPreRelax()	76
3.4.4.129 HYPRE_StructPFMGGetPrintLevel()	76
3.4.4.130 HYPRE_StructPFMGGetRAPType()	77
3.4.4.131 HYPRE_StructPFMGGetRelaxType()	77
3.4.4.132 HYPRE_StructPFMGGetRelChange()	77
3.4.4.133 HYPRE_StructPFMGGetSkipRelax()	77
3.4.4.134 HYPRE_StructPFMGGetTol()	77
3.4.4.135 HYPRE_StructPFMGGetZeroGuess()	77
3.4.4.136 HYPRE_StructPFMGSetDxyz()	77
3.4.4.137 HYPRE_StructPFMGSetJacobiWeight()	77
3.4.4.138 HYPRE_StructPFMGSetLogging()	78
3.4.4.139 HYPRE_StructPFMGSetMaxIter()	78
3.4.4.140 HYPRE_StructPFMGSetMaxLevels()	78
3.4.4.141 HYPRE_StructPFMGSetNonZeroGuess()	78

---

3.4.4.142 HYPRE_StructPFMGSetNumPostRelax()	78
3.4.4.143 HYPRE_StructPFMGSetNumPreRelax()	78
3.4.4.144 HYPRE_StructPFMGSetPrintLevel()	79
3.4.4.145 HYPRE_StructPFMGSetRAPType()	79
3.4.4.146 HYPRE_StructPFMGSetRelaxType()	79
3.4.4.147 HYPRE_StructPFMGSetRelChange()	79
3.4.4.148 HYPRE_StructPFMGSetSkipRelax()	80
3.4.4.149 HYPRE_StructPFMGSetTol()	80
3.4.4.150 HYPRE_StructPFMGSetup()	80
3.4.4.151 HYPRE_StructPFMGSetZeroGuess()	80
3.4.4.152 HYPRE_StructPFMGsolve()	80
3.4.4.153 HYPRE_StructSetupInterpreter()	81
3.4.4.154 HYPRE_StructSetupMatvec()	81
3.4.4.155 HYPRE_StructSMGCreate()	81
3.4.4.156 HYPRE_StructSMGDestroy()	81
3.4.4.157 HYPRE_StructSMGGetFinalRelativeResidualNorm()	81
3.4.4.158 HYPRE_StructSMGGetLogging()	81
3.4.4.159 HYPRE_StructSMGGetMaxIter()	81
3.4.4.160 HYPRE_StructSMGGetMemoryUse()	82
3.4.4.161 HYPRE_StructSMGGetNumIterations()	82
3.4.4.162 HYPRE_StructSMGGetNumPostRelax()	82
3.4.4.163 HYPRE_StructSMGGetNumPreRelax()	82
3.4.4.164 HYPRE_StructSMGGetPrintLevel()	82
3.4.4.165 HYPRE_StructSMGGetRelChange()	82
3.4.4.166 HYPRE_StructSMGGetTol()	82
3.4.4.167 HYPRE_StructSMGGetZeroGuess()	83
3.4.4.168 HYPRE_StructSMGSetLogging()	83
3.4.4.169 HYPRE_StructSMGSetMaxIter()	83
3.4.4.170 HYPRE_StructSMGSetMemoryUse()	83
3.4.4.171 HYPRE_StructSMGSetNonZeroGuess()	83
3.4.4.172 HYPRE_StructSMGSetNumPostRelax()	83
3.4.4.173 HYPRE_StructSMGSetNumPreRelax()	84
3.4.4.174 HYPRE_StructSMGSetPrintLevel()	84
3.4.4.175 HYPRE_StructSMGSetRelChange()	84
3.4.4.176 HYPRE_StructSMGSetTol()	84
3.4.4.177 HYPRE_StructSMGSetup()	84
3.4.4.178 HYPRE_StructSMGSetZeroGuess()	84
3.4.4.179 HYPRE_StructSMGsolve()	85
3.4.4.180 HYPRE_StructSparseMSGCreate()	85
3.4.4.181 HYPRE_StructSparseMSGDestroy()	85
3.4.4.182 HYPRE_StructSparseMSGGetFinalRelativeResidualNorm()	85
3.4.4.183 HYPRE_StructSparseMSGGetNumIterations()	85

3.4.4.184 HYPRE_StructSparseMSGSetJacobiWeight()	85
3.4.4.185 HYPRE_StructSparseMSGSetJump()	85
3.4.4.186 HYPRE_StructSparseMSGSetLogging()	86
3.4.4.187 HYPRE_StructSparseMSGSetMaxIter()	86
3.4.4.188 HYPRE_StructSparseMSGSetNonZeroGuess()	86
3.4.4.189 HYPRE_StructSparseMSGSetNumFineRelax()	86
3.4.4.190 HYPRE_StructSparseMSGSetNumPostRelax()	86
3.4.4.191 HYPRE_StructSparseMSGSetNumPreRelax()	86
3.4.4.192 HYPRE_StructSparseMSGSetPrintLevel()	86
3.4.4.193 HYPRE_StructSparseMSGSetRelaxType()	86
3.4.4.194 HYPRE_StructSparseMSGSetRelChange()	87
3.4.4.195 HYPRE_StructSparseMSGSetTol()	87
3.4.4.196 HYPRE_StructSparseMSGSetup()	87
3.4.4.197 HYPRE_StructSparseMSGSetZeroGuess()	87
3.4.4.198 HYPRE_StructSparseMSGSolve()	87
3.5 SStruct Solvers	87
3.5.1 Detailed Description	93
3.5.2 Macro Definition Documentation	93
3.5.2.1 HYPRE_Jacobi	93
3.5.2.2 HYPRE_MODIFYPC	93
3.5.2.3 HYPRE_PFMG	93
3.5.2.4 HYPRE_SMG	93
3.5.2.5 HYPRE_SOLVER_STRUCT	93
3.5.3 Typedef Documentation	93
3.5.3.1 HYPRE_PtrToModifyPCFcn	93
3.5.3.2 HYPRE_PtrToSStructSolverFcn	94
3.5.3.3 HYPRE_Solver	94
3.5.3.4 HYPRE_SStructSolver	94
3.5.4 Function Documentation	94
3.5.4.1 HYPRE_SStructBiCGSTABCreate()	94
3.5.4.2 HYPRE_SStructBiCGSTABDestroy()	94
3.5.4.3 HYPRE_SStructBiCGSTABGetFinalRelativeResidualNorm()	94
3.5.4.4 HYPRE_SStructBiCGSTABGetNumIterations()	94
3.5.4.5 HYPRE_SStructBiCGSTABGetResidual()	95
3.5.4.6 HYPRE_SStructBiCGSTABSetAbsoluteTol()	95
3.5.4.7 HYPRE_SStructBiCGSTABSetLogging()	95
3.5.4.8 HYPRE_SStructBiCGSTABSetMaxIter()	95
3.5.4.9 HYPRE_SStructBiCGSTABSetMinIter()	95
3.5.4.10 HYPRE_SStructBiCGSTABSetPrecond()	95
3.5.4.11 HYPRE_SStructBiCGSTABSetPrintLevel()	95
3.5.4.12 HYPRE_SStructBiCGSTABSetStopCrit()	96
3.5.4.13 HYPRE_SStructBiCGSTABSetTol()	96

3.5.4.14 HYPRE_SStructBiCGSTABSetup()	96
3.5.4.15 HYPRE_SStructBiCGSTABsolve()	96
3.5.4.16 HYPRE_SStructDiagScale()	96
3.5.4.17 HYPRE_SStructDiagScaleSetup()	96
3.5.4.18 HYPRE_SStructFACAMR_RAP()	97
3.5.4.19 HYPRE_SStructFACCreate()	97
3.5.4.20 HYPRE_SStructFACDestroy2()	97
3.5.4.21 HYPRE_SStructFACGetFinalRelativeResidualNorm()	97
3.5.4.22 HYPRE_SStructFACGetNumIterations()	97
3.5.4.23 HYPRE_SStructFACSetCoarseSolverType()	98
3.5.4.24 HYPRE_SStructFACSetJacobiWeight()	98
3.5.4.25 HYPRE_SStructFACSetLogging()	98
3.5.4.26 HYPRE_SStructFACSetMaxIter()	98
3.5.4.27 HYPRE_SStructFACSetMaxLevels()	98
3.5.4.28 HYPRE_SStructFACSetNonZeroGuess()	99
3.5.4.29 HYPRE_SStructFACSetNumPostRelax()	99
3.5.4.30 HYPRE_SStructFACSetNumPreRelax()	99
3.5.4.31 HYPRE_SStructFACSetPLevels()	99
3.5.4.32 HYPRE_SStructFACSetPRefinements()	99
3.5.4.33 HYPRE_SStructFACSetRelaxType()	99
3.5.4.34 HYPRE_SStructFACSetRelChange()	100
3.5.4.35 HYPRE_SStructFACSetTol()	100
3.5.4.36 HYPRE_SStructFACSetup2()	100
3.5.4.37 HYPRE_SStructFACSetZeroGuess()	100
3.5.4.38 HYPRE_SStructFACsolve3()	100
3.5.4.39 HYPRE_SStructFACZeroAMRMatrixData()	100
3.5.4.40 HYPRE_SStructFACZeroAMRVectorData()	101
3.5.4.41 HYPRE_SStructFACZeroCFSten()	101
3.5.4.42 HYPRE_SStructFACZeroFCSten()	101
3.5.4.43 HYPRE_SStructFlexGMRESCreate()	101
3.5.4.44 HYPRE_SStructFlexGMRESDestroy()	101
3.5.4.45 HYPRE_SStructFlexGMRESGetFinalRelativeResidualNorm()	102
3.5.4.46 HYPRE_SStructFlexGMRESGetNumIterations()	102
3.5.4.47 HYPRE_SStructFlexGMRESGetResidual()	102
3.5.4.48 HYPRE_SStructFlexGMRESSetAbsoluteTol()	102
3.5.4.49 HYPRE_SStructFlexGMRESSetKDim()	102
3.5.4.50 HYPRE_SStructFlexGMRESSetLogging()	102
3.5.4.51 HYPRE_SStructFlexGMRESSetMaxIter()	102
3.5.4.52 HYPRE_SStructFlexGMRESSetMinIter()	102
3.5.4.53 HYPRE_SStructFlexGMRESSetModifyPC()	103
3.5.4.54 HYPRE_SStructFlexGMRESSetPrecond()	103
3.5.4.55 HYPRE_SStructFlexGMRESSetPrintLevel()	103

3.5.4.56 HYPRE_SStructFlexGMRESSetTol()	103
3.5.4.57 HYPRE_SStructFlexGMRESSetup()	103
3.5.4.58 HYPRE_SStructFlexGMRESSolve()	103
3.5.4.59 HYPRE_SStructGMRESCreate()	103
3.5.4.60 HYPRE_SStructGMRESDestroy()	104
3.5.4.61 HYPRE_SStructGMRESGetFinalRelativeResidualNorm()	104
3.5.4.62 HYPRE_SStructGMRESGetNumIterations()	104
3.5.4.63 HYPRE_SStructGMRESGetResidual()	104
3.5.4.64 HYPRE_SStructGMRESSetAbsoluteTol()	104
3.5.4.65 HYPRE_SStructGMRESSetKDim()	104
3.5.4.66 HYPRE_SStructGMRESSetLogging()	104
3.5.4.67 HYPRE_SStructGMRESSetMaxIter()	105
3.5.4.68 HYPRE_SStructGMRESSetMinIter()	105
3.5.4.69 HYPRE_SStructGMRESSetPrecond()	105
3.5.4.70 HYPRE_SStructGMRESSetPrintLevel()	105
3.5.4.71 HYPRE_SStructGMRESSetStopCrit()	105
3.5.4.72 HYPRE_SStructGMRESSetTol()	105
3.5.4.73 HYPRE_SStructGMRESSetup()	105
3.5.4.74 HYPRE_SStructGMRESSolve()	106
3.5.4.75 HYPRE_SStructLGMRESCreate()	106
3.5.4.76 HYPRE_SStructLGMRESDestroy()	106
3.5.4.77 HYPRE_SStructLGMRESGetFinalRelativeResidualNorm()	106
3.5.4.78 HYPRE_SStructLGMRESGetNumIterations()	106
3.5.4.79 HYPRE_SStructLGMRESGetResidual()	106
3.5.4.80 HYPRE_SStructLGMRESSetAbsoluteTol()	106
3.5.4.81 HYPRE_SStructLGMRESSetAugDim()	107
3.5.4.82 HYPRE_SStructLGMRESSetKDim()	107
3.5.4.83 HYPRE_SStructLGMRESSetLogging()	107
3.5.4.84 HYPRE_SStructLGMRESSetMaxIter()	107
3.5.4.85 HYPRE_SStructLGMRESSetMinIter()	107
3.5.4.86 HYPRE_SStructLGMRESSetPrecond()	107
3.5.4.87 HYPRE_SStructLGMRESSetPrintLevel()	107
3.5.4.88 HYPRE_SStructLGMRESSetTol()	108
3.5.4.89 HYPRE_SStructLGMRESSetup()	108
3.5.4.90 HYPRE_SStructLGMRESSolve()	108
3.5.4.91 HYPRE_SStructMaxwellCreate()	108
3.5.4.92 HYPRE_SStructMaxwellDestroy()	108
3.5.4.93 HYPRE_SStructMaxwellEliminateRowsCols()	108
3.5.4.94 HYPRE_SStructMaxwellGetFinalRelativeResidualNorm()	109
3.5.4.95 HYPRE_SStructMaxwellGetNumIterations()	109
3.5.4.96 HYPRE_SStructMaxwellGrad()	109
3.5.4.97 HYPRE_SStructMaxwellPhysBdy()	109

3.5.4.98 HYPRE_SStructMaxwellSetGrad()	109
3.5.4.99 HYPRE_SStructMaxwellSetLogging()	109
3.5.4.100 HYPRE_SStructMaxwellSetMaxIter()	110
3.5.4.101 HYPRE_SStructMaxwellSetNumPostRelax()	110
3.5.4.102 HYPRE_SStructMaxwellSetNumPreRelax()	110
3.5.4.103 HYPRE_SStructMaxwellSetRelChange()	110
3.5.4.104 HYPRE_SStructMaxwellSetRfactors()	110
3.5.4.105 HYPRE_SStructMaxwellSetSetConstantCoef()	110
3.5.4.106 HYPRE_SStructMaxwellSetTol()	111
3.5.4.107 HYPRE_SStructMaxwellSetup()	111
3.5.4.108 HYPRE_SStructMaxwellSolve()	111
3.5.4.109 HYPRE_SStructMaxwellSolve2()	111
3.5.4.110 HYPRE_SStructMaxwellZeroVector()	111
3.5.4.111 HYPRE_SStructPCGCreate()	112
3.5.4.112 HYPRE_SStructPCGDestroy()	112
3.5.4.113 HYPRE_SStructPCGGetFinalRelativeResidualNorm()	112
3.5.4.114 HYPRE_SStructPCGGetNumIterations()	112
3.5.4.115 HYPRE_SStructPCGGetResidual()	112
3.5.4.116 HYPRE_SStructPCGSetAbsoluteTol()	112
3.5.4.117 HYPRE_SStructPCGSetLogging()	112
3.5.4.118 HYPRE_SStructPCGSetMaxIter()	113
3.5.4.119 HYPRE_SStructPCGSetPrecond()	113
3.5.4.120 HYPRE_SStructPCGSetPrintLevel()	113
3.5.4.121 HYPRE_SStructPCGSetRelChange()	113
3.5.4.122 HYPRE_SStructPCGSetTol()	113
3.5.4.123 HYPRE_SStructPCGSetTwoNorm()	113
3.5.4.124 HYPRE_SStructPCGSetup()	113
3.5.4.125 HYPRE_SStructPCGSolve()	114
3.5.4.126 HYPRE_SStructSetupInterpreter()	114
3.5.4.127 HYPRE_SStructSetupMatvec()	114
3.5.4.128 HYPRE_SStructSplitCreate()	114
3.5.4.129 HYPRE_SStructSplitDestroy()	114
3.5.4.130 HYPRE_SStructSplitGetFinalRelativeResidualNorm()	114
3.5.4.131 HYPRE_SStructSplitGetNumIterations()	115
3.5.4.132 HYPRE_SStructSplitSetMaxIter()	115
3.5.4.133 HYPRE_SStructSplitSetNonZeroGuess()	115
3.5.4.134 HYPRE_SStructSplitSetStructSolver()	115
3.5.4.135 HYPRE_SStructSplitSetTol()	115
3.5.4.136 HYPRE_SStructSplitSetup()	115
3.5.4.137 HYPRE_SStructSplitSetZeroGuess()	116
3.5.4.138 HYPRE_SStructSplitSolve()	116
3.5.4.139 HYPRE_SStructSysPFMGCreate()	116

3.5.4.140 HYPRE_SStructSysPFMGDestroy()	116
3.5.4.141 HYPRE_SStructSysPFMGGetFinalRelativeResidualNorm()	116
3.5.4.142 HYPRE_SStructSysPFMGGetNumIterations()	116
3.5.4.143 HYPRE_SStructSysPFMGSetDxyz()	117
3.5.4.144 HYPRE_SStructSysPFMGSetJacobiWeight()	117
3.5.4.145 HYPRE_SStructSysPFMGSetLogging()	117
3.5.4.146 HYPRE_SStructSysPFMGSetMaxIter()	117
3.5.4.147 HYPRE_SStructSysPFMGSetNonZeroGuess()	117
3.5.4.148 HYPRE_SStructSysPFMGSetNumPostRelax()	117
3.5.4.149 HYPRE_SStructSysPFMGSetNumPreRelax()	118
3.5.4.150 HYPRE_SStructSysPFMGSetPrintLevel()	118
3.5.4.151 HYPRE_SStructSysPFMGSetRelaxType()	118
3.5.4.152 HYPRE_SStructSysPFMGSetRelChange()	118
3.5.4.153 HYPRE_SStructSysPFMGSetSkipRelax()	118
3.5.4.154 HYPRE_SStructSysPFMGSetTol()	119
3.5.4.155 HYPRE_SStructSysPFMGSetup()	119
3.5.4.156 HYPRE_SStructSysPFMGSetZeroGuess()	119
3.5.4.157 HYPRE_SStructSysPFMGsolve()	119
3.6 ParCSR Solvers	119
3.6.1 Detailed Description	134
3.6.2 Macro Definition Documentation	134
3.6.2.1 HYPRE_MODIFYPC	134
3.6.2.2 HYPRE_SOLVER_STRUCT	134
3.6.3 Typedef Documentation	134
3.6.3.1 HYPRE_PtrToModifyPCFcn	134
3.6.3.2 HYPRE_PtrToParSolverFcn	135
3.6.3.3 HYPRE_Solver	135
3.6.4 Function Documentation	135
3.6.4.1 GenerateCoordinates()	135
3.6.4.2 GenerateDifConv()	135
3.6.4.3 GenerateLaplacian()	135
3.6.4.4 GenerateLaplacian27pt()	136
3.6.4.5 GenerateLaplacian9pt()	136
3.6.4.6 GenerateRotate7pt()	136
3.6.4.7 GenerateRSVarDifConv()	136
3.6.4.8 GenerateVarDifConv()	137
3.6.4.9 HYPRE_ADSCreate()	137
3.6.4.10 HYPRE_ADSDestroy()	137
3.6.4.11 HYPRE_ADGetFinalRelativeResidualNorm()	137
3.6.4.12 HYPRE_ADGetNumIterations()	137
3.6.4.13 HYPRE_ADSSetAMGOptions()	138
3.6.4.14 HYPRE_ADSSetAMSOptions()	138



3.6.4.15 HYPRE_ADSSetChebySmoothingOptions()	138
3.6.4.16 HYPRE_ADSSetCoordinateVectors()	138
3.6.4.17 HYPRE_ADSSetCycleType()	139
3.6.4.18 HYPRE_ADSSetDiscreteCurl()	139
3.6.4.19 HYPRE_ADSSetDiscreteGradient()	139
3.6.4.20 HYPRE_ADSSetInterpolations()	140
3.6.4.21 HYPRE_ADSSetMaxIter()	140
3.6.4.22 HYPRE_ADSSetPrintLevel()	140
3.6.4.23 HYPRE_ADSSetSmoothingOptions()	141
3.6.4.24 HYPRE_ADSSetTol()	141
3.6.4.25 HYPRE_ADSSetup()	141
3.6.4.26 HYPRE_ADSSolve()	142
3.6.4.27 HYPRE_AMSConstructDiscreteGradient()	142
3.6.4.28 HYPRE_AMSCreate()	142
3.6.4.29 HYPRE_AMSDestroy()	142
3.6.4.30 HYPRE_AMSGetFinalRelativeResidualNorm()	143
3.6.4.31 HYPRE_AMSGetNumIterations()	143
3.6.4.32 HYPRE_AMSProjectOutGradients()	143
3.6.4.33 HYPRE_AMSSetAlphaAMGCoarseRelaxType()	143
3.6.4.34 HYPRE_AMSSetAlphaAMGOptions()	143
3.6.4.35 HYPRE_AMSSetAlphaPoissonMatrix()	144
3.6.4.36 HYPRE_AMSSetBetaAMGCoarseRelaxType()	144
3.6.4.37 HYPRE_AMSSetBetaAMGOptions()	144
3.6.4.38 HYPRE_AMSSetBetaPoissonMatrix()	144
3.6.4.39 HYPRE_AMSSetCoordinateVectors()	145
3.6.4.40 HYPRE_AMSSetCycleType()	145
3.6.4.41 HYPRE_AMSSetDimension()	145
3.6.4.42 HYPRE_AMSSetDiscreteGradient()	146
3.6.4.43 HYPRE_AMSSetEdgeConstantVectors()	146
3.6.4.44 HYPRE_AMSSetInteriorNodes()	146
3.6.4.45 HYPRE_AMSSetInterpolations()	146
3.6.4.46 HYPRE_AMSSetMaxIter()	147
3.6.4.47 HYPRE_AMSSetPrintLevel()	147
3.6.4.48 HYPRE_AMSSetProjectionFrequency()	147
3.6.4.49 HYPRE_AMSSetSmoothingOptions()	147
3.6.4.50 HYPRE_AMSSetTol()	148
3.6.4.51 HYPRE_AMSSetup()	148
3.6.4.52 HYPRE_AMSSolve()	148
3.6.4.53 HYPRE_BoomerAMGCreate()	148
3.6.4.54 HYPRE_BoomerAMGDDCreate()	149
3.6.4.55 HYPRE_BoomerAMGDDDestroy()	149
3.6.4.56 HYPRE_BoomerAMGDDGetAMG()	149

3.6.4.57 HYPRE_BoomerAMGDDGetFinalRelativeResidualNorm()	149
3.6.4.58 HYPRE_BoomerAMGDDGetNumIterations()	149
3.6.4.59 HYPRE_BoomerAMGDDSetFACCycleType()	149
3.6.4.60 HYPRE_BoomerAMGDDSetFACNumCycles()	150
3.6.4.61 HYPRE_BoomerAMGDDSetFACNumRelax()	150
3.6.4.62 HYPRE_BoomerAMGDDSetFACRelaxType()	150
3.6.4.63 HYPRE_BoomerAMGDDSetFACRelaxWeight()	150
3.6.4.64 HYPRE_BoomerAMGDDSetNumGhostLayers()	150
3.6.4.65 HYPRE_BoomerAMGDDSetPadding()	150
3.6.4.66 HYPRE_BoomerAMGDDSetStartLevel()	151
3.6.4.67 HYPRE_BoomerAMGDDSetup()	151
3.6.4.68 HYPRE_BoomerAMGDDSetUserFACRelaxation()	151
3.6.4.69 HYPRE_BoomerAMGDDsolve()	151
3.6.4.70 HYPRE_BoomerAMGDestroy()	152
3.6.4.71 HYPRE_BoomerAMGGetFinalRelativeResidualNorm()	152
3.6.4.72 HYPRE_BoomerAMGGetGridHierarchy()	152
3.6.4.73 HYPRE_BoomerAMGGetNumIterations()	152
3.6.4.74 HYPRE_BoomerAMGGetResidual()	153
3.6.4.75 HYPRE_BoomerAMGInitGridRelaxation()	153
3.6.4.76 HYPRE_BoomerAMGSetAdditive()	153
3.6.4.77 HYPRE_BoomerAMGSetAddLastLvl()	153
3.6.4.78 HYPRE_BoomerAMGSetAddRelaxType()	153
3.6.4.79 HYPRE_BoomerAMGSetAddRelaxWt()	154
3.6.4.80 HYPRE_BoomerAMGSetADropTol()	154
3.6.4.81 HYPRE_BoomerAMGSetADropType()	154
3.6.4.82 HYPRE_BoomerAMGSetAggInterpType()	154
3.6.4.83 HYPRE_BoomerAMGSetAggNumLevels()	155
3.6.4.84 HYPRE_BoomerAMGSetAggP12MaxElmts()	155
3.6.4.85 HYPRE_BoomerAMGSetAggP12TruncFactor()	155
3.6.4.86 HYPRE_BoomerAMGSetAggPMaxElmts()	155
3.6.4.87 HYPRE_BoomerAMGSetAggTruncFactor()	155
3.6.4.88 HYPRE_BoomerAMGSetCGCIts()	155
3.6.4.89 HYPRE_BoomerAMGSetChebyEigEst()	156
3.6.4.90 HYPRE_BoomerAMGSetChebyFraction()	156
3.6.4.91 HYPRE_BoomerAMGSetChebyOrder()	156
3.6.4.92 HYPRE_BoomerAMGSetChebyScale()	156
3.6.4.93 HYPRE_BoomerAMGSetChebyVariant()	156
3.6.4.94 HYPRE_BoomerAMGSetCoarsenCutFactor()	156
3.6.4.95 HYPRE_BoomerAMGSetCoarsenType()	157
3.6.4.96 HYPRE_BoomerAMGSetConvergeType()	157
3.6.4.97 HYPRE_BoomerAMGSetCoordDim()	157
3.6.4.98 HYPRE_BoomerAMGSetCoordinates()	158

3.6.4.99 HYPRE_BoomerAMGSetCPoints()	158
3.6.4.100 HYPRE_BoomerAMGSetCpointsToKeep()	158
3.6.4.101 HYPRE_BoomerAMGSetCRRate()	158
3.6.4.102 HYPRE_BoomerAMGSetCRStrongTh()	158
3.6.4.103 HYPRE_BoomerAMGSetCRUseCG()	159
3.6.4.104 HYPRE_BoomerAMGSetCycleNumSweeps()	159
3.6.4.105 HYPRE_BoomerAMGSetCycleRelaxType()	159
3.6.4.106 HYPRE_BoomerAMGSetCycleType()	159
3.6.4.107 HYPRE_BoomerAMGSetDebugFlag()	160
3.6.4.108 HYPRE_BoomerAMGSetDofFunc()	160
3.6.4.109 HYPRE_BoomerAMGSetDomainType()	160
3.6.4.110 HYPRE_BoomerAMGSetDropTol()	160
3.6.4.111 HYPRE_BoomerAMGSetEuBJ()	160
3.6.4.112 HYPRE_BoomerAMGSetEuclidFile()	161
3.6.4.113 HYPRE_BoomerAMGSetEuLevel()	161
3.6.4.114 HYPRE_BoomerAMGSetEuSparseA()	161
3.6.4.115 HYPRE_BoomerAMGSetFCycle()	161
3.6.4.116 HYPRE_BoomerAMGSetFilter()	161
3.6.4.117 HYPRE_BoomerAMGSetFilterThresholdR()	161
3.6.4.118 HYPRE_BoomerAMGSetFPoints()	161
3.6.4.119 HYPRE_BoomerAMGSetGMRESSwitchR()	162
3.6.4.120 HYPRE_BoomerAMGSetGridRelaxPoints()	162
3.6.4.121 HYPRE_BoomerAMGSetGridRelaxType()	162
3.6.4.122 HYPRE_BoomerAMGSetGSMG()	162
3.6.4.123 HYPRE_BoomerAMGSetILUDroptol()	163
3.6.4.124 HYPRE_BoomerAMGSetILULevel()	163
3.6.4.125 HYPRE_BoomerAMGSetILUMaxIter()	163
3.6.4.126 HYPRE_BoomerAMGSetILUMaxRowNnz()	163
3.6.4.127 HYPRE_BoomerAMGSetILUType()	163
3.6.4.128 HYPRE_BoomerAMGSetInterpType()	164
3.6.4.129 HYPRE_BoomerAMGSetInterpVecAbsQTrunc()	164
3.6.4.130 HYPRE_BoomerAMGSetInterpVecQMax()	165
3.6.4.131 HYPRE_BoomerAMGSetInterpVectors()	165
3.6.4.132 HYPRE_BoomerAMGSetInterpVecVariant()	165
3.6.4.133 HYPRE_BoomerAMGSetIsolatedFPoints()	165
3.6.4.134 HYPRE_BoomerAMGSetIsTriangular()	166
3.6.4.135 HYPRE_BoomerAMGSetIStype()	166
3.6.4.136 HYPRE_BoomerAMGSetJacobiTruncThreshold()	166
3.6.4.137 HYPRE_BoomerAMGSetKeepSameSign()	166
3.6.4.138 HYPRE_BoomerAMGSetKeepTranspose()	166
3.6.4.139 HYPRE_BoomerAMGSetLevel()	166
3.6.4.140 HYPRE_BoomerAMGSetLevelNonGalerkinTol()	167

3.6.4.141 HYPRE_BoomerAMGSetLevelOuterWt()	167
3.6.4.142 HYPRE_BoomerAMGSetLevelRelaxWt()	167
3.6.4.143 HYPRE_BoomerAMGSetLogging()	168
3.6.4.144 HYPRE_BoomerAMGSetMaxCoarseSize()	168
3.6.4.145 HYPRE_BoomerAMGSetMaxIter()	168
3.6.4.146 HYPRE_BoomerAMGSetMaxLevels()	168
3.6.4.147 HYPRE_BoomerAMGSetMaxNzPerRow()	168
3.6.4.148 HYPRE_BoomerAMGSetMaxRowSum()	168
3.6.4.149 HYPRE_BoomerAMGSetMeasureType()	169
3.6.4.150 HYPRE_BoomerAMGSetMinCoarseSize()	169
3.6.4.151 HYPRE_BoomerAMGSetMinIter()	169
3.6.4.152 HYPRE_BoomerAMGSetModuleRAP2()	169
3.6.4.153 HYPRE_BoomerAMGSetMultAdditive()	169
3.6.4.154 HYPRE_BoomerAMGSetMultAddPMaxElmts()	169
3.6.4.155 HYPRE_BoomerAMGSetMultAddTruncFactor()	170
3.6.4.156 HYPRE_BoomerAMGSetNodal()	170
3.6.4.157 HYPRE_BoomerAMGSetNodalDiag()	170
3.6.4.158 HYPRE_BoomerAMGSetNonGalerkinTol()	170
3.6.4.159 HYPRE_BoomerAMGSetNonGalerkTol()	171
3.6.4.160 HYPRE_BoomerAMGSetNumCRRRelaxSteps()	171
3.6.4.161 HYPRE_BoomerAMGSetNumFunctions()	171
3.6.4.162 HYPRE_BoomerAMGSetNumGridSweeps()	171
3.6.4.163 HYPRE_BoomerAMGSetNumPaths()	171
3.6.4.164 HYPRE_BoomerAMGSetNumSamples()	171
3.6.4.165 HYPRE_BoomerAMGSetNumSweeps()	172
3.6.4.166 HYPRE_BoomerAMGSetOldDefault()	172
3.6.4.167 HYPRE_BoomerAMGSetOmega()	172
3.6.4.168 HYPRE_BoomerAMGSetOuterWt()	172
3.6.4.169 HYPRE_BoomerAMGSetOverlap()	172
3.6.4.170 HYPRE_BoomerAMGSetPlotFileName()	173
3.6.4.171 HYPRE_BoomerAMGSetPlotGrids()	173
3.6.4.172 HYPRE_BoomerAMGSetPMaxElmts()	173
3.6.4.173 HYPRE_BoomerAMGSetPostInterpType()	173
3.6.4.174 HYPRE_BoomerAMGSetPrintFileName()	173
3.6.4.175 HYPRE_BoomerAMGSetPrintLevel()	173
3.6.4.176 HYPRE_BoomerAMGSetRAP2()	174
3.6.4.177 HYPRE_BoomerAMGSetRedundant()	174
3.6.4.178 HYPRE_BoomerAMGSetRelaxOrder()	174
3.6.4.179 HYPRE_BoomerAMGSetRelaxType()	174
3.6.4.180 HYPRE_BoomerAMGSetRelaxWeight()	175
3.6.4.181 HYPRE_BoomerAMGSetRelaxWt()	175
3.6.4.182 HYPRE_BoomerAMGSetRestriction()	176

3.6.4.183 HYPRE_BoomerAMGSetSabs()	176
3.6.4.184 HYPRE_BoomerAMGSetSchwarzRlxWeight()	176
3.6.4.185 HYPRE_BoomerAMGSetSchwarzUseNonSymm()	176
3.6.4.186 HYPRE_BoomerAMGSetSCommPkgSwitch()	177
3.6.4.187 HYPRE_BoomerAMGSetSepWeight()	177
3.6.4.188 HYPRE_BoomerAMGSetSeqThreshold()	177
3.6.4.189 HYPRE_BoomerAMGSetSimple()	177
3.6.4.190 HYPRE_BoomerAMGSetSmoothNumLevels()	177
3.6.4.191 HYPRE_BoomerAMGSetSmoothNumSweeps()	178
3.6.4.192 HYPRE_BoomerAMGSetSmoothType()	178
3.6.4.193 HYPRE_BoomerAMGSetStrongThreshold()	178
3.6.4.194 HYPRE_BoomerAMGSetStrongThresholdR()	178
3.6.4.195 HYPRE_BoomerAMGSetSym()	179
3.6.4.196 HYPRE_BoomerAMGSetThreshold()	179
3.6.4.197 HYPRE_BoomerAMGSetTol()	179
3.6.4.198 HYPRE_BoomerAMGSetTruncFactor()	179
3.6.4.199 HYPRE_BoomerAMGSetup()	179
3.6.4.200 HYPRE_BoomerAMGSetVariant()	180
3.6.4.201 HYPRE_BoomerAMGSolve()	180
3.6.4.202 HYPRE_BoomerAMGSolveT()	180
3.6.4.203 HYPRE_EuclidCreate()	181
3.6.4.204 HYPRE_EuclidDestroy()	181
3.6.4.205 HYPRE_EuclidSetBJ()	181
3.6.4.206 HYPRE_EuclidSetILUT()	181
3.6.4.207 HYPRE_EuclidSetLevel()	181
3.6.4.208 HYPRE_EuclidSetMem()	182
3.6.4.209 HYPRE_EuclidSetParams()	182
3.6.4.210 HYPRE_EuclidSetParamsFromFile()	182
3.6.4.211 HYPRE_EuclidSetRowScale()	182
3.6.4.212 HYPRE_EuclidSetSparseA()	183
3.6.4.213 HYPRE_EuclidSetStats()	183
3.6.4.214 HYPRE_EuclidSetup()	183
3.6.4.215 HYPRE_EuclidSolve()	183
3.6.4.216 HYPRE_ILUCreate()	184
3.6.4.217 HYPRE_ILUDestroy()	184
3.6.4.218 HYPRE_ILUGetFinalRelativeResidualNorm()	184
3.6.4.219 HYPRE_ILUGetNumIterations()	184
3.6.4.220 HYPRE_ILUSetDropThreshold()	184
3.6.4.221 HYPRE_ILUSetDropThresholdArray()	185
3.6.4.222 HYPRE_ILUSetLevelOfFill()	185
3.6.4.223 HYPRE_ILUSetLocalReordering()	185
3.6.4.224 HYPRE_ILUSetLogging()	185

3.6.4.225 HYPRE_ILUSetMaxIter()	186
3.6.4.226 HYPRE_ILUSetMaxNnzPerRow()	186
3.6.4.227 HYPRE_ILUSetNSHDropThreshold()	186
3.6.4.228 HYPRE_ILUSetNSHDropThresholdArray()	186
3.6.4.229 HYPRE_ILUSetPrintLevel()	186
3.6.4.230 HYPRE_ILUSetSchurMaxIter()	187
3.6.4.231 HYPRE_ILUSetTol()	187
3.6.4.232 HYPRE_ILUSetType()	187
3.6.4.233 HYPRE_ILUSetup()	187
3.6.4.234 HYPRE_ILUSolve()	188
3.6.4.235 HYPRE_MGRBuildAff()	188
3.6.4.236 HYPRE_MGRCreate()	188
3.6.4.237 HYPRE_MGRDestroy()	188
3.6.4.238 HYPRE_MGRGetCoarseGridConvergenceFactor()	189
3.6.4.239 HYPRE_MGRGetFinalRelativeResidualNorm()	189
3.6.4.240 HYPRE_MGRGetNumIterations()	189
3.6.4.241 HYPRE_MGRSetBlockSize()	189
3.6.4.242 HYPRE_MGRSetCoarseGridMethod()	189
3.6.4.243 HYPRE_MGRSetCoarseGridPrintLevel()	189
3.6.4.244 HYPRE_MGRSetCoarseSolver()	190
3.6.4.245 HYPRE_MGRSetCpointsByBlock()	191
3.6.4.246 HYPRE_MGRSetCpointsByContiguousBlock()	191
3.6.4.247 HYPRE_MGRSetCpointsByPointMarkerArray()	192
3.6.4.248 HYPRE_MGRSetFRelaxMethod()	192
3.6.4.249 HYPRE_MGRSetFRelaxPrintLevel()	192
3.6.4.250 HYPRE_MGRSetFSolver()	192
3.6.4.251 HYPRE_MGRSetGlobalSmoothType()	193
3.6.4.252 HYPRE_MGRSetInterpType()	193
3.6.4.253 HYPRE_MGRSetLevelFRelaxMethod()	193
3.6.4.254 HYPRE_MGRSetLevelFRelaxNumFunctions()	194
3.6.4.255 HYPRE_MGRSetLevelInterpType()	194
3.6.4.256 HYPRE_MGRSetLevelRestrictType()	194
3.6.4.257 HYPRE_MGRSetLogging()	194
3.6.4.258 HYPRE_MGRSetMaxCoarseLevels()	194
3.6.4.259 HYPRE_MGRSetMaxGlobalSmoothIters()	194
3.6.4.260 HYPRE_MGRSetMaxIter()	195
3.6.4.261 HYPRE_MGRSetNonCpointsToFpoints()	195
3.6.4.262 HYPRE_MGRSetNumInterpSweeps()	195
3.6.4.263 HYPRE_MGRSetNumRelaxSweeps()	195
3.6.4.264 HYPRE_MGRSetNumRestrictSweeps()	195
3.6.4.265 HYPRE_MGRSetPMaxElmts()	196
3.6.4.266 HYPRE_MGRSetPrintLevel()	196

3.6.4.267 HYPRE_MGRSetRelaxType()	196
3.6.4.268 HYPRE_MGRSetReservedCoarseNodes()	196
3.6.4.269 HYPRE_MGRSetReservedCpointsLevelToKeep()	197
3.6.4.270 HYPRE_MGRSetRestrictType()	197
3.6.4.271 HYPRE_MGRSetTol()	197
3.6.4.272 HYPRE_MGRSetTruncateCoarseGridThreshold()	197
3.6.4.273 HYPRE_MGRSetup()	197
3.6.4.274 HYPRE_MGRSolve()	198
3.6.4.275 HYPRE_ParaSailsBuildIJMatrix()	198
3.6.4.276 HYPRE_ParaSailsCreate()	198
3.6.4.277 HYPRE_ParaSailsDestroy()	199
3.6.4.278 HYPRE_ParaSailsSetFilter()	199
3.6.4.279 HYPRE_ParaSailsSetLoadbal()	199
3.6.4.280 HYPRE_ParaSailsSetLogging()	199
3.6.4.281 HYPRE_ParaSailsSetParams()	200
3.6.4.282 HYPRE_ParaSailsSetReuse()	200
3.6.4.283 HYPRE_ParaSailsSetSym()	200
3.6.4.284 HYPRE_ParaSailsSetup()	201
3.6.4.285 HYPRE_ParaSailsSolve()	201
3.6.4.286 HYPRE_ParCSRBiCGSTABCreate()	201
3.6.4.287 HYPRE_ParCSRBiCGSTABDestroy()	202
3.6.4.288 HYPRE_ParCSRBiCGSTABGetFinalRelativeResidualNorm()	202
3.6.4.289 HYPRE_ParCSRBiCGSTABGetNumIterations()	202
3.6.4.290 HYPRE_ParCSRBiCGSTABGetPrecond()	202
3.6.4.291 HYPRE_ParCSRBiCGSTABGetResidual()	202
3.6.4.292 HYPRE_ParCSRBiCGSTABSetAbsoluteTol()	202
3.6.4.293 HYPRE_ParCSRBiCGSTABSetLogging()	202
3.6.4.294 HYPRE_ParCSRBiCGSTABSetMaxIter()	203
3.6.4.295 HYPRE_ParCSRBiCGSTABSetMinIter()	203
3.6.4.296 HYPRE_ParCSRBiCGSTABSetPrecond()	203
3.6.4.297 HYPRE_ParCSRBiCGSTABSetPrintLevel()	203
3.6.4.298 HYPRE_ParCSRBiCGSTABSetStopCrit()	203
3.6.4.299 HYPRE_ParCSRBiCGSTABSetTol()	203
3.6.4.300 HYPRE_ParCSRBiCGSTABSetup()	203
3.6.4.301 HYPRE_ParCSRBiCGSTABSolve()	204
3.6.4.302 HYPRE_ParCSRCGNRCreate()	204
3.6.4.303 HYPRE_ParCSRCGNRDestroy()	204
3.6.4.304 HYPRE_ParCSRCGNRGetFinalRelativeResidualNorm()	204
3.6.4.305 HYPRE_ParCSRCGNRGetNumIterations()	204
3.6.4.306 HYPRE_ParCSRCGNRGetPrecond()	204
3.6.4.307 HYPRE_ParCSRCGNRSetLogging()	204
3.6.4.308 HYPRE_ParCSRCGNRSetMaxIter()	205

3.6.4.309 HYPRE_ParCSRCONRSetMinIter()	205
3.6.4.310 HYPRE_ParCSRCONRSetPrecond()	205
3.6.4.311 HYPRE_ParCSRCONRSetStopCrit()	205
3.6.4.312 HYPRE_ParCSRCONRSetTol()	205
3.6.4.313 HYPRE_ParCSRCONRSetup()	205
3.6.4.314 HYPRE_ParCSRCONRSolve()	205
3.6.4.315 HYPRE_ParCSRCONMRESCreate()	206
3.6.4.316 HYPRE_ParCSRCONMRESDestroy()	206
3.6.4.317 HYPRE_ParCSRCONMRESGetFinalRelativeResidualNorm()	206
3.6.4.318 HYPRE_ParCSRCONMRESGetNumIterations()	206
3.6.4.319 HYPRE_ParCSRCONMRESGetPrecond()	206
3.6.4.320 HYPRE_ParCSRCONMRESGetResidual()	206
3.6.4.321 HYPRE_ParCSRCONMRESSetAbsoluteTol()	206
3.6.4.322 HYPRE_ParCSRCONMRESSetCGS()	207
3.6.4.323 HYPRE_ParCSRCONMRESSetKDim()	207
3.6.4.324 HYPRE_ParCSRCONMRESSetLogging()	207
3.6.4.325 HYPRE_ParCSRCONMRESSetMaxIter()	207
3.6.4.326 HYPRE_ParCSRCONMRESSetMinIter()	207
3.6.4.327 HYPRE_ParCSRCONMRESSetPrecond()	207
3.6.4.328 HYPRE_ParCSRCONMRESSetPrintLevel()	207
3.6.4.329 HYPRE_ParCSRCONMRESSetTol()	208
3.6.4.330 HYPRE_ParCSRCONMRESSetUnroll()	208
3.6.4.331 HYPRE_ParCSRCONMRESSetup()	208
3.6.4.332 HYPRE_ParCSRCONMRESolve()	208
3.6.4.333 HYPRE_ParCSRDiagScale()	208
3.6.4.334 HYPRE_ParCSRDiagScaleSetup()	208
3.6.4.335 HYPRE_ParCSRFlexGMRESCreate()	209
3.6.4.336 HYPRE_ParCSRFlexGMRESDestroy()	209
3.6.4.337 HYPRE_ParCSRFlexGMRESGetFinalRelativeResidualNorm()	209
3.6.4.338 HYPRE_ParCSRFlexGMRESGetNumIterations()	209
3.6.4.339 HYPRE_ParCSRFlexGMRESGetPrecond()	209
3.6.4.340 HYPRE_ParCSRFlexGMRESGetResidual()	209
3.6.4.341 HYPRE_ParCSRFlexGMRESSetAbsoluteTol()	209
3.6.4.342 HYPRE_ParCSRFlexGMRESSetKDim()	210
3.6.4.343 HYPRE_ParCSRFlexGMRESSetLogging()	210
3.6.4.344 HYPRE_ParCSRFlexGMRESSetMaxIter()	210
3.6.4.345 HYPRE_ParCSRFlexGMRESSetMinIter()	210
3.6.4.346 HYPRE_ParCSRFlexGMRESSetModifyPC()	210
3.6.4.347 HYPRE_ParCSRFlexGMRESSetPrecond()	210
3.6.4.348 HYPRE_ParCSRFlexGMRESSetPrintLevel()	210
3.6.4.349 HYPRE_ParCSRFlexGMRESSetTol()	211
3.6.4.350 HYPRE_ParCSRFlexGMRESSetup()	211



3.6.4.351 HYPRE_ParCSRFlexGMRESSolve()	211
3.6.4.352 HYPRE_ParCSRGMRESCreate()	211
3.6.4.353 HYPRE_ParCSRGMRESDestroy()	211
3.6.4.354 HYPRE_ParCSRGMRESGetFinalRelativeResidualNorm()	211
3.6.4.355 HYPRE_ParCSRGMRESGetNumIterations()	211
3.6.4.356 HYPRE_ParCSRGMRESGetPrecond()	212
3.6.4.357 HYPRE_ParCSRGMRESGetResidual()	212
3.6.4.358 HYPRE_ParCSRGMRESSetAbsoluteTol()	212
3.6.4.359 HYPRE_ParCSRGMRESSetKDim()	212
3.6.4.360 HYPRE_ParCSRGMRESSetLogging()	212
3.6.4.361 HYPRE_ParCSRGMRESSetMaxIter()	212
3.6.4.362 HYPRE_ParCSRGMRESSetMinIter()	212
3.6.4.363 HYPRE_ParCSRGMRESSetPrecond()	213
3.6.4.364 HYPRE_ParCSRGMRESSetPrintLevel()	213
3.6.4.365 HYPRE_ParCSRGMRESSetStopCrit()	213
3.6.4.366 HYPRE_ParCSRGMRESSetTol()	213
3.6.4.367 HYPRE_ParCSRGMRESSetup()	213
3.6.4.368 HYPRE_ParCSRGMRESSolve()	213
3.6.4.369 HYPRE_ParCSRHybridCreate()	213
3.6.4.370 HYPRE_ParCSRHybridDestroy()	214
3.6.4.371 HYPRE_ParCSRHybridGetDSCGNumIterations()	214
3.6.4.372 HYPRE_ParCSRHybridGetFinalRelativeResidualNorm()	214
3.6.4.373 HYPRE_ParCSRHybridGetNumIterations()	214
3.6.4.374 HYPRE_ParCSRHybridGetPCGNumIterations()	214
3.6.4.375 HYPRE_ParCSRHybridGetRecomputeResidual()	214
3.6.4.376 HYPRE_ParCSRHybridGetRecomputeResidualP()	215
3.6.4.377 HYPRE_ParCSRHybridGetSetupSolveTime()	215
3.6.4.378 HYPRE_ParCSRHybridSetAbsoluteTol()	215
3.6.4.379 HYPRE_ParCSRHybridSetAggInterpType()	215
3.6.4.380 HYPRE_ParCSRHybridSetAggNumLevels()	215
3.6.4.381 HYPRE_ParCSRHybridSetCoarsenType()	216
3.6.4.382 HYPRE_ParCSRHybridSetConvergenceTol()	216
3.6.4.383 HYPRE_ParCSRHybridSetCycleNumSweeps()	216
3.6.4.384 HYPRE_ParCSRHybridSetCycleRelaxType()	217
3.6.4.385 HYPRE_ParCSRHybridSetCycleType()	217
3.6.4.386 HYPRE_ParCSRHybridSetDofFunc()	217
3.6.4.387 HYPRE_ParCSRHybridSetDSCGMaxIter()	217
3.6.4.388 HYPRE_ParCSRHybridSetGridRelaxPoints()	217
3.6.4.389 HYPRE_ParCSRHybridSetGridRelaxType()	218
3.6.4.390 HYPRE_ParCSRHybridSetInterpType()	218
3.6.4.391 HYPRE_ParCSRHybridSetKDim()	218
3.6.4.392 HYPRE_ParCSRHybridSetKeepTranspose()	218

3.6.4.393 HYPRE_ParCSRHybridSetLevelOuterWt()	218
3.6.4.394 HYPRE_ParCSRHybridSetLevelRelaxWt()	218
3.6.4.395 HYPRE_ParCSRHybridSetLogging()	219
3.6.4.396 HYPRE_ParCSRHybridSetMaxCoarseSize()	219
3.6.4.397 HYPRE_ParCSRHybridSetMaxLevels()	219
3.6.4.398 HYPRE_ParCSRHybridSetMaxRowSum()	219
3.6.4.399 HYPRE_ParCSRHybridSetMeasureType()	219
3.6.4.400 HYPRE_ParCSRHybridSetMinCoarseSize()	219
3.6.4.401 HYPRE_ParCSRHybridSetNodal()	220
3.6.4.402 HYPRE_ParCSRHybridSetNonGalerkinTol()	220
3.6.4.403 HYPRE_ParCSRHybridSetNumFunctions()	220
3.6.4.404 HYPRE_ParCSRHybridSetNumGridSweeps()	220
3.6.4.405 HYPRE_ParCSRHybridSetNumPaths()	220
3.6.4.406 HYPRE_ParCSRHybridSetNumSweeps()	220
3.6.4.407 HYPRE_ParCSRHybridSetOmega()	221
3.6.4.408 HYPRE_ParCSRHybridSetOuterWt()	221
3.6.4.409 HYPRE_ParCSRHybridSetPCGMaxIter()	221
3.6.4.410 HYPRE_ParCSRHybridSetPMaxElmts()	221
3.6.4.411 HYPRE_ParCSRHybridSetPrecond()	221
3.6.4.412 HYPRE_ParCSRHybridSetPrintLevel()	222
3.6.4.413 HYPRE_ParCSRHybridSetRecomputeResidual()	222
3.6.4.414 HYPRE_ParCSRHybridSetRecomputeResidualP()	222
3.6.4.415 HYPRE_ParCSRHybridSetRelaxOrder()	222
3.6.4.416 HYPRE_ParCSRHybridSetRelaxType()	223
3.6.4.417 HYPRE_ParCSRHybridSetRelaxWeight()	223
3.6.4.418 HYPRE_ParCSRHybridSetRelaxWt()	223
3.6.4.419 HYPRE_ParCSRHybridSetRelChange()	224
3.6.4.420 HYPRE_ParCSRHybridSetSeqThreshold()	224
3.6.4.421 HYPRE_ParCSRHybridSetSetupType()	224
3.6.4.422 HYPRE_ParCSRHybridSetSolverType()	224
3.6.4.423 HYPRE_ParCSRHybridSetStopCrit()	224
3.6.4.424 HYPRE_ParCSRHybridSetStrongThreshold()	224
3.6.4.425 HYPRE_ParCSRHybridSetTol()	225
3.6.4.426 HYPRE_ParCSRHybridSetTruncFactor()	225
3.6.4.427 HYPRE_ParCSRHybridSetTwoNorm()	225
3.6.4.428 HYPRE_ParCSRHybridSetup()	225
3.6.4.429 HYPRE_ParCSRHybridSolve()	225
3.6.4.430 HYPRE_ParCSRLGMRESCreate()	227
3.6.4.431 HYPRE_ParCSRLGMRESDestroy()	227
3.6.4.432 HYPRE_ParCSRLGMRESGetFinalRelativeResidualNorm()	227
3.6.4.433 HYPRE_ParCSRLGMRESGetNumIterations()	227
3.6.4.434 HYPRE_ParCSRLGMRESGetPrecond()	227

3.6.4.435 HYPRE_ParCSRLGMRESGetResidual()	227
3.6.4.436 HYPRE_ParCSRLGMRESSetAbsoluteTol()	228
3.6.4.437 HYPRE_ParCSRLGMRESSetAugDim()	228
3.6.4.438 HYPRE_ParCSRLGMRESSetKDim()	228
3.6.4.439 HYPRE_ParCSRLGMRESSetLogging()	228
3.6.4.440 HYPRE_ParCSRLGMRESSetMaxIter()	228
3.6.4.441 HYPRE_ParCSRLGMRESSetMinIter()	228
3.6.4.442 HYPRE_ParCSRLGMRESSetPrecond()	228
3.6.4.443 HYPRE_ParCSRLGMRESSetPrintLevel()	229
3.6.4.444 HYPRE_ParCSRLGMRESSetTol()	229
3.6.4.445 HYPRE_ParCSRLGMRESSetup()	229
3.6.4.446 HYPRE_ParCSRLGMRESSolve()	229
3.6.4.447 HYPRE_ParCSRMultiVectorPrint()	229
3.6.4.448 HYPRE_ParCSRMultiVectorRead()	229
3.6.4.449 HYPRE_ParCSROnProcTriSetup()	229
3.6.4.450 HYPRE_ParCSROnProcTriSolve()	230
3.6.4.451 HYPRE_ParCSRParaSailsCreate()	230
3.6.4.452 HYPRE_ParCSRParaSailsDestroy()	230
3.6.4.453 HYPRE_ParCSRParaSailsSetFilter()	230
3.6.4.454 HYPRE_ParCSRParaSailsSetLoadbal()	230
3.6.4.455 HYPRE_ParCSRParaSailsSetLogging()	230
3.6.4.456 HYPRE_ParCSRParaSailsSetParams()	230
3.6.4.457 HYPRE_ParCSRParaSailsSetReuse()	231
3.6.4.458 HYPRE_ParCSRParaSailsSetSym()	231
3.6.4.459 HYPRE_ParCSRParaSailsSetup()	231
3.6.4.460 HYPRE_ParCSRParaSailsSolve()	231
3.6.4.461 HYPRE_ParCSRPCGCreate()	231
3.6.4.462 HYPRE_ParCSRPCGDestroy()	231
3.6.4.463 HYPRE_ParCSRPCGGetFinalRelativeResidualNorm()	231
3.6.4.464 HYPRE_ParCSRPCGGetNumIterations()	232
3.6.4.465 HYPRE_ParCSRPCGGetPrecond()	232
3.6.4.466 HYPRE_ParCSRPCGGetResidual()	232
3.6.4.467 HYPRE_ParCSRPCGSetAbsoluteTol()	232
3.6.4.468 HYPRE_ParCSRPCGSetLogging()	232
3.6.4.469 HYPRE_ParCSRPCGSetMaxIter()	232
3.6.4.470 HYPRE_ParCSRPCGSetPrecond()	232
3.6.4.471 HYPRE_ParCSRPCGSetPrintLevel()	233
3.6.4.472 HYPRE_ParCSRPCGSetRelChange()	233
3.6.4.473 HYPRE_ParCSRPCGSetStopCrit()	233
3.6.4.474 HYPRE_ParCSRPCGSetTol()	233
3.6.4.475 HYPRE_ParCSRPCGSetTwoNorm()	233
3.6.4.476 HYPRE_ParCSRPCGSetup()	233

3.6.4.477 HYPRE_ParCSRPCGSolve()	233
3.6.4.478 HYPRE_ParCSRPilutCreate()	234
3.6.4.479 HYPRE_ParCSRPilutDestroy()	234
3.6.4.480 HYPRE_ParCSRPilutSetDropTolerance()	234
3.6.4.481 HYPRE_ParCSRPilutSetFactorRowSize()	234
3.6.4.482 HYPRE_ParCSRPilutSetLogging()	234
3.6.4.483 HYPRE_ParCSRPilutSetMaxIter()	234
3.6.4.484 HYPRE_ParCSRPilutSetup()	235
3.6.4.485 HYPRE_ParCSRPilutSolve()	235
3.6.4.486 HYPRE_ParCSRSetupInterpreter()	235
3.6.4.487 HYPRE_ParCSRSetupMatvec()	235
3.6.4.488 HYPRE_SchwarzCreate()	235
3.6.4.489 HYPRE_SchwarzDestroy()	235
3.6.4.490 HYPRE_SchwarzSetDofFunc()	235
3.6.4.491 HYPRE_SchwarzSetDomainStructure()	236
3.6.4.492 HYPRE_SchwarzSetDomainType()	236
3.6.4.493 HYPRE_SchwarzSetNonSymm()	236
3.6.4.494 HYPRE_SchwarzSetNumFunctions()	236
3.6.4.495 HYPRE_SchwarzSetOverlap()	236
3.6.4.496 HYPRE_SchwarzSetRelaxWeight()	236
3.6.4.497 HYPRE_SchwarzSetup()	236
3.6.4.498 HYPRE_SchwarzSetVariant()	237
3.6.4.499 HYPRE_SchwarzSolve()	237
3.7 Krylov Solvers	237
3.7.1 Detailed Description	241
3.7.2 Macro Definition Documentation	241
3.7.2.1 HYPRE_MATRIX_STRUCT	241
3.7.2.2 HYPRE_MODIFYPC	242
3.7.2.3 HYPRE_SOLVER_STRUCT	242
3.7.2.4 HYPRE_VECTOR_STRUCT	242
3.7.3 Typedef Documentation	242
3.7.3.1 HYPRE_Matrix	242
3.7.3.2 HYPRE_PtrToModifyPCFcn	242
3.7.3.3 HYPRE_PtrToSolverFcn	242
3.7.3.4 HYPRE_Solver	242
3.7.3.5 HYPRE_Vector	242
3.7.4 Function Documentation	243
3.7.4.1 HYPRE_BiCGSTABDestroy()	243
3.7.4.2 HYPRE_BiCGSTABGetFinalRelativeResidualNorm()	243
3.7.4.3 HYPRE_BiCGSTABGetNumIterations()	243
3.7.4.4 HYPRE_BiCGSTABGetPrecond()	243
3.7.4.5 HYPRE_BiCGSTABGetResidual()	243

3.7.4.6 HYPRE_BiCGSTABSetAbsoluteTol()	243
3.7.4.7 HYPRE_BiCGSTABSetConvergenceFactorTol()	244
3.7.4.8 HYPRE_BiCGSTABSetLogging()	244
3.7.4.9 HYPRE_BiCGSTABSetMaxIter()	244
3.7.4.10 HYPRE_BiCGSTABSetMinIter()	244
3.7.4.11 HYPRE_BiCGSTABSetPrecond()	244
3.7.4.12 HYPRE_BiCGSTABSetPrintLevel()	244
3.7.4.13 HYPRE_BiCGSTABSetStopCrit()	245
3.7.4.14 HYPRE_BiCGSTABSetTol()	245
3.7.4.15 HYPRE_BiCGSTABSetup()	245
3.7.4.16 HYPRE_BiCGSTABsolve()	245
3.7.4.17 HYPRE_CGNRDestroy()	245
3.7.4.18 HYPRE_CGNRGetFinalRelativeResidualNorm()	245
3.7.4.19 HYPRE_CGNRGetNumIterations()	246
3.7.4.20 HYPRE_CGNRGetPrecond()	246
3.7.4.21 HYPRE_CGNRSetLogging()	246
3.7.4.22 HYPRE_CGNRSetMaxIter()	246
3.7.4.23 HYPRE_CGNRSetMinIter()	246
3.7.4.24 HYPRE_CGNRSetPrecond()	246
3.7.4.25 HYPRE_CGNRSetStopCrit()	247
3.7.4.26 HYPRE_CGNRSetTol()	247
3.7.4.27 HYPRE_CGNRSetup()	247
3.7.4.28 HYPRE_CGNRSolve()	247
3.7.4.29 HYPRE_COGMRESGetCGS()	247
3.7.4.30 HYPRE_COGMRESGetConverged()	247
3.7.4.31 HYPRE_COGMRESGetConvergenceFactorTol()	248
3.7.4.32 HYPRE_COGMRESGetFinalRelativeResidualNorm()	248
3.7.4.33 HYPRE_COGMRESGetKDim()	248
3.7.4.34 HYPRE_COGMRESGetLogging()	248
3.7.4.35 HYPRE_COGMRESGetMaxIter()	248
3.7.4.36 HYPRE_COGMRESGetMinIter()	248
3.7.4.37 HYPRE_COGMRESGetNumIterations()	248
3.7.4.38 HYPRE_COGMRESGetPrecond()	249
3.7.4.39 HYPRE_COGMRESGetPrintLevel()	249
3.7.4.40 HYPRE_COGMRESGetResidual()	249
3.7.4.41 HYPRE_COGMRESGetTol()	249
3.7.4.42 HYPRE_COGMRESGetUnroll()	249
3.7.4.43 HYPRE_COGMRESSetAbsoluteTol()	249
3.7.4.44 HYPRE_COGMRESSetCGS()	249
3.7.4.45 HYPRE_COGMRESSetConvergenceFactorTol()	250
3.7.4.46 HYPRE_COGMRESSetKDim()	250
3.7.4.47 HYPRE_COGMRESSetLogging()	250

3.7.4.48 HYPRE_COGMRESsetMaxIter()	250
3.7.4.49 HYPRE_COGMRESsetMinIter()	250
3.7.4.50 HYPRE_COGMRESsetModifyPC()	250
3.7.4.51 HYPRE_COGMRESsetPrecond()	251
3.7.4.52 HYPRE_COGMRESsetPrintLevel()	251
3.7.4.53 HYPRE_COGMRESsetTol()	251
3.7.4.54 HYPRE_COGMRESsetUnroll()	251
3.7.4.55 HYPRE_COGMRESsetup()	251
3.7.4.56 HYPRE_COGMRESsolve()	252
3.7.4.57 HYPRE_FlexGMRESgetConverged()	252
3.7.4.58 HYPRE_FlexGMRESgetConvergenceFactorTol()	252
3.7.4.59 HYPRE_FlexGMRESgetFinalRelativeResidualNorm()	252
3.7.4.60 HYPRE_FlexGMRESgetKDim()	252
3.7.4.61 HYPRE_FlexGMRESgetLogging()	252
3.7.4.62 HYPRE_FlexGMRESsetMaxIter()	252
3.7.4.63 HYPRE_FlexGMRESsetMinIter()	253
3.7.4.64 HYPRE_FlexGMRESgetNumIterations()	253
3.7.4.65 HYPRE_FlexGMRESgetPrecond()	253
3.7.4.66 HYPRE_FlexGMRESgetPrintLevel()	253
3.7.4.67 HYPRE_FlexGMRESgetResidual()	253
3.7.4.68 HYPRE_FlexGMRESgetStopCrit()	253
3.7.4.69 HYPRE_FlexGMRESgetTol()	253
3.7.4.70 HYPRE_FlexGMRESsetAbsoluteTol()	254
3.7.4.71 HYPRE_FlexGMRESsetConvergenceFactorTol()	254
3.7.4.72 HYPRE_FlexGMRESsetKDim()	254
3.7.4.73 HYPRE_FlexGMRESsetLogging()	254
3.7.4.74 HYPRE_FlexGMRESsetMaxIter()	254
3.7.4.75 HYPRE_FlexGMRESsetMinIter()	254
3.7.4.76 HYPRE_FlexGMRESsetModifyPC()	255
3.7.4.77 HYPRE_FlexGMRESsetPrecond()	255
3.7.4.78 HYPRE_FlexGMRESsetPrintLevel()	255
3.7.4.79 HYPRE_FlexGMRESsetTol()	255
3.7.4.80 HYPRE_FlexGMRESsetup()	255
3.7.4.81 HYPRE_FlexGMRESsolve()	256
3.7.4.82 HYPRE_GMRESgetAbsoluteTol()	256
3.7.4.83 HYPRE_GMRESgetConverged()	256
3.7.4.84 HYPRE_GMRESgetConvergenceFactorTol()	256
3.7.4.85 HYPRE_GMRESgetFinalRelativeResidualNorm()	256
3.7.4.86 HYPRE_GMRESgetKDim()	256
3.7.4.87 HYPRE_GMRESgetLogging()	256
3.7.4.88 HYPRE_GMRESsetMaxIter()	257
3.7.4.89 HYPRE_GMRESsetMinIter()	257

3.7.4.90 HYPRE_GMRESGetNumIterations()	257
3.7.4.91 HYPRE_GMRESGetPrecond()	257
3.7.4.92 HYPRE_GMRESGetPrintLevel()	257
3.7.4.93 HYPRE_GMRESGetRelChange()	257
3.7.4.94 HYPRE_GMRESGetResidual()	257
3.7.4.95 HYPRE_GMRESGetSkipRealResidualCheck()	258
3.7.4.96 HYPRE_GMRESGetStopCrit()	258
3.7.4.97 HYPRE_GMRESGetTol()	258
3.7.4.98 HYPRE_GMRESSetAbsoluteTol()	258
3.7.4.99 HYPRE_GMRESSetConvergenceFactorTol()	258
3.7.4.100 HYPRE_GMRESSetKDim()	258
3.7.4.101 HYPRE_GMRESSetLogging()	258
3.7.4.102 HYPRE_GMRESSetMaxIter()	259
3.7.4.103 HYPRE_GMRESSetMinIter()	259
3.7.4.104 HYPRE_GMRESSetPrecond()	259
3.7.4.105 HYPRE_GMRESSetPrintLevel()	259
3.7.4.106 HYPRE_GMRESSetRelChange()	259
3.7.4.107 HYPRE_GMRESSetSkipRealResidualCheck()	259
3.7.4.108 HYPRE_GMRESSetStopCrit()	260
3.7.4.109 HYPRE_GMRESSetTol()	260
3.7.4.110 HYPRE_GMRESSetup()	260
3.7.4.111 HYPRE_GMRESolve()	260
3.7.4.112 HYPRE_LGMRESGetAugDim()	260
3.7.4.113 HYPRE_LGMRESGetConverged()	260
3.7.4.114 HYPRE_LGMRESGetConvergenceFactorTol()	261
3.7.4.115 HYPRE_LGMRESGetFinalRelativeResidualNorm()	261
3.7.4.116 HYPRE_LGMRESGetKDim()	261
3.7.4.117 HYPRE_LGMRESGetLogging()	261
3.7.4.118 HYPRE_LGMRESGetMaxIter()	261
3.7.4.119 HYPRE_LGMRESGetMinIter()	261
3.7.4.120 HYPRE_LGMRESGetNumIterations()	261
3.7.4.121 HYPRE_LGMRESGetPrecond()	262
3.7.4.122 HYPRE_LGMRESGetPrintLevel()	262
3.7.4.123 HYPRE_LGMRESGetResidual()	262
3.7.4.124 HYPRE_LGMRESGetStopCrit()	262
3.7.4.125 HYPRE_LGMRESGetTol()	262
3.7.4.126 HYPRE_LGMRESSetAbsoluteTol()	262
3.7.4.127 HYPRE_LGMRESSetAugDim()	262
3.7.4.128 HYPRE_LGMRESSetConvergenceFactorTol()	263
3.7.4.129 HYPRE_LGMRESSetKDim()	263
3.7.4.130 HYPRE_LGMRESSetLogging()	263
3.7.4.131 HYPRE_LGMRESSetMaxIter()	263

3.7.4.132 HYPRE_LGMRESSetMinIter()	263
3.7.4.133 HYPRE_LGMRESSetPrecond()	263
3.7.4.134 HYPRE_LGMRESSetPrintLevel()	264
3.7.4.135 HYPRE_LGMRESSetTol()	264
3.7.4.136 HYPRE_LGMRESSetup()	264
3.7.4.137 HYPRE_LGMRESSolve()	264
3.7.4.138 HYPRE_PCGGetAbsoluteTolFactor()	264
3.7.4.139 HYPRE_PCGGetConverged()	264
3.7.4.140 HYPRE_PCGGetConvergenceFactorTol()	265
3.7.4.141 HYPRE_PCGGetFinalRelativeResidualNorm()	265
3.7.4.142 HYPRE_PCGGetLogging()	265
3.7.4.143 HYPRE_PCGGetMaxIter()	265
3.7.4.144 HYPRE_PCGGetNumIterations()	265
3.7.4.145 HYPRE_PCGGetPrecond()	265
3.7.4.146 HYPRE_PCGGetPrintLevel()	265
3.7.4.147 HYPRE_PCGGetRelChange()	266
3.7.4.148 HYPRE_PCGGetResidual()	266
3.7.4.149 HYPRE_PCGGetResidualTol()	266
3.7.4.150 HYPRE_PCGGetStopCrit()	266
3.7.4.151 HYPRE_PCGGetTol()	266
3.7.4.152 HYPRE_PCGGetTwoNorm()	266
3.7.4.153 HYPRE_PCGSetAbsoluteTol()	266
3.7.4.154 HYPRE_PCGSetAbsoluteTolFactor()	267
3.7.4.155 HYPRE_PCGSetConvergenceFactorTol()	267
3.7.4.156 HYPRE_PCGSetLogging()	267
3.7.4.157 HYPRE_PCGSetMaxIter()	267
3.7.4.158 HYPRE_PCGSetPrecond()	267
3.7.4.159 HYPRE_PCGSetPrintLevel()	267
3.7.4.160 HYPRE_PCGSetRecomputeResidual()	268
3.7.4.161 HYPRE_PCGSetRecomputeResidualIP()	268
3.7.4.162 HYPRE_PCGSetRelChange()	268
3.7.4.163 HYPRE_PCGSetResidualTol()	268
3.7.4.164 HYPRE_PCGSetStopCrit()	268
3.7.4.165 HYPRE_PCGSetTol()	268
3.7.4.166 HYPRE_PCGSetTwoNorm()	269
3.7.4.167 HYPRE_PCGSetup()	269
3.7.4.168 HYPRE_PCGSolve()	269
3.8 Eigensolvers	269
3.8.1 Detailed Description	270
3.8.2 Function Documentation	270
3.8.2.1 HYPRE_LOBPCGCreate()	270
3.8.2.2 HYPRE_LOBPCGDestroy()	270



3.8.2.3 HYPRE_LOBPCGEigenvaluesHistory()	270
3.8.2.4 HYPRE_LOBPCGGetPrecond()	270
3.8.2.5 HYPRE_LOBPCGIterations()	270
3.8.2.6 hypre_LOBPCGMultiOperatorB()	270
3.8.2.7 HYPRE_LOBPCGResidualNorms()	271
3.8.2.8 HYPRE_LOBPCGResidualNormsHistory()	271
3.8.2.9 HYPRE_LOBPCGSetMaxIter()	271
3.8.2.10 HYPRE_LOBPCGSetPrecond()	271
3.8.2.11 HYPRE_LOBPCGSetPrecondUsageMode()	271
3.8.2.12 HYPRE_LOBPCGSetPrintLevel()	271
3.8.2.13 HYPRE_LOBPCGSetRTol()	272
3.8.2.14 HYPRE_LOBPCGSetTol()	272
3.8.2.15 HYPRE_LOBPCGSetup()	272
3.8.2.16 HYPRE_LOBPCGSetupB()	272
3.8.2.17 HYPRE_LOBPCGSetupT()	272
3.8.2.18 HYPRE_LOBPCGSolve()	272
3.8.2.19 lobpcg_MultiVectorByMultiVector()	273

## 4 File Documentation 275

4.1 HYPRE_IJ_mv.h File Reference	275
4.2 HYPRE_krylov.h File Reference	276
4.3 HYPRE_lobpcg.h File Reference	280
4.4 HYPRE_parcsr_ls.h File Reference	281
4.5 HYPRE_sstruct_ls.h File Reference	294
4.6 HYPRE_sstruct_mv.h File Reference	299
4.7 HYPRE_struct_ls.h File Reference	301
4.8 HYPRE_struct_mv.h File Reference	307
4.8.1 Macro Definition Documentation	309
4.8.1.1 HYPRE_StructVector_defined	309
4.8.2 Typedef Documentation	309
4.8.2.1 HYPRE_CommPkg	309
4.8.2.2 HYPRE_StructVector	309
4.8.3 Function Documentation	310
4.8.3.1 HYPRE_CommPkgDestroy()	310
4.8.3.2 HYPRE_StructMatrixGetGrid()	310
4.8.3.3 HYPRE_StructVectorGetMigrateCommPkg()	310
4.8.3.4 HYPRE_StructVectorMigrate()	310
4.8.3.5 HYPRE_StructVectorSetConstantValues()	310
4.8.3.6 HYPRE_StructVectorSetNumGhost()	310



# Chapter 1

## Topic Index

### 1.1 Topics

Here is a list of all topics with brief descriptions:

Struct System Interface . . . . .	5
SStruct System Interface . . . . .	17
IJ System Interface . . . . .	39
Struct Solvers . . . . .	49
SStruct Solvers . . . . .	87
ParCSR Solvers . . . . .	119
Krylov Solvers . . . . .	237
Eigensolvers . . . . .	269



## Chapter 2

# File Index

### 2.1 File List

Here is a list of all files with brief descriptions:

<a href="#">HYPRE_IJ_mv.h</a>	275
<a href="#">HYPRE_krylov.h</a>	276
<a href="#">HYPRE_lobpcg.h</a>	280
<a href="#">HYPRE_parcsr_ls.h</a>	281
<a href="#">HYPRE_sstruct_ls.h</a>	294
<a href="#">HYPRE_sstruct_mv.h</a>	299
<a href="#">HYPRE_struct_ls.h</a>	301
<a href="#">HYPRE_struct_mv.h</a>	307



# Chapter 3

## Topic Documentation

### 3.1 Struct System Interface

#### Struct Grids

- typedef struct hypre\_StructGrid\_struct \* [HYPRE\\_StructGrid](#)
- HYPRE\_Int [HYPRE\\_StructGridCreate](#) (MPI\_Comm comm, HYPRE\_Int ndim, [HYPRE\\_StructGrid](#) \*grid)
- HYPRE\_Int [HYPRE\\_StructGridDestroy](#) ([HYPRE\\_StructGrid](#) grid)
- HYPRE\_Int [HYPRE\\_StructGridSetExtents](#) ([HYPRE\\_StructGrid](#) grid, HYPRE\_Int \*ilower, HYPRE\_Int \*iupper)
- HYPRE\_Int [HYPRE\\_StructGridAssemble](#) ([HYPRE\\_StructGrid](#) grid)
- HYPRE\_Int [HYPRE\\_StructGridSetPeriodic](#) ([HYPRE\\_StructGrid](#) grid, HYPRE\_Int \*periodic)
- HYPRE\_Int [HYPRE\\_StructGridSetNumGhost](#) ([HYPRE\\_StructGrid](#) grid, HYPRE\_Int \*num\_ghost)

#### Struct Stencils

- typedef struct hypre\_StructStencil\_struct \* [HYPRE\\_StructStencil](#)
- HYPRE\_Int [HYPRE\\_StructStencilCreate](#) (HYPRE\_Int ndim, HYPRE\_Int size, [HYPRE\\_StructStencil](#) \*stencil)
- HYPRE\_Int [HYPRE\\_StructStencilDestroy](#) ([HYPRE\\_StructStencil](#) stencil)
- HYPRE\_Int [HYPRE\\_StructStencilSetElement](#) ([HYPRE\\_StructStencil](#) stencil, HYPRE\_Int entry, HYPRE\_Int \*offset)

#### Struct Matrices

- typedef struct hypre\_StructMatrix\_struct \* [HYPRE\\_StructMatrix](#)
- HYPRE\_Int [HYPRE\\_StructMatrixCreate](#) (MPI\_Comm comm, [HYPRE\\_StructGrid](#) grid, [HYPRE\\_StructStencil](#) stencil, [HYPRE\\_StructMatrix](#) \*matrix)
- HYPRE\_Int [HYPRE\\_StructMatrixDestroy](#) ([HYPRE\\_StructMatrix](#) matrix)
- HYPRE\_Int [HYPRE\\_StructMatrixInitialize](#) ([HYPRE\\_StructMatrix](#) matrix)
- HYPRE\_Int [HYPRE\\_StructMatrixSetValues](#) ([HYPRE\\_StructMatrix](#) matrix, HYPRE\_Int \*index, HYPRE\_Int nentries, HYPRE\_Int \*entries, HYPRE\_Complex \*values)
- HYPRE\_Int [HYPRE\\_StructMatrixAddToValues](#) ([HYPRE\\_StructMatrix](#) matrix, HYPRE\_Int \*index, HYPRE\_Int nentries, HYPRE\_Int \*entries, HYPRE\_Complex \*values)
- HYPRE\_Int [HYPRE\\_StructMatrixSetConstantValues](#) ([HYPRE\\_StructMatrix](#) matrix, HYPRE\_Int nentries, HYPRE\_Int \*entries, HYPRE\_Complex \*values)
- HYPRE\_Int [HYPRE\\_StructMatrixAddToConstantValues](#) ([HYPRE\\_StructMatrix](#) matrix, HYPRE\_Int nentries, HYPRE\_Int \*entries, HYPRE\_Complex \*values)

- HYPRE\_Int [HYPRE\\_StructMatrixSetBoxValues](#) (HYPRE\_StructMatrix matrix, HYPRE\_Int \*ilower, HYPRE\_Int \*iupper, HYPRE\_Int nentries, HYPRE\_Int \*entries, HYPRE\_Complex \*values)
- HYPRE\_Int [HYPRE\\_StructMatrixAddToBoxValues](#) (HYPRE\_StructMatrix matrix, HYPRE\_Int \*ilower, HYPRE\_Int \*iupper, HYPRE\_Int nentries, HYPRE\_Int \*entries, HYPRE\_Complex \*values)
- HYPRE\_Int [HYPRE\\_StructMatrixSetBoxValues2](#) (HYPRE\_StructMatrix matrix, HYPRE\_Int \*ilower, HYPRE\_Int \*iupper, HYPRE\_Int nentries, HYPRE\_Int \*entries, HYPRE\_Int \*vilower, HYPRE\_Int \*viupper, HYPRE\_Complex \*values)
- HYPRE\_Int [HYPRE\\_StructMatrixAddToBoxValues2](#) (HYPRE\_StructMatrix matrix, HYPRE\_Int \*ilower, HYPRE\_Int \*iupper, HYPRE\_Int nentries, HYPRE\_Int \*entries, HYPRE\_Int \*vilower, HYPRE\_Int \*viupper, HYPRE\_Complex \*values)
- HYPRE\_Int [HYPRE\\_StructMatrixAssemble](#) (HYPRE\_StructMatrix matrix)
- HYPRE\_Int [HYPRE\\_StructMatrixGetValues](#) (HYPRE\_StructMatrix matrix, HYPRE\_Int \*index, HYPRE\_Int nentries, HYPRE\_Int \*entries, HYPRE\_Complex \*values)
- HYPRE\_Int [HYPRE\\_StructMatrixGetBoxValues](#) (HYPRE\_StructMatrix matrix, HYPRE\_Int \*ilower, HYPRE\_Int \*iupper, HYPRE\_Int nentries, HYPRE\_Int \*entries, HYPRE\_Complex \*values)
- HYPRE\_Int [HYPRE\\_StructMatrixGetBoxValues2](#) (HYPRE\_StructMatrix matrix, HYPRE\_Int \*ilower, HYPRE\_Int \*iupper, HYPRE\_Int nentries, HYPRE\_Int \*entries, HYPRE\_Int \*vilower, HYPRE\_Int \*viupper, HYPRE\_Complex \*values)
- HYPRE\_Int [HYPRE\\_StructMatrixSetSymmetric](#) (HYPRE\_StructMatrix matrix, HYPRE\_Int symmetric)
- HYPRE\_Int [HYPRE\\_StructMatrixSetConstantEntries](#) (HYPRE\_StructMatrix matrix, HYPRE\_Int nentries, HYPRE\_Int \*entries)
- HYPRE\_Int [HYPRE\\_StructMatrixSetNumGhost](#) (HYPRE\_StructMatrix matrix, HYPRE\_Int \*num\_ghost)
- HYPRE\_Int [HYPRE\\_StructMatrixPrint](#) (const char \*filename, HYPRE\_StructMatrix matrix, HYPRE\_Int all)
- HYPRE\_Int [HYPRE\\_StructMatrixMatvec](#) (HYPRE\_Complex alpha, HYPRE\_StructMatrix A, HYPRE\_StructVector x, HYPRE\_Complex beta, HYPRE\_StructVector y)

## Struct Vectors

- HYPRE\_Int [HYPRE\\_StructVectorCreate](#) (MPI\_Comm comm, HYPRE\_StructGrid grid, HYPRE\_StructVector \*vector)
- HYPRE\_Int [HYPRE\\_StructVectorDestroy](#) (HYPRE\_StructVector vector)
- HYPRE\_Int [HYPRE\\_StructVectorInitialize](#) (HYPRE\_StructVector vector)
- HYPRE\_Int [HYPRE\\_StructVectorSetValues](#) (HYPRE\_StructVector vector, HYPRE\_Int \*index, HYPRE\_Complex value)
- HYPRE\_Int [HYPRE\\_StructVectorAddToValues](#) (HYPRE\_StructVector vector, HYPRE\_Int \*index, HYPRE\_Complex value)
- HYPRE\_Int [HYPRE\\_StructVectorSetBoxValues](#) (HYPRE\_StructVector vector, HYPRE\_Int \*ilower, HYPRE\_Int \*iupper, HYPRE\_Complex \*values)
- HYPRE\_Int [HYPRE\\_StructVectorAddToBoxValues](#) (HYPRE\_StructVector vector, HYPRE\_Int \*ilower, HYPRE\_Int \*iupper, HYPRE\_Complex \*values)
- HYPRE\_Int [HYPRE\\_StructVectorSetBoxValues2](#) (HYPRE\_StructVector vector, HYPRE\_Int \*ilower, HYPRE\_Int \*iupper, HYPRE\_Int \*vilower, HYPRE\_Int \*viupper, HYPRE\_Complex \*values)
- HYPRE\_Int [HYPRE\\_StructVectorAddToBoxValues2](#) (HYPRE\_StructVector vector, HYPRE\_Int \*ilower, HYPRE\_Int \*iupper, HYPRE\_Int \*vilower, HYPRE\_Int \*viupper, HYPRE\_Complex \*values)
- HYPRE\_Int [HYPRE\\_StructVectorAssemble](#) (HYPRE\_StructVector vector)
- HYPRE\_Int [HYPRE\\_StructVectorGetValues](#) (HYPRE\_StructVector vector, HYPRE\_Int \*index, HYPRE\_Complex \*value)
- HYPRE\_Int [HYPRE\\_StructVectorGetBoxValues](#) (HYPRE\_StructVector vector, HYPRE\_Int \*ilower, HYPRE\_Int \*iupper, HYPRE\_Complex \*values)
- HYPRE\_Int [HYPRE\\_StructVectorGetBoxValues2](#) (HYPRE\_StructVector vector, HYPRE\_Int \*ilower, HYPRE\_Int \*iupper, HYPRE\_Int \*vilower, HYPRE\_Int \*viupper, HYPRE\_Complex \*values)
- HYPRE\_Int [HYPRE\\_StructVectorPrint](#) (const char \*filename, HYPRE\_StructVector vector, HYPRE\_Int all)



### 3.1.1 Detailed Description

This interface represents a structured-grid conceptual view of a linear system.

@memo A structured-grid conceptual interface

### 3.1.2 Typedef Documentation

#### 3.1.2.1 HYPRE\_StructGrid

```
typedef struct hypre_StructGrid_struct* HYPRE_StructGrid
```

A grid object is constructed out of several "boxes", defined on a global abstract index space.

#### 3.1.2.2 HYPRE\_StructMatrix

```
typedef struct hypre_StructMatrix_struct* HYPRE_StructMatrix
```

The matrix object.

#### 3.1.2.3 HYPRE\_StructStencil

```
typedef struct hypre_StructStencil_struct* HYPRE_StructStencil
```

The stencil object.

### 3.1.3 Function Documentation

#### 3.1.3.1 HYPRE\_StructGridAssemble()

```
HYPRE_Int HYPRE_StructGridAssemble (
    HYPRE_StructGrid grid )
```

Finalize the construction of the grid before using.

#### 3.1.3.2 HYPRE\_StructGridCreate()

```
HYPRE_Int HYPRE_StructGridCreate (
    MPI_Comm comm,
    HYPRE_Int ndim,
    HYPRE_StructGrid * grid )
```

Create an *ndim*-dimensional grid object.

### 3.1.3.3 HYPRE\_StructGridDestroy()

```
HYPRE_Int HYPRE_StructGridDestroy (
    HYPRE_StructGrid grid )
```

Destroy a grid object. An object should be explicitly destroyed using this destructor when the user's code no longer needs direct access to it. Once destroyed, the object must not be referenced again. Note that the object may not be deallocated at the completion of this call, since there may be internal package references to the object. The object will then be destroyed when all internal reference counts go to zero.

### 3.1.3.4 HYPRE\_StructGridSetExtents()

```
HYPRE_Int HYPRE_StructGridSetExtents (
    HYPRE_StructGrid grid,
    HYPRE_Int * ilower,
    HYPRE_Int * iupper )
```

Set the extents for a box on the grid.

### 3.1.3.5 HYPRE\_StructGridSetNumGhost()

```
HYPRE_Int HYPRE_StructGridSetNumGhost (
    HYPRE_StructGrid grid,
    HYPRE_Int * num_ghost )
```

Set the ghost layer in the grid object

### 3.1.3.6 HYPRE\_StructGridSetPeriodic()

```
HYPRE_Int HYPRE_StructGridSetPeriodic (
    HYPRE_StructGrid grid,
    HYPRE_Int * periodic )
```

Set the periodicity for the grid.

The argument *periodic* is an *ndim*-dimensional integer array that contains the periodicity for each dimension. A zero value for a dimension means non-periodic, while a nonzero value means periodic and contains the actual period. For example, periodicity in the first and third dimensions for a 10x11x12 grid is indicated by the array [10,0,12].

NOTE: Some of the solvers in hypre have power-of-two restrictions on the size of the periodic dimensions.

### 3.1.3.7 HYPRE\_StructMatrixAddToBoxValues()

```
HYPRE_Int HYPRE_StructMatrixAddToBoxValues (
    HYPRE_StructMatrix matrix,
    HYPRE_Int * ilower,
    HYPRE_Int * iupper,
    HYPRE_Int nentries,
    HYPRE_Int * entries,
    HYPRE_Complex * values )
```

Add to matrix coefficients a box at a time. The data in *values* is ordered as in [HYPRE\\_StructMatrixSetBoxValues](#).

**3.1.3.8 HYPRE\_StructMatrixAddToBoxValues2()**

```

HYPRE_Int HYPRE_StructMatrixAddToBoxValues2 (
    HYPRE_StructMatrix matrix,
    HYPRE_Int * ilower,
    HYPRE_Int * iupper,
    HYPRE_Int nentries,
    HYPRE_Int * entries,
    HYPRE_Int * vilower,
    HYPRE_Int * viupper,
    HYPRE_Complex * values )

```

Add to matrix coefficients a box at a time. The data in *values* is ordered as in [HYPRE\\_StructMatrixSetBoxValues2](#).

**3.1.3.9 HYPRE\_StructMatrixAddToConstantValues()**

```

HYPRE_Int HYPRE_StructMatrixAddToConstantValues (
    HYPRE_StructMatrix matrix,
    HYPRE_Int nentries,
    HYPRE_Int * entries,
    HYPRE_Complex * values )

```

Add to matrix coefficients which are constant over the grid. The *values* array is of length *nentries*.

**3.1.3.10 HYPRE\_StructMatrixAddToValues()**

```

HYPRE_Int HYPRE_StructMatrixAddToValues (
    HYPRE_StructMatrix matrix,
    HYPRE_Int * index,
    HYPRE_Int nentries,
    HYPRE_Int * entries,
    HYPRE_Complex * values )

```

Add to matrix coefficients index by index. The *values* array is of length *nentries*.

NOTE: For better efficiency, use [HYPRE\\_StructMatrixAddToBoxValues](#) to set coefficients a box at a time.

**3.1.3.11 HYPRE\_StructMatrixAssemble()**

```

HYPRE_Int HYPRE_StructMatrixAssemble (
    HYPRE_StructMatrix matrix )

```

Finalize the construction of the matrix before using.

**3.1.3.12 HYPRE\_StructMatrixCreate()**

```

HYPRE_Int HYPRE_StructMatrixCreate (
    MPI_Comm comm,
    HYPRE_StructGrid grid,
    HYPRE_StructStencil stencil,
    HYPRE_StructMatrix * matrix )

```

Create a matrix object.

### 3.1.3.13 HYPRE\_StructMatrixDestroy()

```
HYPRE_Int HYPRE_StructMatrixDestroy (
    HYPRE_StructMatrix matrix )
```

Destroy a matrix object.

### 3.1.3.14 HYPRE\_StructMatrixGetBoxValues()

```
HYPRE_Int HYPRE_StructMatrixGetBoxValues (
    HYPRE_StructMatrix matrix,
    HYPRE_Int * ilower,
    HYPRE_Int * iupper,
    HYPRE_Int nentries,
    HYPRE_Int * entries,
    HYPRE_Complex * values )
```

Get matrix coefficients a box at a time. The data in *values* is ordered as in [HYPRE\\_StructMatrixSetBoxValues](#).

### 3.1.3.15 HYPRE\_StructMatrixGetBoxValues2()

```
HYPRE_Int HYPRE_StructMatrixGetBoxValues2 (
    HYPRE_StructMatrix matrix,
    HYPRE_Int * ilower,
    HYPRE_Int * iupper,
    HYPRE_Int nentries,
    HYPRE_Int * entries,
    HYPRE_Int * vilower,
    HYPRE_Int * viupper,
    HYPRE_Complex * values )
```

Get matrix coefficients a box at a time. The data in *values* is ordered as in [HYPRE\\_StructMatrixSetBoxValues2](#).

### 3.1.3.16 HYPRE\_StructMatrixGetValues()

```
HYPRE_Int HYPRE_StructMatrixGetValues (
    HYPRE_StructMatrix matrix,
    HYPRE_Int * index,
    HYPRE_Int nentries,
    HYPRE_Int * entries,
    HYPRE_Complex * values )
```

Get matrix coefficients index by index. The *values* array is of length *nentries*.

NOTE: For better efficiency, use [HYPRE\\_StructMatrixGetBoxValues](#) to get coefficients a box at a time.

### 3.1.3.17 HYPRE\_StructMatrixInitialize()

```
HYPRE_Int HYPRE_StructMatrixInitialize (
    HYPRE_StructMatrix matrix )
```

Prepare a matrix object for setting coefficient values.

**3.1.3.18 HYPRE\_StructMatrixMatvec()**

```
HYPRE_Int HYPRE_StructMatrixMatvec (
    HYPRE_Complex alpha,
    HYPRE_StructMatrix A,
    HYPRE_StructVector x,
    HYPRE_Complex beta,
    HYPRE_StructVector y )
```

Matvec operator. This operation is  $y = \alpha Ax + \beta y$ . Note that you can do a simple matrix-vector multiply by setting  $\alpha = 1$  and  $\beta = 0$ .

**3.1.3.19 HYPRE\_StructMatrixPrint()**

```
HYPRE_Int HYPRE_StructMatrixPrint (
    const char * filename,
    HYPRE_StructMatrix matrix,
    HYPRE_Int all )
```

Print the matrix to file. This is mainly for debugging purposes.

**3.1.3.20 HYPRE\_StructMatrixSetBoxValues()**

```
HYPRE_Int HYPRE_StructMatrixSetBoxValues (
    HYPRE_StructMatrix matrix,
    HYPRE_Int * ilower,
    HYPRE_Int * iupper,
    HYPRE_Int nentries,
    HYPRE_Int * entries,
    HYPRE_Complex * values )
```

Set matrix coefficients a box at a time. The data in *values* is ordered as follows:

```
m = 0;
for (k = ilower[2]; k <= iupper[2]; k++)
    for (j = ilower[1]; j <= iupper[1]; j++)
        for (i = ilower[0]; i <= iupper[0]; i++)
            for (entry = 0; entry < nentries; entry++)
            {
                values[m] = ...;
                m++;
            }
```

**3.1.3.21 HYPRE\_StructMatrixSetBoxValues2()**

```
HYPRE_Int HYPRE_StructMatrixSetBoxValues2 (
    HYPRE_StructMatrix matrix,
    HYPRE_Int * ilower,
    HYPRE_Int * iupper,
    HYPRE_Int nentries,
    HYPRE_Int * entries,
    HYPRE_Int * vilower,
    HYPRE_Int * viupper,
    HYPRE_Complex * values )
```

Set matrix coefficients a box at a time. The *values* array is logically box shaped with value-box extents *vilower* and *viupper* that must contain the set-box extents *ilower* and *iupper*. The data in the *values* array is ordered as in [HYPRE\\_StructMatrixSetBoxValues](#), but based on the value-box extents.

### 3.1.3.22 HYPRE\_StructMatrixSetConstantEntries()

```
HYPRE_Int HYPRE_StructMatrixSetConstantEntries (
    HYPRE_StructMatrix matrix,
    HYPRE_Int nentries,
    HYPRE_Int * entries )
```

Specify which stencil entries are constant over the grid. Declaring entries to be "constant over the grid" yields significant memory savings because the value for each declared entry will only be stored once. However, not all solvers are able to utilize this feature.

Presently supported:

- no entries constant (this function need not be called)
- all entries constant
- all but the diagonal entry constant

### 3.1.3.23 HYPRE\_StructMatrixSetConstantValues()

```
HYPRE_Int HYPRE_StructMatrixSetConstantValues (
    HYPRE_StructMatrix matrix,
    HYPRE_Int nentries,
    HYPRE_Int * entries,
    HYPRE_Complex * values )
```

Set matrix coefficients which are constant over the grid. The *values* array is of length *nentries*.

### 3.1.3.24 HYPRE\_StructMatrixSetNumGhost()

```
HYPRE_Int HYPRE_StructMatrixSetNumGhost (
    HYPRE_StructMatrix matrix,
    HYPRE_Int * num_ghost )
```

Set the ghost layer in the matrix

### 3.1.3.25 HYPRE\_StructMatrixSetSymmetric()

```
HYPRE_Int HYPRE_StructMatrixSetSymmetric (
    HYPRE_StructMatrix matrix,
    HYPRE_Int symmetric )
```

Define symmetry properties of the matrix. By default, matrices are assumed to be nonsymmetric. Significant storage savings can be made if the matrix is symmetric.

**3.1.3.26 HYPRE\_StructMatrixSetValues()**

```

HYPRE_Int HYPRE_StructMatrixSetValues (
    HYPRE_StructMatrix matrix,
    HYPRE_Int * index,
    HYPRE_Int nentries,
    HYPRE_Int * entries,
    HYPRE_Complex * values )

```

Set matrix coefficients index by index. The *values* array is of length *nentries*.

NOTE: For better efficiency, use [HYPRE\\_StructMatrixSetBoxValues](#) to set coefficients a box at a time.

**3.1.3.27 HYPRE\_StructStencilCreate()**

```

HYPRE_Int HYPRE_StructStencilCreate (
    HYPRE_Int ndim,
    HYPRE_Int size,
    HYPRE_StructStencil * stencil )

```

Create a stencil object for the specified number of spatial dimensions and stencil entries.

**3.1.3.28 HYPRE\_StructStencilDestroy()**

```

HYPRE_Int HYPRE_StructStencilDestroy (
    HYPRE_StructStencil stencil )

```

Destroy a stencil object.

**3.1.3.29 HYPRE\_StructStencilSetElement()**

```

HYPRE_Int HYPRE_StructStencilSetElement (
    HYPRE_StructStencil stencil,
    HYPRE_Int entry,
    HYPRE_Int * offset )

```

Set a stencil entry.

NOTE: The name of this routine will eventually be changed to *HYPRE\_StructStencilSetEntry*.

**3.1.3.30 HYPRE\_StructVectorAddToBoxValues()**

```

HYPRE_Int HYPRE_StructVectorAddToBoxValues (
    HYPRE_StructVector vector,
    HYPRE_Int * ilower,
    HYPRE_Int * iupper,
    HYPRE_Complex * values )

```

Add to vector coefficients a box at a time. The data in *values* is ordered as in [HYPRE\\_StructVectorSetBoxValues](#).

### 3.1.3.31 HYPRE\_StructVectorAddToBoxValues2()

```
HYPRE_Int HYPRE_StructVectorAddToBoxValues2 (
    HYPRE_StructVector vector,
    HYPRE_Int * ilower,
    HYPRE_Int * iupper,
    HYPRE_Int * vilower,
    HYPRE_Int * viupper,
    HYPRE_Complex * values )
```

Add to vector coefficients a box at a time. The data in *values* is ordered as in [HYPRE\\_StructVectorSetBoxValues2](#).

### 3.1.3.32 HYPRE\_StructVectorAddToValues()

```
HYPRE_Int HYPRE_StructVectorAddToValues (
    HYPRE_StructVector vector,
    HYPRE_Int * index,
    HYPRE_Complex value )
```

Add to vector coefficients index by index.

NOTE: For better efficiency, use [HYPRE\\_StructVectorAddToBoxValues](#) to set coefficients a box at a time.

### 3.1.3.33 HYPRE\_StructVectorAssemble()

```
HYPRE_Int HYPRE_StructVectorAssemble (
    HYPRE_StructVector vector )
```

Finalize the construction of the vector before using.

### 3.1.3.34 HYPRE\_StructVectorCreate()

```
HYPRE_Int HYPRE_StructVectorCreate (
    MPI_Comm comm,
    HYPRE_StructGrid grid,
    HYPRE_StructVector * vector )
```

The vector object. Create a vector object.

### 3.1.3.35 HYPRE\_StructVectorDestroy()

```
HYPRE_Int HYPRE_StructVectorDestroy (
    HYPRE_StructVector vector )
```

Destroy a vector object.



**3.1.3.36 HYPRE\_StructVectorGetBoxValues()**

```

HYPRE_Int HYPRE_StructVectorGetBoxValues (
    HYPRE_StructVector vector,
    HYPRE_Int * ilower,
    HYPRE_Int * iupper,
    HYPRE_Complex * values )

```

Get vector coefficients a box at a time. The data in *values* is ordered as in [HYPRE\\_StructVectorSetBoxValues](#).

**3.1.3.37 HYPRE\_StructVectorGetBoxValues2()**

```

HYPRE_Int HYPRE_StructVectorGetBoxValues2 (
    HYPRE_StructVector vector,
    HYPRE_Int * ilower,
    HYPRE_Int * iupper,
    HYPRE_Int * vilower,
    HYPRE_Int * viupper,
    HYPRE_Complex * values )

```

Get vector coefficients a box at a time. The data in *values* is ordered as in [HYPRE\\_StructVectorSetBoxValues2](#).

**3.1.3.38 HYPRE\_StructVectorGetValues()**

```

HYPRE_Int HYPRE_StructVectorGetValues (
    HYPRE_StructVector vector,
    HYPRE_Int * index,
    HYPRE_Complex * value )

```

Get vector coefficients index by index.

NOTE: For better efficiency, use [HYPRE\\_StructVectorGetBoxValues](#) to get coefficients a box at a time.

**3.1.3.39 HYPRE\_StructVectorInitialize()**

```

HYPRE_Int HYPRE_StructVectorInitialize (
    HYPRE_StructVector vector )

```

Prepare a vector object for setting coefficient values.

**3.1.3.40 HYPRE\_StructVectorPrint()**

```

HYPRE_Int HYPRE_StructVectorPrint (
    const char * filename,
    HYPRE_StructVector vector,
    HYPRE_Int all )

```

Print the vector to file. This is mainly for debugging purposes.

### 3.1.3.41 HYPRE\_StructVectorSetBoxValues()

```
HYPRE_Int HYPRE_StructVectorSetBoxValues (
    HYPRE_StructVector vector,
    HYPRE_Int * ilower,
    HYPRE_Int * iupper,
    HYPRE_Complex * values )
```

Set vector coefficients a box at a time. The data in *values* is ordered as follows:

```
m = 0;
for (k = ilower[2]; k <= iupper[2]; k++)
    for (j = ilower[1]; j <= iupper[1]; j++)
        for (i = ilower[0]; i <= iupper[0]; i++)
        {
            values[m] = ...;
            m++;
        }
```

### 3.1.3.42 HYPRE\_StructVectorSetBoxValues2()

```
HYPRE_Int HYPRE_StructVectorSetBoxValues2 (
    HYPRE_StructVector vector,
    HYPRE_Int * ilower,
    HYPRE_Int * iupper,
    HYPRE_Int * vilower,
    HYPRE_Int * viupper,
    HYPRE_Complex * values )
```

Set vector coefficients a box at a time. The *values* array is logically box shaped with value-box extents *vilower* and *viupper* that must contain the set-box extents *ilower* and *iupper*. The data in the *values* array is ordered as in [HYPRE\\_StructVectorSetBoxValues](#), but based on the value-box extents.

### 3.1.3.43 HYPRE\_StructVectorSetValues()

```
HYPRE_Int HYPRE_StructVectorSetValues (
    HYPRE_StructVector vector,
    HYPRE_Int * index,
    HYPRE_Complex value )
```

Set vector coefficients index by index.

NOTE: For better efficiency, use [HYPRE\\_StructVectorSetBoxValues](#) to set coefficients a box at a time.

## 3.2 SStruct System Interface

### SStruct Grids

- typedef struct hypr\_SStructGrid\_struct \* [HYPRE\\_SStructGrid](#)
- typedef HYPRE\_Int [HYPRE\\_SStructVariable](#)
- HYPRE\_Int [HYPRE\\_SStructGridCreate](#) (MPI\_Comm comm, HYPRE\_Int ndim, HYPRE\_Int nparts, [HYPRE\\_SStructGrid](#) \*grid)
- HYPRE\_Int [HYPRE\\_SStructGridDestroy](#) ([HYPRE\\_SStructGrid](#) grid)
- HYPRE\_Int [HYPRE\\_SStructGridSetExtents](#) ([HYPRE\\_SStructGrid](#) grid, HYPRE\_Int part, HYPRE\_Int \*ilower, HYPRE\_Int \*iupper)
- HYPRE\_Int [HYPRE\\_SStructGridSetVariables](#) ([HYPRE\\_SStructGrid](#) grid, HYPRE\_Int part, HYPRE\_Int nvars, [HYPRE\\_SStructVariable](#) \*vartypes)
- HYPRE\_Int [HYPRE\\_SStructGridAddVariables](#) ([HYPRE\\_SStructGrid](#) grid, HYPRE\_Int part, HYPRE\_Int \*index, HYPRE\_Int nvars, [HYPRE\\_SStructVariable](#) \*vartypes)
- HYPRE\_Int [HYPRE\\_SStructGridSetFEMOrdering](#) ([HYPRE\\_SStructGrid](#) grid, HYPRE\_Int part, HYPRE\_Int \*ordering)
- HYPRE\_Int [HYPRE\\_SStructGridSetNeighborPart](#) ([HYPRE\\_SStructGrid](#) grid, HYPRE\_Int part, HYPRE\_Int \*ilower, HYPRE\_Int \*iupper, HYPRE\_Int nbor\_part, HYPRE\_Int \*nbor\_ilower, HYPRE\_Int \*nbor\_iupper, HYPRE\_Int \*index\_map, HYPRE\_Int \*index\_dir)
- HYPRE\_Int [HYPRE\\_SStructGridSetSharedPart](#) ([HYPRE\\_SStructGrid](#) grid, HYPRE\_Int part, HYPRE\_Int \*ilower, HYPRE\_Int \*iupper, HYPRE\_Int \*offset, HYPRE\_Int shared\_part, HYPRE\_Int \*shared\_ilower, HYPRE\_Int \*shared\_iupper, HYPRE\_Int \*shared\_offset, HYPRE\_Int \*index\_map, HYPRE\_Int \*index\_dir)
- HYPRE\_Int [HYPRE\\_SStructGridAddUnstructuredPart](#) ([HYPRE\\_SStructGrid](#) grid, HYPRE\_Int ilower, HYPRE\_Int iupper)
- HYPRE\_Int [HYPRE\\_SStructGridAssemble](#) ([HYPRE\\_SStructGrid](#) grid)
- HYPRE\_Int [HYPRE\\_SStructGridSetPeriodic](#) ([HYPRE\\_SStructGrid](#) grid, HYPRE\_Int part, HYPRE\_Int \*periodic)
- HYPRE\_Int [HYPRE\\_SStructGridSetNumGhost](#) ([HYPRE\\_SStructGrid](#) grid, HYPRE\_Int \*num\_ghost)
- #define [HYPRE\\_SSTRUCT\\_VARIABLE\\_UNDEFINED](#) -1
- #define [HYPRE\\_SSTRUCT\\_VARIABLE\\_CELL](#) 0
- #define [HYPRE\\_SSTRUCT\\_VARIABLE\\_NODE](#) 1
- #define [HYPRE\\_SSTRUCT\\_VARIABLE\\_XFACE](#) 2
- #define [HYPRE\\_SSTRUCT\\_VARIABLE\\_YFACE](#) 3
- #define [HYPRE\\_SSTRUCT\\_VARIABLE\\_ZFACE](#) 4
- #define [HYPRE\\_SSTRUCT\\_VARIABLE\\_XEDGE](#) 5
- #define [HYPRE\\_SSTRUCT\\_VARIABLE\\_YEDGE](#) 6
- #define [HYPRE\\_SSTRUCT\\_VARIABLE\\_ZEDGE](#) 7

### SStruct Stencils

- typedef struct hypr\_SStructStencil\_struct \* [HYPRE\\_SStructStencil](#)
- HYPRE\_Int [HYPRE\\_SStructStencilCreate](#) (HYPRE\_Int ndim, HYPRE\_Int size, [HYPRE\\_SStructStencil](#) \*stencil)
- HYPRE\_Int [HYPRE\\_SStructStencilDestroy](#) ([HYPRE\\_SStructStencil](#) stencil)
- HYPRE\_Int [HYPRE\\_SStructStencilSetEntry](#) ([HYPRE\\_SStructStencil](#) stencil, HYPRE\_Int entry, HYPRE\_Int \*offset, HYPRE\_Int var)

## SStruct Graphs

- typedef struct hypre\_SStructGraph\_struct \* [HYPRE\\_SStructGraph](#)
- HYPRE\_Int [HYPRE\\_SStructGraphCreate](#) (MPI\_Comm comm, [HYPRE\\_SStructGrid](#) grid, [HYPRE\\_SStructGraph](#) \*graph)
- HYPRE\_Int [HYPRE\\_SStructGraphDestroy](#) ([HYPRE\\_SStructGraph](#) graph)
- HYPRE\_Int [HYPRE\\_SStructGraphSetDomainGrid](#) ([HYPRE\\_SStructGraph](#) graph, [HYPRE\\_SStructGrid](#) domain\_grid)
- HYPRE\_Int [HYPRE\\_SStructGraphSetStencil](#) ([HYPRE\\_SStructGraph](#) graph, HYPRE\_Int part, HYPRE\_Int var, [HYPRE\\_SStructStencil](#) stencil)
- HYPRE\_Int [HYPRE\\_SStructGraphSetFEM](#) ([HYPRE\\_SStructGraph](#) graph, HYPRE\_Int part)
- HYPRE\_Int [HYPRE\\_SStructGraphSetFEMSparsity](#) ([HYPRE\\_SStructGraph](#) graph, HYPRE\_Int part, HYPRE\_Int nspare, HYPRE\_Int \*sparsity)
- HYPRE\_Int [HYPRE\\_SStructGraphAddEntries](#) ([HYPRE\\_SStructGraph](#) graph, HYPRE\_Int part, HYPRE\_Int \*index, HYPRE\_Int var, HYPRE\_Int to\_part, HYPRE\_Int \*to\_index, HYPRE\_Int to\_var)
- HYPRE\_Int [HYPRE\\_SStructGraphAssemble](#) ([HYPRE\\_SStructGraph](#) graph)
- HYPRE\_Int [HYPRE\\_SStructGraphSetObjectType](#) ([HYPRE\\_SStructGraph](#) graph, HYPRE\_Int type)

## SStruct Matrices

- typedef struct hypre\_SStructMatrix\_struct \* [HYPRE\\_SStructMatrix](#)
- HYPRE\_Int [HYPRE\\_SStructMatrixCreate](#) (MPI\_Comm comm, [HYPRE\\_SStructGraph](#) graph, [HYPRE\\_SStructMatrix](#) \*matrix)
- HYPRE\_Int [HYPRE\\_SStructMatrixDestroy](#) ([HYPRE\\_SStructMatrix](#) matrix)
- HYPRE\_Int [HYPRE\\_SStructMatrixInitialize](#) ([HYPRE\\_SStructMatrix](#) matrix)
- HYPRE\_Int [HYPRE\\_SStructMatrixSetValues](#) ([HYPRE\\_SStructMatrix](#) matrix, HYPRE\_Int part, HYPRE\_Int \*index, HYPRE\_Int var, HYPRE\_Int nentries, HYPRE\_Int \*entries, HYPRE\_Complex \*values)
- HYPRE\_Int [HYPRE\\_SStructMatrixAddToValues](#) ([HYPRE\\_SStructMatrix](#) matrix, HYPRE\_Int part, HYPRE\_Int \*index, HYPRE\_Int var, HYPRE\_Int nentries, HYPRE\_Int \*entries, HYPRE\_Complex \*values)
- HYPRE\_Int [HYPRE\\_SStructMatrixAddFEMValues](#) ([HYPRE\\_SStructMatrix](#) matrix, HYPRE\_Int part, HYPRE\_Int \*index, HYPRE\_Complex \*values)
- HYPRE\_Int [HYPRE\\_SStructMatrixGetValues](#) ([HYPRE\\_SStructMatrix](#) matrix, HYPRE\_Int part, HYPRE\_Int \*index, HYPRE\_Int var, HYPRE\_Int nentries, HYPRE\_Int \*entries, HYPRE\_Complex \*values)
- HYPRE\_Int [HYPRE\\_SStructMatrixGetFEMValues](#) ([HYPRE\\_SStructMatrix](#) matrix, HYPRE\_Int part, HYPRE\_Int \*index, HYPRE\_Complex \*values)
- HYPRE\_Int [HYPRE\\_SStructMatrixSetBoxValues](#) ([HYPRE\\_SStructMatrix](#) matrix, HYPRE\_Int part, HYPRE\_Int \*ilower, HYPRE\_Int \*iupper, HYPRE\_Int var, HYPRE\_Int nentries, HYPRE\_Int \*entries, HYPRE\_Complex \*values)
- HYPRE\_Int [HYPRE\\_SStructMatrixAddToBoxValues](#) ([HYPRE\\_SStructMatrix](#) matrix, HYPRE\_Int part, HYPRE\_Int \*ilower, HYPRE\_Int \*iupper, HYPRE\_Int var, HYPRE\_Int nentries, HYPRE\_Int \*entries, HYPRE\_Complex \*values)
- HYPRE\_Int [HYPRE\\_SStructMatrixSetBoxValues2](#) ([HYPRE\\_SStructMatrix](#) matrix, HYPRE\_Int part, HYPRE\_Int \*ilower, HYPRE\_Int \*iupper, HYPRE\_Int var, HYPRE\_Int nentries, HYPRE\_Int \*entries, HYPRE\_Int \*vilower, HYPRE\_Int \*viupper, HYPRE\_Complex \*values)
- HYPRE\_Int [HYPRE\\_SStructMatrixAddToBoxValues2](#) ([HYPRE\\_SStructMatrix](#) matrix, HYPRE\_Int part, HYPRE\_Int \*ilower, HYPRE\_Int \*iupper, HYPRE\_Int var, HYPRE\_Int nentries, HYPRE\_Int \*entries, HYPRE\_Int \*vilower, HYPRE\_Int \*viupper, HYPRE\_Complex \*values)
- HYPRE\_Int [HYPRE\\_SStructMatrixAssemble](#) ([HYPRE\\_SStructMatrix](#) matrix)
- HYPRE\_Int [HYPRE\\_SStructMatrixGetBoxValues](#) ([HYPRE\\_SStructMatrix](#) matrix, HYPRE\_Int part, HYPRE\_Int \*ilower, HYPRE\_Int \*iupper, HYPRE\_Int var, HYPRE\_Int nentries, HYPRE\_Int \*entries, HYPRE\_Complex \*values)
- HYPRE\_Int [HYPRE\\_SStructMatrixGetBoxValues2](#) ([HYPRE\\_SStructMatrix](#) matrix, HYPRE\_Int part, HYPRE\_Int \*ilower, HYPRE\_Int \*iupper, HYPRE\_Int var, HYPRE\_Int nentries, HYPRE\_Int \*entries, HYPRE\_Int \*vilower, HYPRE\_Int \*viupper, HYPRE\_Complex \*values)
- HYPRE\_Int [HYPRE\\_SStructMatrixSetSymmetric](#) ([HYPRE\\_SStructMatrix](#) matrix, HYPRE\_Int part, HYPRE\_Int var, HYPRE\_Int to\_var, HYPRE\_Int symmetric)

- HYPRE\_Int [HYPRE\\_SStructMatrixSetNSSymmetric](#) (HYPRE\_SStructMatrix matrix, HYPRE\_Int symmetric)
- HYPRE\_Int [HYPRE\\_SStructMatrixSetObjectType](#) (HYPRE\_SStructMatrix matrix, HYPRE\_Int type)
- HYPRE\_Int [HYPRE\\_SStructMatrixGetObject](#) (HYPRE\_SStructMatrix matrix, void \*\*object)
- HYPRE\_Int [HYPRE\\_SStructMatrixPrint](#) (const char \*filename, HYPRE\_SStructMatrix matrix, HYPRE\_Int all)

### SStruct Vectors

- typedef struct hypre\_SStructVector\_struct \* [HYPRE\\_SStructVector](#)
- HYPRE\_Int [HYPRE\\_SStructVectorCreate](#) (MPI\_Comm comm, HYPRE\_SStructGrid grid, HYPRE\_SStructVector \*vector)
- HYPRE\_Int [HYPRE\\_SStructVectorDestroy](#) (HYPRE\_SStructVector vector)
- HYPRE\_Int [HYPRE\\_SStructVectorInitialize](#) (HYPRE\_SStructVector vector)
- HYPRE\_Int [HYPRE\\_SStructVectorSetValues](#) (HYPRE\_SStructVector vector, HYPRE\_Int part, HYPRE\_Int \*index, HYPRE\_Int var, HYPRE\_Complex \*value)
- HYPRE\_Int [HYPRE\\_SStructVectorAddToValues](#) (HYPRE\_SStructVector vector, HYPRE\_Int part, HYPRE\_Int \*index, HYPRE\_Int var, HYPRE\_Complex \*value)
- HYPRE\_Int [HYPRE\\_SStructVectorAddFEMValues](#) (HYPRE\_SStructVector vector, HYPRE\_Int part, HYPRE\_Int \*index, HYPRE\_Complex \*values)
- HYPRE\_Int [HYPRE\\_SStructVectorGetValues](#) (HYPRE\_SStructVector vector, HYPRE\_Int part, HYPRE\_Int \*index, HYPRE\_Int var, HYPRE\_Complex \*value)
- HYPRE\_Int [HYPRE\\_SStructVectorGetFEMValues](#) (HYPRE\_SStructVector vector, HYPRE\_Int part, HYPRE\_Int \*index, HYPRE\_Complex \*values)
- HYPRE\_Int [HYPRE\\_SStructVectorSetBoxValues](#) (HYPRE\_SStructVector vector, HYPRE\_Int part, HYPRE\_Int \*ilower, HYPRE\_Int \*iupper, HYPRE\_Int var, HYPRE\_Complex \*values)
- HYPRE\_Int [HYPRE\\_SStructVectorAddToBoxValues](#) (HYPRE\_SStructVector vector, HYPRE\_Int part, HYPRE\_Int \*ilower, HYPRE\_Int \*iupper, HYPRE\_Int var, HYPRE\_Complex \*values)
- HYPRE\_Int [HYPRE\\_SStructVectorSetBoxValues2](#) (HYPRE\_SStructVector vector, HYPRE\_Int part, HYPRE\_Int \*ilower, HYPRE\_Int \*iupper, HYPRE\_Int var, HYPRE\_Int \*vilower, HYPRE\_Int \*viupper, HYPRE\_Complex \*values)
- HYPRE\_Int [HYPRE\\_SStructVectorAddToBoxValues2](#) (HYPRE\_SStructVector vector, HYPRE\_Int part, HYPRE\_Int \*ilower, HYPRE\_Int \*iupper, HYPRE\_Int var, HYPRE\_Int \*vilower, HYPRE\_Int \*viupper, HYPRE\_Complex \*values)
- HYPRE\_Int [HYPRE\\_SStructVectorAssemble](#) (HYPRE\_SStructVector vector)
- HYPRE\_Int [HYPRE\\_SStructVectorGetBoxValues](#) (HYPRE\_SStructVector vector, HYPRE\_Int part, HYPRE\_Int \*ilower, HYPRE\_Int \*iupper, HYPRE\_Int var, HYPRE\_Complex \*values)
- HYPRE\_Int [HYPRE\\_SStructVectorGetBoxValues2](#) (HYPRE\_SStructVector vector, HYPRE\_Int part, HYPRE\_Int \*ilower, HYPRE\_Int \*iupper, HYPRE\_Int var, HYPRE\_Int \*vilower, HYPRE\_Int \*viupper, HYPRE\_Complex \*values)
- HYPRE\_Int [HYPRE\\_SStructVectorGather](#) (HYPRE\_SStructVector vector)
- HYPRE\_Int [HYPRE\\_SStructVectorSetObjectType](#) (HYPRE\_SStructVector vector, HYPRE\_Int type)
- HYPRE\_Int [HYPRE\\_SStructVectorGetObject](#) (HYPRE\_SStructVector vector, void \*\*object)
- HYPRE\_Int [HYPRE\\_SStructVectorPrint](#) (const char \*filename, HYPRE\_SStructVector vector, HYPRE\_Int all)

### 3.2.1 Detailed Description

This interface represents a semi-structured-grid conceptual view of a linear system.

@memo A semi-structured-grid conceptual interface

### 3.2.2 Macro Definition Documentation

#### 3.2.2.1 HYPRE\_SSTRUCT\_VARIABLE\_CELL

```
#define HYPRE_SSTRUCT_VARIABLE_CELL 0
```

### 3.2.2.2 HYPRE\_SSTRUCT\_VARIABLE\_NODE

```
#define HYPRE_SSTRUCT_VARIABLE_NODE 1
```

### 3.2.2.3 HYPRE\_SSTRUCT\_VARIABLE\_UNDEFINED

```
#define HYPRE_SSTRUCT_VARIABLE_UNDEFINED -1
```

### 3.2.2.4 HYPRE\_SSTRUCT\_VARIABLE\_XEDGE

```
#define HYPRE_SSTRUCT_VARIABLE_XEDGE 5
```

### 3.2.2.5 HYPRE\_SSTRUCT\_VARIABLE\_XFACE

```
#define HYPRE_SSTRUCT_VARIABLE_XFACE 2
```

### 3.2.2.6 HYPRE\_SSTRUCT\_VARIABLE\_YEDGE

```
#define HYPRE_SSTRUCT_VARIABLE_YEDGE 6
```

### 3.2.2.7 HYPRE\_SSTRUCT\_VARIABLE\_YFACE

```
#define HYPRE_SSTRUCT_VARIABLE_YFACE 3
```

### 3.2.2.8 HYPRE\_SSTRUCT\_VARIABLE\_ZEDGE

```
#define HYPRE_SSTRUCT_VARIABLE_ZEDGE 7
```

### 3.2.2.9 HYPRE\_SSTRUCT\_VARIABLE\_ZFACE

```
#define HYPRE_SSTRUCT_VARIABLE_ZFACE 4
```

## 3.2.3 Typedef Documentation

### 3.2.3.1 HYPRE\_SStructGraph

```
typedef struct hypre_SStructGraph_struct* HYPRE\_SStructGraph
```

The graph object is used to describe the nonzero structure of a matrix.

### 3.2.3.2 HYPRE\_SStructGrid

```
typedef struct hypre_SStructGrid_struct* HYPRE_SStructGrid
```

A grid object is constructed out of several structured "parts" and an optional unstructured "part". Each structured part has its own abstract index space.

### 3.2.3.3 HYPRE\_SStructMatrix

```
typedef struct hypre_SStructMatrix_struct* HYPRE_SStructMatrix
```

The matrix object.

### 3.2.3.4 HYPRE\_SStructStencil

```
typedef struct hypre_SStructStencil_struct* HYPRE_SStructStencil
```

The stencil object.

### 3.2.3.5 HYPRE\_SStructVariable

```
typedef HYPRE_Int HYPRE_SStructVariable
```

An enumerated type that supports cell centered, node centered, face centered, and edge centered variables. Face centered variables are split into x-face, y-face, and z-face variables, and edge centered variables are split into x-edge, y-edge, and z-edge variables. The edge centered variable types are only used in 3D. In 2D, edge centered variables are handled by the face centered types.

Variables are referenced relative to an abstract (cell centered) index in the following way:

- cell centered variables are aligned with the index;
- node centered variables are aligned with the cell corner at relative index (1/2, 1/2, 1/2);
- x-face, y-face, and z-face centered variables are aligned with the faces at relative indexes (1/2, 0, 0), (0, 1/2, 0), and (0, 0, 1/2), respectively;
- x-edge, y-edge, and z-edge centered variables are aligned with the edges at relative indexes (0, 1/2, 1/2), (1/2, 0, 1/2), and (1/2, 1/2, 0), respectively.

The supported identifiers are:

- HYPRE\_SSTRUCT\_VARIABLE\_CELL
- HYPRE\_SSTRUCT\_VARIABLE\_NODE
- HYPRE\_SSTRUCT\_VARIABLE\_XFACE
- HYPRE\_SSTRUCT\_VARIABLE\_YFACE
- HYPRE\_SSTRUCT\_VARIABLE\_ZFACE
- HYPRE\_SSTRUCT\_VARIABLE\_XEDGE
- HYPRE\_SSTRUCT\_VARIABLE\_YEDGE
- HYPRE\_SSTRUCT\_VARIABLE\_ZEDGE

NOTE: Although variables are referenced relative to a unique abstract cell-centered index, some variables are associated with multiple grid cells. For example, node centered variables in 3D are associated with 8 cells (away from boundaries). Although grid cells are distributed uniquely to different processes, variables may be owned by multiple processes because they may be associated with multiple cells.

### 3.2.3.6 HYPRE\_SStructVector

```
typedef struct hypre_SStructVector_struct* HYPRE_SStructVector
```

The vector object.

## 3.2.4 Function Documentation

### 3.2.4.1 HYPRE\_SStructGraphAddEntries()

```
HYPRE_Int HYPRE_SStructGraphAddEntries (
    HYPRE_SStructGraph graph,
    HYPRE_Int part,
    HYPRE_Int * index,
    HYPRE_Int var,
    HYPRE_Int to_part,
    HYPRE_Int * to_index,
    HYPRE_Int to_var )
```

Add a non-stencil graph entry at a particular index. This graph entry is appended to the existing graph entries, and is referenced as such.

NOTE: Users are required to set graph entries on all processes that own the associated variables. This means that some data will be multiply defined.

### 3.2.4.2 HYPRE\_SStructGraphAssemble()

```
HYPRE_Int HYPRE_SStructGraphAssemble (
    HYPRE_SStructGraph graph )
```

Finalize the construction of the graph before using.

### 3.2.4.3 HYPRE\_SStructGraphCreate()

```
HYPRE_Int HYPRE_SStructGraphCreate (
    MPI_Comm comm,
    HYPRE_SStructGrid grid,
    HYPRE_SStructGraph * graph )
```

Create a graph object.

### 3.2.4.4 HYPRE\_SStructGraphDestroy()

```
HYPRE_Int HYPRE_SStructGraphDestroy (
    HYPRE_SStructGraph graph )
```

Destroy a graph object.



**3.2.4.5 HYPRE\_SStructGraphSetDomainGrid()**

```
HYPRE_Int HYPRE_SStructGraphSetDomainGrid (
    HYPRE_SStructGraph graph,
    HYPRE_SStructGrid domain_grid )
```

Set the domain grid.

**3.2.4.6 HYPRE\_SStructGraphSetFEM()**

```
HYPRE_Int HYPRE_SStructGraphSetFEM (
    HYPRE_SStructGraph graph,
    HYPRE_Int part )
```

Indicate that an FEM approach will be used to set matrix values on this part.

**3.2.4.7 HYPRE\_SStructGraphSetFEMSparsity()**

```
HYPRE_Int HYPRE_SStructGraphSetFEMSparsity (
    HYPRE_SStructGraph graph,
    HYPRE_Int part,
    HYPRE_Int nsparse,
    HYPRE_Int * sparsity )
```

Set the finite element stiffness matrix sparsity. This overrides the default full sparsity pattern described below.

Array *sparsity* contains *nsparse* row/column tuples (I,J) that indicate the nonzeros of the local stiffness matrix. The layout of the values passed into the routine [HYPRE\\_SStructMatrixAddFEMValues](#) is determined here.

The default sparsity is full (each variable is coupled to all others), and the values passed into the routine [HYPRE\\_SStructMatrixAddFEMValues](#) are assumed to be by rows (that is, column indices vary fastest).

**3.2.4.8 HYPRE\_SStructGraphSetObjectType()**

```
HYPRE_Int HYPRE_SStructGraphSetObjectType (
    HYPRE_SStructGraph graph,
    HYPRE_Int type )
```

Set the storage type of the associated matrix object. It is used before AddEntries and Assemble to compute the right ranks in the graph.

NOTE: This routine is only necessary for implementation reasons, and will eventually be removed.

See also

[HYPRE\\_SStructMatrixSetObjectType](#)

### 3.2.4.9 HYPRE\_SStructGraphSetStencil()

```
HYPRE_Int HYPRE_SStructGraphSetStencil (
    HYPRE_SStructGraph graph,
    HYPRE_Int part,
    HYPRE_Int var,
    HYPRE_SStructStencil stencil )
```

Set the stencil for a variable on a structured part of the grid.

### 3.2.4.10 HYPRE\_SStructGridAddUnstructuredPart()

```
HYPRE_Int HYPRE_SStructGridAddUnstructuredPart (
    HYPRE_SStructGrid grid,
    HYPRE_Int ilower,
    HYPRE_Int iupper )
```

Add an unstructured part to the grid. The variables in the unstructured part of the grid are referenced by a global rank between 0 and the total number of unstructured variables minus one. Each process owns some unique consecutive range of variables, defined by *ilower* and *iupper*.

NOTE: This is just a placeholder. This part of the interface is not finished.

### 3.2.4.11 HYPRE\_SStructGridAddVariables()

```
HYPRE_Int HYPRE_SStructGridAddVariables (
    HYPRE_SStructGrid grid,
    HYPRE_Int part,
    HYPRE_Int * index,
    HYPRE_Int nvars,
    HYPRE_SStructVariable * vartypes )
```

Describe additional variables that live at a particular index. These variables are appended to the array of variables set in [HYPRE\\_SStructGridSetVariables](#), and are referenced as such.

NOTE: This routine is not yet supported.

### 3.2.4.12 HYPRE\_SStructGridAssemble()

```
HYPRE_Int HYPRE_SStructGridAssemble (
    HYPRE_SStructGrid grid )
```

Finalize the construction of the grid before using.

### 3.2.4.13 HYPRE\_SStructGridCreate()

```
HYPRE_Int HYPRE_SStructGridCreate (
    MPI_Comm comm,
    HYPRE_Int ndim,
    HYPRE_Int nparts,
    HYPRE_SStructGrid * grid )
```

Create an *ndim*-dimensional grid object with *nparts* structured parts.

**3.2.4.14 HYPRE\_SStructGridDestroy()**

```
HYPRE_Int HYPRE_SStructGridDestroy (
    HYPRE_SStructGrid grid )
```

Destroy a grid object. An object should be explicitly destroyed using this destructor when the user's code no longer needs direct access to it. Once destroyed, the object must not be referenced again. Note that the object may not be deallocated at the completion of this call, since there may be internal package references to the object. The object will then be destroyed when all internal reference counts go to zero.

**3.2.4.15 HYPRE\_SStructGridSetExtents()**

```
HYPRE_Int HYPRE_SStructGridSetExtents (
    HYPRE_SStructGrid grid,
    HYPRE_Int part,
    HYPRE_Int * ilower,
    HYPRE_Int * iupper )
```

Set the extents for a box on a structured part of the grid.

**3.2.4.16 HYPRE\_SStructGridSetFEMOrdering()**

```
HYPRE_Int HYPRE_SStructGridSetFEMOrdering (
    HYPRE_SStructGrid grid,
    HYPRE_Int part,
    HYPRE_Int * ordering )
```

Set the ordering of variables in a finite element problem. This overrides the default ordering described below.

Array *ordering* is composed of blocks of size  $(1 + ndim)$ . Each block indicates a specific variable in the element and the ordering of the blocks defines the ordering of the variables. A block contains a variable number followed by an offset direction relative to the element's center. For example, a block containing (2, 1, -1, 0) means variable 2 on the edge located in the (1, -1, 0) direction from the center of the element. Note that here variable 2 must be of type ZEDGE for this to make sense. The *ordering* array must account for all variables in the element. This routine can only be called after [HYPRE\\_SStructGridSetVariables](#).

The default ordering for element variables (var, i, j, k) varies fastest in index i, followed by j, then k, then var. For example, if var 0, var 1, and var 2 are declared to be XFACE, YFACE, and NODE variables, respectively, then the default ordering (in 2D) would first list the two XFACE variables, then the two YFACE variables, then the four NODE variables as follows:

(0,-1,0), (0,1,0), (1,0,-1), (1,0,1), (2,-1,-1), (2,1,-1), (2,-1,1), (2,1,1)

### 3.2.4.17 HYPRE\_SStructGridSetNeighborPart()

```
HYPRE_Int HYPRE_SStructGridSetNeighborPart (
    HYPRE_SStructGrid grid,
    HYPRE_Int part,
    HYPRE_Int * ilower,
    HYPRE_Int * iupper,
    HYPRE_Int nbor_part,
    HYPRE_Int * nbor_ilower,
    HYPRE_Int * nbor_iupper,
    HYPRE_Int * index_map,
    HYPRE_Int * index_dir )
```

Describe how regions just outside of a part relate to other parts. This is done a box at a time.

Parts *part* and *nbor\_part* must be different, except in the case where only cell-centered data is used.

Indexes should increase from *ilower* to *iupper*. It is not necessary that indexes increase from *nbor\_ilower* to *nbor\_iupper*.

The *index\_map* describes the mapping of indexes 0, 1, and 2 on part *part* to the corresponding indexes on part *nbor\_part*. For example, triple (1, 2, 0) means that indexes 0, 1, and 2 on part *part* map to indexes 1, 2, and 0 on part *nbor\_part*, respectively.

The *index\_dir* describes the direction of the mapping in *index\_map*. For example, triple (1, 1, -1) means that for indexes 0 and 1, increasing values map to increasing values on *nbor\_part*, while for index 2, decreasing values map to increasing values.

NOTE: All parts related to each other via this routine must have an identical list of variables and variable types. For example, if part 0 has only two variables on it, a cell centered variable and a node centered variable, and we declare part 1 to be a neighbor of part 0, then part 1 must also have only two variables on it, and they must be of type cell and node. In addition, variables associated with FACES or EDGES must be grouped together and listed in X, Y, Z order. This is to enable the code to correctly associate variables on one part with variables on its neighbor part when a coordinate transformation is specified. For example, an XFACE variable on one part may correspond to a YFACE variable on a neighbor part under a particular transformation, and the code determines this association by assuming that the variable lists are as noted here.

### 3.2.4.18 HYPRE\_SStructGridSetNumGhost()

```
HYPRE_Int HYPRE_SStructGridSetNumGhost (
    HYPRE_SStructGrid grid,
    HYPRE_Int * num_ghost )
```

Setting ghost in the sgrids.

### 3.2.4.19 HYPRE\_SStructGridSetPeriodic()

```
HYPRE_Int HYPRE_SStructGridSetPeriodic (
    HYPRE_SStructGrid grid,
    HYPRE_Int part,
    HYPRE_Int * periodic )
```

Set the periodicity on a particular part.

The argument *periodic* is an *ndim-dimensional* integer array that contains the periodicity for each dimension. A zero value for a dimension means non-periodic, while a nonzero value means periodic and contains the actual period. For example, periodicity in the first and third dimensions for a 10x11x12 part is indicated by the array [10,0,12].

NOTE: Some of the solvers in hypre have power-of-two restrictions on the size of the periodic dimensions.

### 3.2.4.20 HYPRE\_SStructGridSetSharedPart()

```
HYPRE_Int HYPRE_SStructGridSetSharedPart (
    HYPRE_SStructGrid grid,
    HYPRE_Int part,
    HYPRE_Int * ilower,
    HYPRE_Int * iupper,
    HYPRE_Int * offset,
    HYPRE_Int shared_part,
    HYPRE_Int * shared_ilower,
    HYPRE_Int * shared_iupper,
    HYPRE_Int * shared_offset,
    HYPRE_Int * index_map,
    HYPRE_Int * index_dir )
```

Describe how regions inside a part are shared with regions in other parts.

Parts *part* and *shared\_part* must be different.

Indexes should increase from *ilower* to *iupper*. It is not necessary that indexes increase from *shared\_ilower* to *shared\_iupper*. This is to maintain consistency with the `SetNeighborPart` function, which is also able to describe shared regions but in a more limited fashion.

The *offset* is a triple (in 3D) used to indicate the dimensionality of the shared set of data and its position with respect to the box extents *ilower* and *iupper* on part *part*. The dimensionality is given by the number of 0's in the triple, and the position is given by plus or minus 1's. For example: (0, 0, 0) indicates sharing of all data in the given box; (1, 0, 0) indicates sharing of data on the faces in the (1, 0, 0) direction; (1, 0, -1) indicates sharing of data on the edges in the (1, 0, -1) direction; and (1, -1, 1) indicates sharing of data on the nodes in the (1, -1, 1) direction. To ensure the dimensionality, it is required that for every nonzero entry, the corresponding extents of the box are the same. For example, if *offset* is (0, 1, 0), then (2, 1, 3) and (10, 1, 15) are valid box extents, whereas (2, 1, 3) and (10, 7, 15) are invalid (because 1 and 7 are not the same).

The *shared\_offset* is used in the same way as *offset*, but with respect to the box extents *shared\_ilower* and *shared\_iupper* on part *shared\_part*.

The *index\_map* describes the mapping of indexes 0, 1, and 2 on part *part* to the corresponding indexes on part *shared\_part*. For example, triple (1, 2, 0) means that indexes 0, 1, and 2 on part *part* map to indexes 1, 2, and 0 on part *shared\_part*, respectively.

The *index\_dir* describes the direction of the mapping in *index\_map*. For example, triple (1, 1, -1) means that for indexes 0 and 1, increasing values map to increasing values on *shared\_part*, while for index 2, decreasing values map to increasing values.

NOTE: All parts related to each other via this routine must have an identical list of variables and variable types. For example, if part 0 has only two variables on it, a cell centered variable and a node centered variable, and we declare part 1 to have shared regions with part 0, then part 1 must also have only two variables on it, and they must be of type cell and node. In addition, variables associated with FACES or EDGES must be grouped together and listed in X, Y, Z order. This is to enable the code to correctly associate variables on one part with variables on a shared part when a coordinate transformation is specified. For example, an XFACE variable on one part may correspond to a YFACE variable on a shared part under a particular transformation, and the code determines this association by assuming that the variable lists are as noted here.

### 3.2.4.21 HYPRE\_SStructGridSetVariables()

```
HYPRE_Int HYPRE_SStructGridSetVariables (
    HYPRE_SStructGrid grid,
    HYPRE_Int part,
    HYPRE_Int nvars,
    HYPRE_SStructVariable * vartypes )
```

Describe the variables that live on a structured part of the grid.

### 3.2.4.22 HYPRE\_SStructMatrixAddFEMValues()

```
HYPRE_Int HYPRE_SStructMatrixAddFEMValues (
    HYPRE_SStructMatrix matrix,
    HYPRE_Int part,
    HYPRE_Int * index,
    HYPRE_Complex * values )
```

Add finite element stiffness matrix coefficients index by index. The layout of the data in *values* is determined by the routines [HYPRE\\_SStructGridSetFEMOrdering](#) and [HYPRE\\_SStructGraphSetFEMSparsity](#).

### 3.2.4.23 HYPRE\_SStructMatrixAddToBoxValues()

```
HYPRE_Int HYPRE_SStructMatrixAddToBoxValues (
    HYPRE_SStructMatrix matrix,
    HYPRE_Int part,
    HYPRE_Int * ilower,
    HYPRE_Int * iupper,
    HYPRE_Int var,
    HYPRE_Int nentries,
    HYPRE_Int * entries,
    HYPRE_Complex * values )
```

Add to matrix coefficients a box at a time. The data in *values* is ordered as in [HYPRE\\_SStructMatrixSetBoxValues](#).

NOTE: Users are required to set values on all processes that own the associated variables. This means that some data will be multiply defined.

NOTE: The entries in this routine must all be of stencil type. Also, they must all represent couplings to the same variable type.

### 3.2.4.24 HYPRE\_SStructMatrixAddToBoxValues2()

```
HYPRE_Int HYPRE_SStructMatrixAddToBoxValues2 (
    HYPRE_SStructMatrix matrix,
    HYPRE_Int part,
    HYPRE_Int * ilower,
    HYPRE_Int * iupper,
    HYPRE_Int var,
    HYPRE_Int nentries,
    HYPRE_Int * entries,
    HYPRE_Int * vilower,
    HYPRE_Int * viupper,
    HYPRE_Complex * values )
```

Add to matrix coefficients a box at a time. The data in *values* is ordered as in [HYPRE\\_SStructMatrixSetBoxValues2](#).

**3.2.4.25 HYPRE\_SStructMatrixAddToValues()**

```

HYPRE_Int HYPRE_SStructMatrixAddToValues (
    HYPRE_SStructMatrix matrix,
    HYPRE_Int part,
    HYPRE_Int * index,
    HYPRE_Int var,
    HYPRE_Int nentries,
    HYPRE_Int * entries,
    HYPRE_Complex * values )

```

Add to matrix coefficients index by index. The *values* array is of length *nentries*.

NOTE: For better efficiency, use [HYPRE\\_SStructMatrixAddToBoxValues](#) to set coefficients a box at a time.

NOTE: Users are required to set values on all processes that own the associated variables. This means that some data will be multiply defined.

NOTE: The entries in this routine must all be of the same type: either stencil or non-stencil, but not both. Also, if they are stencil entries, they must all represent couplings to the same variable type.

**3.2.4.26 HYPRE\_SStructMatrixAssemble()**

```

HYPRE_Int HYPRE_SStructMatrixAssemble (
    HYPRE_SStructMatrix matrix )

```

Finalize the construction of the matrix before using.

**3.2.4.27 HYPRE\_SStructMatrixCreate()**

```

HYPRE_Int HYPRE_SStructMatrixCreate (
    MPI_Comm comm,
    HYPRE_SStructGraph graph,
    HYPRE_SStructMatrix * matrix )

```

Create a matrix object.

**3.2.4.28 HYPRE\_SStructMatrixDestroy()**

```

HYPRE_Int HYPRE_SStructMatrixDestroy (
    HYPRE_SStructMatrix matrix )

```

Destroy a matrix object.

### 3.2.4.29 HYPRE\_SStructMatrixGetBoxValues()

```
HYPRE_Int HYPRE_SStructMatrixGetBoxValues (
    HYPRE_SStructMatrix matrix,
    HYPRE_Int part,
    HYPRE_Int * ilower,
    HYPRE_Int * iupper,
    HYPRE_Int var,
    HYPRE_Int nentries,
    HYPRE_Int * entries,
    HYPRE_Complex * values )
```

Get matrix coefficients a box at a time. The data in *values* is ordered as in [HYPRE\\_SStructMatrixSetBoxValues](#).

NOTE: Users may get values on any process that owns the associated variables.

NOTE: The entries in this routine must all be of stencil type. Also, they must all represent couplings to the same variable type.

### 3.2.4.30 HYPRE\_SStructMatrixGetBoxValues2()

```
HYPRE_Int HYPRE_SStructMatrixGetBoxValues2 (
    HYPRE_SStructMatrix matrix,
    HYPRE_Int part,
    HYPRE_Int * ilower,
    HYPRE_Int * iupper,
    HYPRE_Int var,
    HYPRE_Int nentries,
    HYPRE_Int * entries,
    HYPRE_Int * vilower,
    HYPRE_Int * viupper,
    HYPRE_Complex * values )
```

Get matrix coefficients a box at a time. The data in *values* is ordered as in [HYPRE\\_SStructMatrixSetBoxValues2](#).

### 3.2.4.31 HYPRE\_SStructMatrixGetFEMValues()

```
HYPRE_Int HYPRE_SStructMatrixGetFEMValues (
    HYPRE_SStructMatrix matrix,
    HYPRE_Int part,
    HYPRE_Int * index,
    HYPRE_Complex * values )
```

Get finite element stiffness matrix coefficients index by index. The layout of the data in *values* is determined by the routines [HYPRE\\_SStructGridSetFEMOrdering](#) and [HYPRE\\_SStructGraphSetFEMSparsity](#).

### 3.2.4.32 HYPRE\_SStructMatrixGetObject()

```
HYPRE_Int HYPRE_SStructMatrixGetObject (
    HYPRE_SStructMatrix matrix,
    void ** object )
```

Get a reference to the constructed matrix object.

See also

[HYPRE\\_SStructMatrixSetObjectType](#)



**3.2.4.33 HYPRE\_SStructMatrixGetValues()**

```

HYPRE_Int HYPRE_SStructMatrixGetValues (
    HYPRE_SStructMatrix matrix,
    HYPRE_Int part,
    HYPRE_Int * index,
    HYPRE_Int var,
    HYPRE_Int nentries,
    HYPRE_Int * entries,
    HYPRE_Complex * values )

```

Get matrix coefficients index by index. The *values* array is of length *nentries*.

NOTE: For better efficiency, use [HYPRE\\_SStructMatrixGetBoxValues](#) to get coefficients a box at a time.

NOTE: Users may get values on any process that owns the associated variables.

NOTE: The entries in this routine must all be of the same type: either stencil or non-stencil, but not both. Also, if they are stencil entries, they must all represent couplings to the same variable type (there are no such restrictions for non-stencil entries).

**3.2.4.34 HYPRE\_SStructMatrixInitialize()**

```

HYPRE_Int HYPRE_SStructMatrixInitialize (
    HYPRE_SStructMatrix matrix )

```

Prepare a matrix object for setting coefficient values.

**3.2.4.35 HYPRE\_SStructMatrixPrint()**

```

HYPRE_Int HYPRE_SStructMatrixPrint (
    const char * filename,
    HYPRE_SStructMatrix matrix,
    HYPRE_Int all )

```

Print the matrix to file. This is mainly for debugging purposes.

**3.2.4.36 HYPRE\_SStructMatrixSetBoxValues()**

```

HYPRE_Int HYPRE_SStructMatrixSetBoxValues (
    HYPRE_SStructMatrix matrix,
    HYPRE_Int part,
    HYPRE_Int * ilower,
    HYPRE_Int * iupper,
    HYPRE_Int var,
    HYPRE_Int nentries,
    HYPRE_Int * entries,
    HYPRE_Complex * values )

```

Set matrix coefficients a box at a time. The data in *values* is ordered as follows:

```

m = 0;
for (k = ilower[2]; k <= iupper[2]; k++)
  for (j = ilower[1]; j <= iupper[1]; j++)
    for (i = ilower[0]; i <= iupper[0]; i++)
      for (entry = 0; entry < nentries; entry++)
        {
          values[m] = ...;
          m++;
        }

```

NOTE: Users are required to set values on all processes that own the associated variables. This means that some data will be multiply defined.

NOTE: The entries in this routine must all be of the same type: either stencil or non-stencil, but not both. Also, if they are stencil entries, they must all represent couplings to the same variable type (there are no such restrictions for non-stencil entries).

### 3.2.4.37 HYPRE\_SStructMatrixSetBoxValues2()

```

HYPRE_Int HYPRE_SStructMatrixSetBoxValues2 (
    HYPRE_SStructMatrix matrix,
    HYPRE_Int part,
    HYPRE_Int * ilower,
    HYPRE_Int * iupper,
    HYPRE_Int var,
    HYPRE_Int nentries,
    HYPRE_Int * entries,
    HYPRE_Int * vilower,
    HYPRE_Int * viupper,
    HYPRE_Complex * values )

```

Set matrix coefficients a box at a time. The *values* array is logically box shaped with value-box extents *vilower* and *viupper* that must contain the set-box extents *ilower* and *iupper*. The data in the *values* array is ordered as in [HYPRE\\_SStructMatrixSetBoxValues](#), but based on the value-box extents.

### 3.2.4.38 HYPRE\_SStructMatrixSetNSSymmetric()

```

HYPRE_Int HYPRE_SStructMatrixSetNSSymmetric (
    HYPRE_SStructMatrix matrix,
    HYPRE_Int symmetric )

```

Define symmetry properties for all non-stencil matrix entries.

### 3.2.4.39 HYPRE\_SStructMatrixSetObjectType()

```

HYPRE_Int HYPRE_SStructMatrixSetObjectType (
    HYPRE_SStructMatrix matrix,
    HYPRE_Int type )

```

Set the storage type of the matrix object to be constructed. Currently, *type* can be either `HYPRE_SSTRUCT` (the default), `HYPRE_STRUCT`, or `HYPRE_PARCSR`.

See also

[HYPRE\\_SStructMatrixGetObject](#)

**3.2.4.40 HYPRE\_SStructMatrixSetSymmetric()**

```
HYPRE_Int HYPRE_SStructMatrixSetSymmetric (
    HYPRE_SStructMatrix matrix,
    HYPRE_Int part,
    HYPRE_Int var,
    HYPRE_Int to_var,
    HYPRE_Int symmetric )
```

Define symmetry properties for the stencil entries in the matrix. The boolean argument *symmetric* is applied to stencil entries on part *part* that couple variable *var* to variable *to\_var*. A value of -1 may be used for *part*, *var*, or *to\_var* to specify "all". For example, if *part* and *to\_var* are set to -1, then the boolean is applied to stencil entries on all parts that couple variable *var* to all other variables.

By default, matrices are assumed to be nonsymmetric. Significant storage savings can be made if the matrix is symmetric.

**3.2.4.41 HYPRE\_SStructMatrixSetValues()**

```
HYPRE_Int HYPRE_SStructMatrixSetValues (
    HYPRE_SStructMatrix matrix,
    HYPRE_Int part,
    HYPRE_Int * index,
    HYPRE_Int var,
    HYPRE_Int nentries,
    HYPRE_Int * entries,
    HYPRE_Complex * values )
```

Set matrix coefficients index by index. The *values* array is of length *nentries*.

NOTE: For better efficiency, use [HYPRE\\_SStructMatrixSetBoxValues](#) to set coefficients a box at a time.

NOTE: Users are required to set values on all processes that own the associated variables. This means that some data will be multiply defined.

NOTE: The entries in this routine must all be of the same type: either stencil or non-stencil, but not both. Also, if they are stencil entries, they must all represent couplings to the same variable type (there are no such restrictions for non-stencil entries).

**3.2.4.42 HYPRE\_SStructStencilCreate()**

```
HYPRE_Int HYPRE_SStructStencilCreate (
    HYPRE_Int ndim,
    HYPRE_Int size,
    HYPRE_SStructStencil * stencil )
```

Create a stencil object for the specified number of spatial dimensions and stencil entries.

**3.2.4.43 HYPRE\_SStructStencilDestroy()**

```
HYPRE_Int HYPRE_SStructStencilDestroy (
    HYPRE_SStructStencil stencil )
```

Destroy a stencil object.

#### 3.2.4.44 HYPRE\_SStructStencilSetEntry()

```
HYPRE_Int HYPRE_SStructStencilSetEntry (
    HYPRE_SStructStencil stencil,
    HYPRE_Int entry,
    HYPRE_Int * offset,
    HYPRE_Int var )
```

Set a stencil entry.

#### 3.2.4.45 HYPRE\_SStructVectorAddFEMValues()

```
HYPRE_Int HYPRE_SStructVectorAddFEMValues (
    HYPRE_SStructVector vector,
    HYPRE_Int part,
    HYPRE_Int * index,
    HYPRE_Complex * values )
```

Add finite element vector coefficients index by index. The layout of the data in *values* is determined by the routine [HYPRE\\_SStructGridSetFEMOrdering](#).

#### 3.2.4.46 HYPRE\_SStructVectorAddToBoxValues()

```
HYPRE_Int HYPRE_SStructVectorAddToBoxValues (
    HYPRE_SStructVector vector,
    HYPRE_Int part,
    HYPRE_Int * ilower,
    HYPRE_Int * iupper,
    HYPRE_Int var,
    HYPRE_Complex * values )
```

Add to vector coefficients a box at a time. The data in *values* is ordered as in [HYPRE\\_SStructVectorSetBoxValues](#).

NOTE: Users are required to set values on all processes that own the associated variables. This means that some data will be multiply defined.

#### 3.2.4.47 HYPRE\_SStructVectorAddToBoxValues2()

```
HYPRE_Int HYPRE_SStructVectorAddToBoxValues2 (
    HYPRE_SStructVector vector,
    HYPRE_Int part,
    HYPRE_Int * ilower,
    HYPRE_Int * iupper,
    HYPRE_Int var,
    HYPRE_Int * vilower,
    HYPRE_Int * viupper,
    HYPRE_Complex * values )
```

Add to vector coefficients a box at a time. The data in *values* is ordered as in [HYPRE\\_SStructVectorSetBoxValues2](#).

**3.2.4.48 HYPRE\_SStructVectorAddToValues()**

```
HYPRE_Int HYPRE_SStructVectorAddToValues (
    HYPRE_SStructVector vector,
    HYPRE_Int part,
    HYPRE_Int * index,
    HYPRE_Int var,
    HYPRE_Complex * value )
```

Add to vector coefficients index by index.

NOTE: For better efficiency, use [HYPRE\\_SStructVectorAddToBoxValues](#) to set coefficients a box at a time.

NOTE: Users are required to set values on all processes that own the associated variables. This means that some data will be multiply defined.

**3.2.4.49 HYPRE\_SStructVectorAssemble()**

```
HYPRE_Int HYPRE_SStructVectorAssemble (
    HYPRE_SStructVector vector )
```

Finalize the construction of the vector before using.

**3.2.4.50 HYPRE\_SStructVectorCreate()**

```
HYPRE_Int HYPRE_SStructVectorCreate (
    MPI_Comm comm,
    HYPRE_SStructGrid grid,
    HYPRE_SStructVector * vector )
```

Create a vector object.

**3.2.4.51 HYPRE\_SStructVectorDestroy()**

```
HYPRE_Int HYPRE_SStructVectorDestroy (
    HYPRE_SStructVector vector )
```

Destroy a vector object.

**3.2.4.52 HYPRE\_SStructVectorGather()**

```
HYPRE_Int HYPRE_SStructVectorGather (
    HYPRE_SStructVector vector )
```

Gather vector data so that efficient `GetValues` can be done. This routine must be called prior to calling `GetValues` to ensure that correct and consistent values are returned, especially for non cell-centered data that is shared between more than one processor.

### 3.2.4.53 HYPRE\_SStructVectorGetBoxValues()

```
HYPRE_Int HYPRE_SStructVectorGetBoxValues (
    HYPRE_SStructVector vector,
    HYPRE_Int part,
    HYPRE_Int * ilower,
    HYPRE_Int * iupper,
    HYPRE_Int var,
    HYPRE_Complex * values )
```

Get vector coefficients a box at a time. The data in *values* is ordered as in [HYPRE\\_SStructVectorSetBoxValues](#). Users must first call the routine [HYPRE\\_SStructVectorGather](#) to ensure that data owned by multiple processes is correct.

NOTE: Users may only get values on processes that own the associated variables.

### 3.2.4.54 HYPRE\_SStructVectorGetBoxValues2()

```
HYPRE_Int HYPRE_SStructVectorGetBoxValues2 (
    HYPRE_SStructVector vector,
    HYPRE_Int part,
    HYPRE_Int * ilower,
    HYPRE_Int * iupper,
    HYPRE_Int var,
    HYPRE_Int * vilower,
    HYPRE_Int * viupper,
    HYPRE_Complex * values )
```

Get vector coefficients a box at a time. The data in *values* is ordered as in [HYPRE\\_SStructVectorSetBoxValues2](#).

### 3.2.4.55 HYPRE\_SStructVectorGetFEMValues()

```
HYPRE_Int HYPRE_SStructVectorGetFEMValues (
    HYPRE_SStructVector vector,
    HYPRE_Int part,
    HYPRE_Int * index,
    HYPRE_Complex * values )
```

Get finite element vector coefficients index by index. The layout of the data in *values* is determined by the routine [HYPRE\\_SStructGridSetFEMOrdering](#). Users must first call the routine [HYPRE\\_SStructVectorGather](#) to ensure that data owned by multiple processes is correct.

### 3.2.4.56 HYPRE\_SStructVectorGetObject()

```
HYPRE_Int HYPRE_SStructVectorGetObject (
    HYPRE_SStructVector vector,
    void ** object )
```

Get a reference to the constructed vector object.

See also

[HYPRE\\_SStructVectorSetObjectType](#)

**3.2.4.57 HYPRE\_SStructVectorGetValues()**

```
HYPRE_Int HYPRE_SStructVectorGetValues (
    HYPRE_SStructVector vector,
    HYPRE_Int part,
    HYPRE_Int * index,
    HYPRE_Int var,
    HYPRE_Complex * value )
```

Get vector coefficients index by index. Users must first call the routine [HYPRE\\_SStructVectorGather](#) to ensure that data owned by multiple processes is correct.

NOTE: For better efficiency, use [HYPRE\\_SStructVectorGetBoxValues](#) to get coefficients a box at a time.

NOTE: Users may only get values on processes that own the associated variables.

**3.2.4.58 HYPRE\_SStructVectorInitialize()**

```
HYPRE_Int HYPRE_SStructVectorInitialize (
    HYPRE_SStructVector vector )
```

Prepare a vector object for setting coefficient values.

**3.2.4.59 HYPRE\_SStructVectorPrint()**

```
HYPRE_Int HYPRE_SStructVectorPrint (
    const char * filename,
    HYPRE_SStructVector vector,
    HYPRE_Int all )
```

Print the vector to file. This is mainly for debugging purposes.

**3.2.4.60 HYPRE\_SStructVectorSetBoxValues()**

```
HYPRE_Int HYPRE_SStructVectorSetBoxValues (
    HYPRE_SStructVector vector,
    HYPRE_Int part,
    HYPRE_Int * ilower,
    HYPRE_Int * iupper,
    HYPRE_Int var,
    HYPRE_Complex * values )
```

Set vector coefficients a box at a time. The data in *values* is ordered as follows:

```
m = 0;
for (k = ilower[2]; k <= iupper[2]; k++)
    for (j = ilower[1]; j <= iupper[1]; j++)
        for (i = ilower[0]; i <= iupper[0]; i++)
        {
            values[m] = ...;
            m++;
        }
```

NOTE: Users are required to set values on all processes that own the associated variables. This means that some data will be multiply defined.

### 3.2.4.61 HYPRE\_SStructVectorSetBoxValues2()

```
HYPRE_Int HYPRE_SStructVectorSetBoxValues2 (
    HYPRE_SStructVector vector,
    HYPRE_Int part,
    HYPRE_Int * ilower,
    HYPRE_Int * iupper,
    HYPRE_Int var,
    HYPRE_Int * vilower,
    HYPRE_Int * viupper,
    HYPRE_Complex * values )
```

Set vector coefficients a box at a time. The *values* array is logically box shaped with value-box extents *vilower* and *viupper* that must contain the set-box extents *ilower* and *iupper*. The data in the *values* array is ordered as in [HYPRE\\_SStructVectorSetBoxValues](#), but based on the value-box extents.

### 3.2.4.62 HYPRE\_SStructVectorSetObjectType()

```
HYPRE_Int HYPRE_SStructVectorSetObjectType (
    HYPRE_SStructVector vector,
    HYPRE_Int type )
```

Set the storage type of the vector object to be constructed. Currently, *type* can be either HYPRE\_SSTRUCT (the default), HYPRE\_STRUCT, or HYPRE\_PARCSR.

See also

[HYPRE\\_SStructVectorGetObject](#)

### 3.2.4.63 HYPRE\_SStructVectorSetValues()

```
HYPRE_Int HYPRE_SStructVectorSetValues (
    HYPRE_SStructVector vector,
    HYPRE_Int part,
    HYPRE_Int * index,
    HYPRE_Int var,
    HYPRE_Complex * value )
```

Set vector coefficients index by index.

NOTE: For better efficiency, use [HYPRE\\_SStructVectorSetBoxValues](#) to set coefficients a box at a time.

NOTE: Users are required to set values on all processes that own the associated variables. This means that some data will be multiply defined.



## 3.3 IJ System Interface

### IJ Matrices

- typedef struct hypre\_IJMatrix\_struct \* [HYPRE\\_IJMatrix](#)
- HYPRE\_Int [HYPRE\\_IJMatrixCreate](#) (MPI\_Comm comm, HYPRE\_BigInt ilower, HYPRE\_BigInt iupper, HYPRE\_BigInt jlower, HYPRE\_BigInt jupper, [HYPRE\\_IJMatrix](#) \*matrix)
- HYPRE\_Int [HYPRE\\_IJMatrixDestroy](#) ([HYPRE\\_IJMatrix](#) matrix)
- HYPRE\_Int [HYPRE\\_IJMatrixInitialize](#) ([HYPRE\\_IJMatrix](#) matrix)
- HYPRE\_Int [HYPRE\\_IJMatrixInitialize\\_v2](#) ([HYPRE\\_IJMatrix](#) matrix, HYPRE\_MemoryLocation memory\_↵ location)
- HYPRE\_Int [HYPRE\\_IJMatrixSetValues](#) ([HYPRE\\_IJMatrix](#) matrix, HYPRE\_Int nrows, HYPRE\_Int \*ncols, const HYPRE\_BigInt \*rows, const HYPRE\_BigInt \*cols, const HYPRE\_Complex \*values)
- HYPRE\_Int [HYPRE\\_IJMatrixSetConstantValues](#) ([HYPRE\\_IJMatrix](#) matrix, HYPRE\_Complex value)
- HYPRE\_Int [HYPRE\\_IJMatrixAddToValues](#) ([HYPRE\\_IJMatrix](#) matrix, HYPRE\_Int nrows, HYPRE\_Int \*ncols, const HYPRE\_BigInt \*rows, const HYPRE\_BigInt \*cols, const HYPRE\_Complex \*values)
- HYPRE\_Int [HYPRE\\_IJMatrixSetValues2](#) ([HYPRE\\_IJMatrix](#) matrix, HYPRE\_Int nrows, HYPRE\_Int \*ncols, const HYPRE\_BigInt \*rows, const HYPRE\_Int \*row\_indexes, const HYPRE\_BigInt \*cols, const HYPRE\_↵ Complex \*values)
- HYPRE\_Int [HYPRE\\_IJMatrixAddToValues2](#) ([HYPRE\\_IJMatrix](#) matrix, HYPRE\_Int nrows, HYPRE\_Int \*ncols, const HYPRE\_BigInt \*rows, const HYPRE\_Int \*row\_indexes, const HYPRE\_BigInt \*cols, const HYPRE\_↵ Complex \*values)
- HYPRE\_Int [HYPRE\\_IJMatrixAssemble](#) ([HYPRE\\_IJMatrix](#) matrix)
- HYPRE\_Int [HYPRE\\_IJMatrixGetRowCounts](#) ([HYPRE\\_IJMatrix](#) matrix, HYPRE\_Int nrows, HYPRE\_BigInt \*rows, HYPRE\_Int \*ncols)
- HYPRE\_Int [HYPRE\\_IJMatrixGetValues](#) ([HYPRE\\_IJMatrix](#) matrix, HYPRE\_Int nrows, HYPRE\_Int \*ncols, HYPRE\_BigInt \*rows, HYPRE\_BigInt \*cols, HYPRE\_Complex \*values)
- HYPRE\_Int [HYPRE\\_IJMatrixSetObjectType](#) ([HYPRE\\_IJMatrix](#) matrix, HYPRE\_Int type)
- HYPRE\_Int [HYPRE\\_IJMatrixGetObjectType](#) ([HYPRE\\_IJMatrix](#) matrix, HYPRE\_Int \*type)
- HYPRE\_Int [HYPRE\\_IJMatrixGetLocalRange](#) ([HYPRE\\_IJMatrix](#) matrix, HYPRE\_BigInt \*ilower, HYPRE\_↵ BigInt \*iupper, HYPRE\_BigInt \*jlower, HYPRE\_BigInt \*jupper)
- HYPRE\_Int [HYPRE\\_IJMatrixGetObject](#) ([HYPRE\\_IJMatrix](#) matrix, void \*\*object)
- HYPRE\_Int [HYPRE\\_IJMatrixSetRowSizes](#) ([HYPRE\\_IJMatrix](#) matrix, const HYPRE\_Int \*sizes)
- HYPRE\_Int [HYPRE\\_IJMatrixSetDiagOffdSizes](#) ([HYPRE\\_IJMatrix](#) matrix, const HYPRE\_Int \*diag\_sizes, const HYPRE\_Int \*offdiag\_sizes)
- HYPRE\_Int [HYPRE\\_IJMatrixSetMaxOffProcElmts](#) ([HYPRE\\_IJMatrix](#) matrix, HYPRE\_Int max\_off\_proc\_↵ elmts)
- HYPRE\_Int [HYPRE\\_IJMatrixSetPrintLevel](#) ([HYPRE\\_IJMatrix](#) matrix, HYPRE\_Int print\_level)
- HYPRE\_Int [HYPRE\\_IJMatrixSetOMPFlag](#) ([HYPRE\\_IJMatrix](#) matrix, HYPRE\_Int omp\_flag)
- HYPRE\_Int [HYPRE\\_IJMatrixRead](#) (const char \*filename, MPI\_Comm comm, HYPRE\_Int type, [HYPRE\\_IJMatrix](#) \*matrix)
- HYPRE\_Int [HYPRE\\_IJMatrixPrint](#) ([HYPRE\\_IJMatrix](#) matrix, const char \*filename)

### IJ Vectors

- typedef struct hypre\_IJVector\_struct \* [HYPRE\\_IJVector](#)
- HYPRE\_Int [HYPRE\\_IJVectorCreate](#) (MPI\_Comm comm, HYPRE\_BigInt jlower, HYPRE\_BigInt jupper, [HYPRE\\_IJVector](#) \*vector)
- HYPRE\_Int [HYPRE\\_IJVectorDestroy](#) ([HYPRE\\_IJVector](#) vector)
- HYPRE\_Int [HYPRE\\_IJVectorInitialize](#) ([HYPRE\\_IJVector](#) vector)
- HYPRE\_Int [HYPRE\\_IJVectorInitialize\\_v2](#) ([HYPRE\\_IJVector](#) vector, HYPRE\_MemoryLocation memory\_↵ location)
- HYPRE\_Int [HYPRE\\_IJVectorSetMaxOffProcElmts](#) ([HYPRE\\_IJVector](#) vector, HYPRE\_Int max\_off\_proc\_↵ elmts)

- HYPRE\_Int [HYPRE\\_IJVectorSetValues](#) (HYPRE\_IJVector vector, HYPRE\_Int nvalues, const HYPRE\_BigInt \*indices, const HYPRE\_Complex \*values)
- HYPRE\_Int [HYPRE\\_IJVectorAddToValues](#) (HYPRE\_IJVector vector, HYPRE\_Int nvalues, const HYPRE\_BigInt \*indices, const HYPRE\_Complex \*values)
- HYPRE\_Int [HYPRE\\_IJVectorAssemble](#) (HYPRE\_IJVector vector)
- HYPRE\_Int [HYPRE\\_IJVectorGetValues](#) (HYPRE\_IJVector vector, HYPRE\_Int nvalues, const HYPRE\_BigInt \*indices, HYPRE\_Complex \*values)
- HYPRE\_Int [HYPRE\\_IJVectorSetObjectType](#) (HYPRE\_IJVector vector, HYPRE\_Int type)
- HYPRE\_Int [HYPRE\\_IJVectorGetObjectType](#) (HYPRE\_IJVector vector, HYPRE\_Int \*type)
- HYPRE\_Int [HYPRE\\_IJVectorGetLocalRange](#) (HYPRE\_IJVector vector, HYPRE\_BigInt \*jlower, HYPRE\_BigInt \*jupper)
- HYPRE\_Int [HYPRE\\_IJVectorGetObject](#) (HYPRE\_IJVector vector, void \*\*object)
- HYPRE\_Int [HYPRE\\_IJVectorSetPrintLevel](#) (HYPRE\_IJVector vector, HYPRE\_Int print\_level)
- HYPRE\_Int [HYPRE\\_IJVectorRead](#) (const char \*filename, MPI\_Comm comm, HYPRE\_Int type, HYPRE\_IJVector \*vector)
- HYPRE\_Int [HYPRE\\_IJVectorPrint](#) (HYPRE\_IJVector vector, const char \*filename)

### 3.3.1 Detailed Description

This interface represents a linear-algebraic conceptual view of a linear system. The 'I' and 'J' in the name are meant to be mnemonic for the traditional matrix notation A(I,J).

@memo A linear-algebraic conceptual interface

### 3.3.2 Typedef Documentation

#### 3.3.2.1 HYPRE\_IJMatrix

```
typedef struct hypre_IJMatrix_struct* HYPRE\_IJMatrix
```

The matrix object.

#### 3.3.2.2 HYPRE\_IJVector

```
typedef struct hypre_IJVector_struct* HYPRE\_IJVector
```

The vector object.

### 3.3.3 Function Documentation

#### 3.3.3.1 HYPRE\_IJMatrixAddToValues()

```
HYPRE_Int HYPRE_IJMatrixAddToValues (
    HYPRE\_IJMatrix matrix,
    HYPRE_Int nrows,
    HYPRE_Int * ncols,
    const HYPRE_BigInt * rows,
    const HYPRE_BigInt * cols,
    const HYPRE_Complex * values )
```

Adds to values for *nrows* rows or partial rows of the matrix. Usage details are analogous to [HYPRE\\_IJMatrixSetValues](#). Adds to any previous values at the specified locations, or, if there was no value there before, inserts a new one. AddToValues can be used to add to values on other processors.

Note that a threaded version (threaded over the number of rows) will be called if HYPRE\_IJMatrixSetOMPFlag is set to a value != 0. This requires that rows[i] != rows[j] for i!= j and is only efficient if a large number of rows is added in one call to HYPRE\_IJMatrixAddToValues.

Not collective.

### 3.3.3.2 HYPRE\_IJMatrixAddToValues2()

```
HYPRE_Int HYPRE_IJMatrixAddToValues2 (
    HYPRE_IJMatrix matrix,
    HYPRE_Int nrows,
    HYPRE_Int * ncols,
    const HYPRE_BigInt * rows,
    const HYPRE_Int * row_indexes,
    const HYPRE_BigInt * cols,
    const HYPRE_Complex * values )
```

Adds to values for *nrows* rows or partial rows of the matrix.

Same as `IJMatrixAddToValues`, but with an additional *row\_indexes* array that provides indexes into the *cols* and *values* arrays. Because of this, there can be gaps between the row data in these latter two arrays.

### 3.3.3.3 HYPRE\_IJMatrixAssemble()

```
HYPRE_Int HYPRE_IJMatrixAssemble (
    HYPRE_IJMatrix matrix )
```

Finalize the construction of the matrix before using.

### 3.3.3.4 HYPRE\_IJMatrixCreate()

```
HYPRE_Int HYPRE_IJMatrixCreate (
    MPI_Comm comm,
    HYPRE_BigInt ilower,
    HYPRE_BigInt iupper,
    HYPRE_BigInt jlower,
    HYPRE_BigInt jupper,
    HYPRE_IJMatrix * matrix )
```

Create a matrix object. Each process owns some unique consecutive range of rows, indicated by the global row indices *ilower* and *iupper*. The row data is required to be such that the value of *ilower* on any process *p* be exactly one more than the value of *iupper* on process *p* − 1. Note that the first row of the global matrix may start with any integer value. In particular, one may use zero- or one-based indexing.

For square matrices, *jlower* and *jupper* typically should match *ilower* and *iupper*, respectively. For rectangular matrices, *jlower* and *jupper* should define a partitioning of the columns. This partitioning must be used for any vector *v* that will be used in matrix-vector products with the rectangular matrix. The matrix data structure may use *jlower* and *jupper* to store the diagonal blocks (rectangular in general) of the matrix separately from the rest of the matrix.

Collective.

### 3.3.3.5 HYPRE\_IJMatrixDestroy()

```
HYPRE_Int HYPRE_IJMatrixDestroy (
    HYPRE_IJMatrix matrix )
```

Destroy a matrix object. An object should be explicitly destroyed using this destructor when the user's code no longer needs direct access to it. Once destroyed, the object must not be referenced again. Note that the object may not be deallocated at the completion of this call, since there may be internal package references to the object. The object will then be destroyed when all internal reference counts go to zero.

### 3.3.3.6 HYPRE\_IJMatrixGetLocalRange()

```
HYPRE_Int HYPRE_IJMatrixGetLocalRange (
    HYPRE_IJMatrix matrix,
    HYPRE_BigInt * ilower,
    HYPRE_BigInt * iupper,
    HYPRE_BigInt * jlower,
    HYPRE_BigInt * jupper )
```

Gets range of rows owned by this processor and range of column partitioning for this processor.

### 3.3.3.7 HYPRE\_IJMatrixGetObject()

```
HYPRE_Int HYPRE_IJMatrixGetObject (
    HYPRE_IJMatrix matrix,
    void ** object )
```

Get a reference to the constructed matrix object.

See also

[HYPRE\\_IJMatrixSetObjectType](#)

### 3.3.3.8 HYPRE\_IJMatrixGetObjectType()

```
HYPRE_Int HYPRE_IJMatrixGetObjectType (
    HYPRE_IJMatrix matrix,
    HYPRE_Int * type )
```

Get the storage type of the constructed matrix object.

### 3.3.3.9 HYPRE\_IJMatrixGetRowCounts()

```
HYPRE_Int HYPRE_IJMatrixGetRowCounts (
    HYPRE_IJMatrix matrix,
    HYPRE_Int nrows,
    HYPRE_BigInt * rows,
    HYPRE_Int * ncols )
```

Gets number of nonzeros elements for *nrows* rows specified in *rows* and returns them in *ncols*, which needs to be allocated by the user.

### 3.3.3.10 HYPRE\_IJMatrixGetValues()

```
HYPRE_Int HYPRE_IJMatrixGetValues (
    HYPRE_IJMatrix matrix,
    HYPRE_Int nrows,
    HYPRE_Int * ncols,
    HYPRE_BigInt * rows,
    HYPRE_BigInt * cols,
    HYPRE_Complex * values )
```

Gets values for *nrows* rows or partial rows of the matrix. Usage details are mostly analogous to [HYPRE\\_IJMatrixSetValues](#). Note that if *nrows* is negative, the routine will return the column\_indices and matrix coefficients of the (-*nrows*) rows contained in *rows*.

### 3.3.3.11 HYPRE\_IJMatrixInitialize()

```
HYPRE_Int HYPRE_IJMatrixInitialize (
    HYPRE_IJMatrix matrix )
```

Prepare a matrix object for setting coefficient values. This routine will also re-initialize an already assembled matrix, allowing users to modify coefficient values.

### 3.3.3.12 HYPRE\_IJMatrixInitialize\_v2()

```
HYPRE_Int HYPRE_IJMatrixInitialize_v2 (
    HYPRE_IJMatrix matrix,
    HYPRE_MemoryLocation memory_location )
```

Prepare a matrix object for setting coefficient values. This routine will also re-initialize an already assembled matrix, allowing users to modify coefficient values. This routine also specifies the memory location, i.e. host or device.

### 3.3.3.13 HYPRE\_IJMatrixPrint()

```
HYPRE_Int HYPRE_IJMatrixPrint (
    HYPRE_IJMatrix matrix,
    const char * filename )
```

Print the matrix to file. This is mainly for debugging purposes.

### 3.3.3.14 HYPRE\_IJMatrixRead()

```
HYPRE_Int HYPRE_IJMatrixRead (
    const char * filename,
    MPI_Comm comm,
    HYPRE_Int type,
    HYPRE_IJMatrix * matrix )
```

Read the matrix from file. This is mainly for debugging purposes.

### 3.3.3.15 HYPRE\_IJMatrixSetConstantValues()

```
HYPRE_Int HYPRE_IJMatrixSetConstantValues (
    HYPRE_IJMatrix matrix,
    HYPRE_Complex value )
```

Sets all matrix coefficients of an already assembled matrix to *value*

### 3.3.3.16 HYPRE\_IJMatrixSetDiagOffdSizes()

```
HYPRE_Int HYPRE_IJMatrixSetDiagOffdSizes (
    HYPRE_IJMatrix matrix,
    const HYPRE_Int * diag_sizes,
    const HYPRE_Int * offdiag_sizes )
```

(Optional) Sets the exact number of nonzeros in each row of the diagonal and off-diagonal blocks. The diagonal block is the submatrix whose column numbers correspond to rows owned by this process, and the off-diagonal block is everything else. The arrays *diag\_sizes* and *offdiag\_sizes* contain estimated sizes for each row of the diagonal and off-diagonal blocks, respectively. This routine can significantly improve the efficiency of matrix construction, and should always be utilized if possible.

Not collective.

### 3.3.3.17 HYPRE\_IJMatrixSetMaxOffProcElmts()

```
HYPRE_Int HYPRE_IJMatrixSetMaxOffProcElmts (
    HYPRE_IJMatrix matrix,
    HYPRE_Int max_off_proc_elmts )
```

(Optional) Sets the maximum number of elements that are expected to be set (or added) on other processors from this processor. This routine can significantly improve the efficiency of matrix construction, and should always be utilized if possible.

Not collective.

### 3.3.3.18 HYPRE\_IJMatrixSetObjectType()

```
HYPRE_Int HYPRE_IJMatrixSetObjectType (
    HYPRE_IJMatrix matrix,
    HYPRE_Int type )
```

Set the storage type of the matrix object to be constructed. Currently, *type* can only be `HYPRE_PARCSR`.

Not collective, but must be the same on all processes.

See also

[HYPRE\\_IJMatrixGetObject](#)

### 3.3.3.19 HYPRE\_IJMatrixSetOMPFlag()

```
HYPRE_Int HYPRE_IJMatrixSetOMPFlag (
    HYPRE_IJMatrix matrix,
    HYPRE_Int omp_flag )
```

(Optional) if set, will use a threaded version of `HYPRE_IJMatrixSetValues` and `HYPRE_IJMatrixAddToValues`. This is only useful if a large number of rows is set or added to at once.

NOTE that the values in the rows array of `HYPRE_IJMatrixSetValues` or `HYPRE_IJMatrixAddToValues` must be different from each other !!!

This option is VERY inefficient if only a small number of rows is set or added at once and/or if reallocation of storage is required and/or if values are added to off processor values.

**3.3.3.20 HYPRE\_IJMatrixSetPrintLevel()**

```
HYPRE_Int HYPRE_IJMatrixSetPrintLevel (
    HYPRE_IJMatrix matrix,
    HYPRE_Int print_level )
```

(Optional) Sets the print level, if the user wants to print error messages. The default is 0, i.e. no error messages are printed.

**3.3.3.21 HYPRE\_IJMatrixSetRowSizes()**

```
HYPRE_Int HYPRE_IJMatrixSetRowSizes (
    HYPRE_IJMatrix matrix,
    const HYPRE_Int * sizes )
```

(Optional) Set the max number of nonzeros to expect in each row. The array *sizes* contains estimated sizes for each row on this process. This call can significantly improve the efficiency of matrix construction, and should always be utilized if possible.

Not collective.

**3.3.3.22 HYPRE\_IJMatrixSetValues()**

```
HYPRE_Int HYPRE_IJMatrixSetValues (
    HYPRE_IJMatrix matrix,
    HYPRE_Int nrows,
    HYPRE_Int * ncols,
    const HYPRE_BigInt * rows,
    const HYPRE_BigInt * cols,
    const HYPRE_Complex * values )
```

Sets values for *nrows* rows or partial rows of the matrix. The arrays *ncols* and *rows* are of dimension *nrows* and contain the number of columns in each row and the row indices, respectively. The array *cols* contains the column indices for each of the *rows*, and is ordered by rows. The data in the *values* array corresponds directly to the column entries in *cols*. Erases any previous values at the specified locations and replaces them with new ones, or, if there was no value there before, inserts a new one if set locally. Note that it is not possible to set values on other processors. If one tries to set a value from proc *i* on proc *j*, proc *i* will erase all previous occurrences of this value in its stack (including values generated with *AddToValues*), and treat it like a zero value. The actual value needs to be set on proc *j*.

Note that a threaded version (threaded over the number of rows) will be called if *HYPRE\_IJMatrixSetOMPFlag* is set to a value  $\neq 0$ . This requires that *rows[i] != rows[j]* for  $i \neq j$  and is only efficient if a large number of rows is set in one call to *HYPRE\_IJMatrixSetValues*.

Not collective.

**3.3.3.23 HYPRE\_IJMatrixSetValues2()**

```
HYPRE_Int HYPRE_IJMatrixSetValues2 (
    HYPRE_IJMatrix matrix,
    HYPRE_Int nrows,
    HYPRE_Int * ncols,
    const HYPRE_BigInt * rows,
    const HYPRE_Int * row_indexes,
    const HYPRE_BigInt * cols,
    const HYPRE_Complex * values )
```

Sets values for *nrows* rows or partial rows of the matrix.

Same as *IJMatrixSetValues*, but with an additional *row\_indexes* array that provides indexes into the *cols* and *values* arrays. Because of this, there can be gaps between the row data in these latter two arrays.

### 3.3.3.24 HYPRE\_IJVectorAddToValues()

```
HYPRE_Int HYPRE_IJVectorAddToValues (
    HYPRE_IJVector vector,
    HYPRE_Int nvalues,
    const HYPRE_BigInt * indices,
    const HYPRE_Complex * values )
```

Adds to values in vector. Usage details are analogous to [HYPRE\\_IJVectorSetValues](#). Adds to any previous values at the specified locations, or, if there was no value there before, inserts a new one. AddToValues can be used to add to values on other processors.

Not collective.

### 3.3.3.25 HYPRE\_IJVectorAssemble()

```
HYPRE_Int HYPRE_IJVectorAssemble (
    HYPRE_IJVector vector )
```

Finalize the construction of the vector before using.

### 3.3.3.26 HYPRE\_IJVectorCreate()

```
HYPRE_Int HYPRE_IJVectorCreate (
    MPI_Comm comm,
    HYPRE_BigInt jlower,
    HYPRE_BigInt jupper,
    HYPRE_IJVector * vector )
```

Create a vector object. Each process owns some unique consecutive range of vector unknowns, indicated by the global indices *jlower* and *jupper*. The data is required to be such that the value of *jlower* on any process *p* be exactly one more than the value of *jupper* on process *p* - 1. Note that the first index of the global vector may start with any integer value. In particular, one may use zero- or one-based indexing.

Collective.

### 3.3.3.27 HYPRE\_IJVectorDestroy()

```
HYPRE_Int HYPRE_IJVectorDestroy (
    HYPRE_IJVector vector )
```

Destroy a vector object. An object should be explicitly destroyed using this destructor when the user's code no longer needs direct access to it. Once destroyed, the object must not be referenced again. Note that the object may not be deallocated at the completion of this call, since there may be internal package references to the object. The object will then be destroyed when all internal reference counts go to zero.

### 3.3.3.28 HYPRE\_IJVectorGetLocalRange()

```
HYPRE_Int HYPRE_IJVectorGetLocalRange (
    HYPRE_IJVector vector,
    HYPRE_BigInt * jlower,
    HYPRE_BigInt * jupper )
```

Returns range of the part of the vector owned by this processor.



**3.3.3.29 HYPRE\_IJVectorGetObject()**

```
HYPRE_Int HYPRE_IJVectorGetObject (
    HYPRE_IJVector vector,
    void ** object )
```

Get a reference to the constructed vector object.

See also

[HYPRE\\_IJVectorSetObjectType](#)

**3.3.3.30 HYPRE\_IJVectorGetObjectType()**

```
HYPRE_Int HYPRE_IJVectorGetObjectType (
    HYPRE_IJVector vector,
    HYPRE_Int * type )
```

Get the storage type of the constructed vector object.

**3.3.3.31 HYPRE\_IJVectorGetValues()**

```
HYPRE_Int HYPRE_IJVectorGetValues (
    HYPRE_IJVector vector,
    HYPRE_Int nvalues,
    const HYPRE_BigInt * indices,
    HYPRE_Complex * values )
```

Gets values in vector. Usage details are analogous to [HYPRE\\_IJVectorSetValues](#).

Not collective.

**3.3.3.32 HYPRE\_IJVectorInitialize()**

```
HYPRE_Int HYPRE_IJVectorInitialize (
    HYPRE_IJVector vector )
```

Prepare a vector object for setting coefficient values. This routine will also re-initialize an already assembled vector, allowing users to modify coefficient values.

**3.3.3.33 HYPRE\_IJVectorInitialize\_v2()**

```
HYPRE_Int HYPRE_IJVectorInitialize_v2 (
    HYPRE_IJVector vector,
    HYPRE_MemoryLocation memory_location )
```

Prepare a vector object for setting coefficient values. This routine will also re-initialize an already assembled vector, allowing users to modify coefficient values. This routine also specifies the memory location, i.e. host or device.

### 3.3.3.34 HYPRE\_IJVectorPrint()

```
HYPRE_Int HYPRE_IJVectorPrint (
    HYPRE_IJVector vector,
    const char * filename )
```

Print the vector to file. This is mainly for debugging purposes.

### 3.3.3.35 HYPRE\_IJVectorRead()

```
HYPRE_Int HYPRE_IJVectorRead (
    const char * filename,
    MPI_Comm comm,
    HYPRE_Int type,
    HYPRE_IJVector * vector )
```

Read the vector from file. This is mainly for debugging purposes.

### 3.3.3.36 HYPRE\_IJVectorSetMaxOffProcElmts()

```
HYPRE_Int HYPRE_IJVectorSetMaxOffProcElmts (
    HYPRE_IJVector vector,
    HYPRE_Int max_off_proc_elmts )
```

(Optional) Sets the maximum number of elements that are expected to be set (or added) on other processors from this processor. This routine can significantly improve the efficiency of matrix construction, and should always be utilized if possible.

Not collective.

### 3.3.3.37 HYPRE\_IJVectorSetObjectType()

```
HYPRE_Int HYPRE_IJVectorSetObjectType (
    HYPRE_IJVector vector,
    HYPRE_Int type )
```

Set the storage type of the vector object to be constructed. Currently, *type* can only be `HYPRE_PARCSR`.

Not collective, but must be the same on all processes.

See also

[HYPRE\\_IJVectorGetObject](#)

### 3.3.3.38 HYPRE\_IJVectorSetPrintLevel()

```
HYPRE_Int HYPRE_IJVectorSetPrintLevel (
    HYPRE_IJVector vector,
    HYPRE_Int print_level )
```

(Optional) Sets the print level, if the user wants to print error messages. The default is 0, i.e. no error messages are printed.

### 3.3.3.39 HYPRE\_IJVectorSetValues()

```
HYPRE_Int HYPRE_IJVectorSetValues (
    HYPRE_IJVector vector,
    HYPRE_Int nvalues,
    const HYPRE_BigInt * indices,
    const HYPRE_Complex * values )
```

Sets values in vector. The arrays *values* and *indices* are of dimension *nvalues* and contain the vector values to be set and the corresponding global vector indices, respectively. Erases any previous values at the specified locations and replaces them with new ones. Note that it is not possible to set values on other processors. If one tries to set a value from proc *i* on proc *j*, proc *i* will erase all previous occurrences of this value in its stack (including values generated with *AddToValues*), and treat it like a zero value. The actual value needs to be set on proc *j*.

Not collective.

## 3.4 Struct Solvers

### Functions

- HYPRE\_Int [HYPRE\\_StructSparseMSGCreate](#) (MPI\_Comm comm, [HYPRE\\_StructSolver](#) \*solver)
- HYPRE\_Int [HYPRE\\_StructSparseMSGDestroy](#) ([HYPRE\\_StructSolver](#) solver)
- HYPRE\_Int [HYPRE\\_StructSparseMSGSetup](#) ([HYPRE\\_StructSolver](#) solver, [HYPRE\\_StructMatrix](#) A, [HYPRE\\_StructVector](#) b, [HYPRE\\_StructVector](#) x)
- HYPRE\_Int [HYPRE\\_StructSparseMSGSolve](#) ([HYPRE\\_StructSolver](#) solver, [HYPRE\\_StructMatrix](#) A, [HYPRE\\_StructVector](#) b, [HYPRE\\_StructVector](#) x)
- HYPRE\_Int [HYPRE\\_StructSparseMSGSetTol](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_StructSparseMSGSetMaxIter](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Int max\_iter)
- HYPRE\_Int [HYPRE\\_StructSparseMSGSetJump](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Int jump)
- HYPRE\_Int [HYPRE\\_StructSparseMSGSetRelChange](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Int rel\_change)
- HYPRE\_Int [HYPRE\\_StructSparseMSGSetZeroGuess](#) ([HYPRE\\_StructSolver](#) solver)
- HYPRE\_Int [HYPRE\\_StructSparseMSGSetNonZeroGuess](#) ([HYPRE\\_StructSolver](#) solver)
- HYPRE\_Int [HYPRE\\_StructSparseMSGSetRelaxType](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Int relax\_type)
- HYPRE\_Int [HYPRE\\_StructSparseMSGSetJacobiWeight](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Real weight)
- HYPRE\_Int [HYPRE\\_StructSparseMSGSetNumPreRelax](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Int num\_↔pre\_relax)
- HYPRE\_Int [HYPRE\\_StructSparseMSGSetNumPostRelax](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Int num\_↔post\_relax)
- HYPRE\_Int [HYPRE\\_StructSparseMSGSetNumFineRelax](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Int num\_↔fine\_relax)
- HYPRE\_Int [HYPRE\\_StructSparseMSGSetLogging](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Int logging)
- HYPRE\_Int [HYPRE\\_StructSparseMSGSetPrintLevel](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Int print\_level)
- HYPRE\_Int [HYPRE\\_StructSparseMSGGetNumIterations](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Int \*num\_↔iterations)
- HYPRE\_Int [HYPRE\\_StructSparseMSGGetFinalRelativeResidualNorm](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Real \*norm)

### Struct Solvers

- typedef struct hypre\_StructSolver\_struct \* [HYPRE\\_StructSolver](#)
- typedef HYPRE\_Int(\* [HYPRE\\_PtrToStructSolverFcn](#)) ([HYPRE\\_StructSolver](#), [HYPRE\\_StructMatrix](#), [HYPRE\\_StructVector](#), [HYPRE\\_StructVector](#))
- typedef struct hypre\_Solver\_struct \* [HYPRE\\_Solver](#)
- typedef HYPRE\_Int(\* [HYPRE\\_PtrToModifyPCFcn](#)) ([HYPRE\\_Solver](#), HYPRE\_Int, HYPRE\_Real)
- #define [HYPRE\\_MODIFYPC](#)
- #define [HYPRE\\_SOLVER\\_STRUCT](#)

## Struct Jacobi Solver

- HYPRE\_Int [HYPRE\\_StructJacobiCreate](#) (MPI\_Comm comm, [HYPRE\\_StructSolver](#) \*solver)
- HYPRE\_Int [HYPRE\\_StructJacobiDestroy](#) ([HYPRE\\_StructSolver](#) solver)
- HYPRE\_Int [HYPRE\\_StructJacobiSetup](#) ([HYPRE\\_StructSolver](#) solver, [HYPRE\\_StructMatrix](#) A, [HYPRE\\_StructVector](#) b, [HYPRE\\_StructVector](#) x)
- HYPRE\_Int [HYPRE\\_StructJacobiSolve](#) ([HYPRE\\_StructSolver](#) solver, [HYPRE\\_StructMatrix](#) A, [HYPRE\\_StructVector](#) b, [HYPRE\\_StructVector](#) x)
- HYPRE\_Int [HYPRE\\_StructJacobiSetTol](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_StructJacobiGetTol](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Real \*tol)
- HYPRE\_Int [HYPRE\\_StructJacobiSetMaxIter](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Int max\_iter)
- HYPRE\_Int [HYPRE\\_StructJacobiGetMaxIter](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Int \*max\_iter)
- HYPRE\_Int [HYPRE\\_StructJacobiSetZeroGuess](#) ([HYPRE\\_StructSolver](#) solver)
- HYPRE\_Int [HYPRE\\_StructJacobiGetZeroGuess](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Int \*zeroguess)
- HYPRE\_Int [HYPRE\\_StructJacobiSetNonZeroGuess](#) ([HYPRE\\_StructSolver](#) solver)
- HYPRE\_Int [HYPRE\\_StructJacobiGetNumIterations](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Int \*num\_↵ iterations)
- HYPRE\_Int [HYPRE\\_StructJacobiGetFinalRelativeResidualNorm](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_↵ Real \*norm)

## Struct PFMG Solver

PFMG is a semicoarsening multigrid solver that uses pointwise relaxation. For periodic problems, users should try to set the grid size in periodic dimensions to be as close to a power-of-two as possible. That is, if the grid size in a periodic dimension is given by  $N = 2^m * M$  where  $M$  is not a power-of-two, then  $M$  should be as small as possible. Large values of  $M$  will generally result in slower convergence rates.

- HYPRE\_Int [HYPRE\\_StructPFMGCreate](#) (MPI\_Comm comm, [HYPRE\\_StructSolver](#) \*solver)
- HYPRE\_Int [HYPRE\\_StructPFMGDestroy](#) ([HYPRE\\_StructSolver](#) solver)
- HYPRE\_Int [HYPRE\\_StructPFMGSetup](#) ([HYPRE\\_StructSolver](#) solver, [HYPRE\\_StructMatrix](#) A, [HYPRE\\_StructVector](#) b, [HYPRE\\_StructVector](#) x)
- HYPRE\_Int [HYPRE\\_StructPFMGsSolve](#) ([HYPRE\\_StructSolver](#) solver, [HYPRE\\_StructMatrix](#) A, [HYPRE\\_StructVector](#) b, [HYPRE\\_StructVector](#) x)
- HYPRE\_Int [HYPRE\\_StructPFMGSetTol](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_StructPFMGGetTol](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Real \*tol)
- HYPRE\_Int [HYPRE\\_StructPFMGSetMaxIter](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Int max\_iter)
- HYPRE\_Int [HYPRE\\_StructPFMGGetMaxIter](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Int \*max\_iter)
- HYPRE\_Int [HYPRE\\_StructPFMGSetMaxLevels](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Int max\_levels)
- HYPRE\_Int [HYPRE\\_StructPFMGGetMaxLevels](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Int \*max\_levels)
- HYPRE\_Int [HYPRE\\_StructPFMGSetRelChange](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Int rel\_change)
- HYPRE\_Int [HYPRE\\_StructPFMGGetRelChange](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Int \*rel\_change)
- HYPRE\_Int [HYPRE\\_StructPFMGSetZeroGuess](#) ([HYPRE\\_StructSolver](#) solver)
- HYPRE\_Int [HYPRE\\_StructPFMGGetZeroGuess](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Int \*zeroguess)
- HYPRE\_Int [HYPRE\\_StructPFMGSetNonZeroGuess](#) ([HYPRE\\_StructSolver](#) solver)
- HYPRE\_Int [HYPRE\\_StructPFMGSetRelaxType](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Int relax\_type)
- HYPRE\_Int [HYPRE\\_StructPFMGGetRelaxType](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Int \*relax\_type)
- HYPRE\_Int [HYPRE\\_StructPFMGSetJacobiWeight](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Real weight)
- HYPRE\_Int [HYPRE\\_StructPFMGGetJacobiWeight](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Real \*weight)
- HYPRE\_Int [HYPRE\\_StructPFMGSetRAPType](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Int rap\_type)
- HYPRE\_Int [HYPRE\\_StructPFMGGetRAPType](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Int \*rap\_type)
- HYPRE\_Int [HYPRE\\_StructPFMGSetNumPreRelax](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Int num\_pre\_↵ relax)
- HYPRE\_Int [HYPRE\\_StructPFMGGetNumPreRelax](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Int \*num\_pre\_↵ relax)

- HYPRE\_Int HYPRE\_StructPFMGSetNumPostRelax (HYPRE\_StructSolver solver, HYPRE\_Int num\_post\_↵ relax)
- HYPRE\_Int HYPRE\_StructPFMGGetNumPostRelax (HYPRE\_StructSolver solver, HYPRE\_Int \*num\_post\_↵ relax)
- HYPRE\_Int HYPRE\_StructPFMGSetSkipRelax (HYPRE\_StructSolver solver, HYPRE\_Int skip\_relax)
- HYPRE\_Int HYPRE\_StructPFMGGetSkipRelax (HYPRE\_StructSolver solver, HYPRE\_Int \*skip\_relax)
- HYPRE\_Int HYPRE\_StructPFMGSetDxyz (HYPRE\_StructSolver solver, HYPRE\_Real \*dxyz)
- HYPRE\_Int HYPRE\_StructPFMGSetLogging (HYPRE\_StructSolver solver, HYPRE\_Int logging)
- HYPRE\_Int HYPRE\_StructPFMGGetLogging (HYPRE\_StructSolver solver, HYPRE\_Int \*logging)
- HYPRE\_Int HYPRE\_StructPFMGSetPrintLevel (HYPRE\_StructSolver solver, HYPRE\_Int print\_level)
- HYPRE\_Int HYPRE\_StructPFMGGetPrintLevel (HYPRE\_StructSolver solver, HYPRE\_Int \*print\_level)
- HYPRE\_Int HYPRE\_StructPFMGGetNumIterations (HYPRE\_StructSolver solver, HYPRE\_Int \*num\_↵ iterations)
- HYPRE\_Int HYPRE\_StructPFMGGetFinalRelativeResidualNorm (HYPRE\_StructSolver solver, HYPRE\_↵ Real \*norm)

### Struct SMG Solver

SMG is a semicoarsening multigrid solver that uses plane smoothing (in 3D). The plane smoother calls a 2D SMG algorithm with line smoothing, and the line smoother is cyclic reduction (1D SMG). For periodic problems, the grid size in periodic dimensions currently must be a power-of-two.

- HYPRE\_Int HYPRE\_StructSMGCreate (MPI\_Comm comm, HYPRE\_StructSolver \*solver)
- HYPRE\_Int HYPRE\_StructSMGDestroy (HYPRE\_StructSolver solver)
- HYPRE\_Int HYPRE\_StructSMGSetup (HYPRE\_StructSolver solver, HYPRE\_StructMatrix A, HYPRE\_StructVector b, HYPRE\_StructVector x)
- HYPRE\_Int HYPRE\_StructSMGSolve (HYPRE\_StructSolver solver, HYPRE\_StructMatrix A, HYPRE\_StructVector b, HYPRE\_StructVector x)
- HYPRE\_Int HYPRE\_StructSMGSetMemoryUse (HYPRE\_StructSolver solver, HYPRE\_Int memory\_use)
- HYPRE\_Int HYPRE\_StructSMGGetMemoryUse (HYPRE\_StructSolver solver, HYPRE\_Int \*memory\_use)
- HYPRE\_Int HYPRE\_StructSMGSetTol (HYPRE\_StructSolver solver, HYPRE\_Real tol)
- HYPRE\_Int HYPRE\_StructSMGGetTol (HYPRE\_StructSolver solver, HYPRE\_Real \*tol)
- HYPRE\_Int HYPRE\_StructSMGSetMaxIter (HYPRE\_StructSolver solver, HYPRE\_Int max\_iter)
- HYPRE\_Int HYPRE\_StructSMGGetMaxIter (HYPRE\_StructSolver solver, HYPRE\_Int \*max\_iter)
- HYPRE\_Int HYPRE\_StructSMGSetRelChange (HYPRE\_StructSolver solver, HYPRE\_Int rel\_change)
- HYPRE\_Int HYPRE\_StructSMGGetRelChange (HYPRE\_StructSolver solver, HYPRE\_Int \*rel\_change)
- HYPRE\_Int HYPRE\_StructSMGSetZeroGuess (HYPRE\_StructSolver solver)
- HYPRE\_Int HYPRE\_StructSMGGetZeroGuess (HYPRE\_StructSolver solver, HYPRE\_Int \*zeroguess)
- HYPRE\_Int HYPRE\_StructSMGSetNonZeroGuess (HYPRE\_StructSolver solver)
- HYPRE\_Int HYPRE\_StructSMGSetNumPreRelax (HYPRE\_StructSolver solver, HYPRE\_Int num\_pre\_relax)
- HYPRE\_Int HYPRE\_StructSMGGetNumPreRelax (HYPRE\_StructSolver solver, HYPRE\_Int \*num\_pre\_↵ relax)
- HYPRE\_Int HYPRE\_StructSMGSetNumPostRelax (HYPRE\_StructSolver solver, HYPRE\_Int num\_post\_↵ relax)
- HYPRE\_Int HYPRE\_StructSMGGetNumPostRelax (HYPRE\_StructSolver solver, HYPRE\_Int \*num\_post\_↵ relax)
- HYPRE\_Int HYPRE\_StructSMGSetLogging (HYPRE\_StructSolver solver, HYPRE\_Int logging)
- HYPRE\_Int HYPRE\_StructSMGGetLogging (HYPRE\_StructSolver solver, HYPRE\_Int \*logging)
- HYPRE\_Int HYPRE\_StructSMGSetPrintLevel (HYPRE\_StructSolver solver, HYPRE\_Int print\_level)
- HYPRE\_Int HYPRE\_StructSMGGetPrintLevel (HYPRE\_StructSolver solver, HYPRE\_Int \*print\_level)
- HYPRE\_Int HYPRE\_StructSMGGetNumIterations (HYPRE\_StructSolver solver, HYPRE\_Int \*num\_↵ iterations)
- HYPRE\_Int HYPRE\_StructSMGGetFinalRelativeResidualNorm (HYPRE\_StructSolver solver, HYPRE\_Real \*norm)

## Struct CycRed Solver

CycRed is a cyclic reduction solver that simultaneously solves a collection of 1D tridiagonal systems embedded in a d-dimensional grid.

- HYPRE\_Int [HYPRE\\_StructCycRedCreate](#) (MPI\_Comm comm, [HYPRE\\_StructSolver](#) \*solver)
- HYPRE\_Int [HYPRE\\_StructCycRedDestroy](#) ([HYPRE\\_StructSolver](#) solver)
- HYPRE\_Int [HYPRE\\_StructCycRedSetup](#) ([HYPRE\\_StructSolver](#) solver, [HYPRE\\_StructMatrix](#) A, [HYPRE\\_StructVector](#) b, [HYPRE\\_StructVector](#) x)
- HYPRE\_Int [HYPRE\\_StructCycRedSolve](#) ([HYPRE\\_StructSolver](#) solver, [HYPRE\\_StructMatrix](#) A, [HYPRE\\_StructVector](#) b, [HYPRE\\_StructVector](#) x)
- HYPRE\_Int [HYPRE\\_StructCycRedSetTDim](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Int tdim)
- HYPRE\_Int [HYPRE\\_StructCycRedSetBase](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Int ndim, HYPRE\_Int \*base\_index, HYPRE\_Int \*base\_stride)

## Struct PCG Solver

These routines should be used in conjunction with the generic interface in [Krylov Solvers](#).

- HYPRE\_Int [HYPRE\\_StructPCGCreate](#) (MPI\_Comm comm, [HYPRE\\_StructSolver](#) \*solver)
- HYPRE\_Int [HYPRE\\_StructPCGDestroy](#) ([HYPRE\\_StructSolver](#) solver)
- HYPRE\_Int [HYPRE\\_StructPCGSetup](#) ([HYPRE\\_StructSolver](#) solver, [HYPRE\\_StructMatrix](#) A, [HYPRE\\_StructVector](#) b, [HYPRE\\_StructVector](#) x)
- HYPRE\_Int [HYPRE\\_StructPCGSolve](#) ([HYPRE\\_StructSolver](#) solver, [HYPRE\\_StructMatrix](#) A, [HYPRE\\_StructVector](#) b, [HYPRE\\_StructVector](#) x)
- HYPRE\_Int [HYPRE\\_StructPCGSetTol](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_StructPCGSetAbsoluteTol](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_StructPCGSetMaxIter](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Int max\_iter)
- HYPRE\_Int [HYPRE\\_StructPCGSetTwoNorm](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Int two\_norm)
- HYPRE\_Int [HYPRE\\_StructPCGSetRelChange](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Int rel\_change)
- HYPRE\_Int [HYPRE\\_StructPCGSetPrecond](#) ([HYPRE\\_StructSolver](#) solver, [HYPRE\\_PtrToStructSolverFcn](#) precondition, [HYPRE\\_PtrToStructSolverFcn](#) precondition\_setup, [HYPRE\\_StructSolver](#) precondition\_solver)
- HYPRE\_Int [HYPRE\\_StructPCGSetLogging](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Int logging)
- HYPRE\_Int [HYPRE\\_StructPCGSetPrintLevel](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Int level)
- HYPRE\_Int [HYPRE\\_StructPCGGetNumIterations](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Int \*num\_↵ iterations)
- HYPRE\_Int [HYPRE\\_StructPCGGetFinalRelativeResidualNorm](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Real \*norm)
- HYPRE\_Int [HYPRE\\_StructPCGGetResidual](#) ([HYPRE\\_StructSolver](#) solver, void \*\*residual)
- HYPRE\_Int [HYPRE\\_StructDiagScaleSetup](#) ([HYPRE\\_StructSolver](#) solver, [HYPRE\\_StructMatrix](#) A, [HYPRE\\_StructVector](#) y, [HYPRE\\_StructVector](#) x)
- HYPRE\_Int [HYPRE\\_StructDiagScale](#) ([HYPRE\\_StructSolver](#) solver, [HYPRE\\_StructMatrix](#) HA, [HYPRE\\_StructVector](#) Hy, [HYPRE\\_StructVector](#) Hx)

### Struct GMRES Solver

These routines should be used in conjunction with the generic interface in [Krylov Solvers](#).

- HYPRE\_Int [HYPRE\\_StructGMRESCreate](#) (MPI\_Comm comm, [HYPRE\\_StructSolver](#) \*solver)
- HYPRE\_Int [HYPRE\\_StructGMRESDestroy](#) ([HYPRE\\_StructSolver](#) solver)
- HYPRE\_Int [HYPRE\\_StructGMRESSetup](#) ([HYPRE\\_StructSolver](#) solver, [HYPRE\\_StructMatrix](#) A, [HYPRE\\_StructVector](#) b, [HYPRE\\_StructVector](#) x)
- HYPRE\_Int [HYPRE\\_StructGMRESSolve](#) ([HYPRE\\_StructSolver](#) solver, [HYPRE\\_StructMatrix](#) A, [HYPRE\\_StructVector](#) b, [HYPRE\\_StructVector](#) x)
- HYPRE\_Int [HYPRE\\_StructGMRESSetTol](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_StructGMRESSetAbsoluteTol](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_StructGMRESSetMaxIter](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Int max\_iter)
- HYPRE\_Int [HYPRE\\_StructGMRESSetKDim](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Int k\_dim)
- HYPRE\_Int [HYPRE\\_StructGMRESSetPrecond](#) ([HYPRE\\_StructSolver](#) solver, [HYPRE\\_PtrToStructSolverFcn](#) precondition, [HYPRE\\_PtrToStructSolverFcn](#) precondition\_setup, [HYPRE\\_StructSolver](#) precondition\_solver)
- HYPRE\_Int [HYPRE\\_StructGMRESSetLogging](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Int logging)
- HYPRE\_Int [HYPRE\\_StructGMRESSetPrintLevel](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Int level)
- HYPRE\_Int [HYPRE\\_StructGMRESGetNumIterations](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Int \*num\_↔ iterations)
- HYPRE\_Int [HYPRE\\_StructGMRESGetFinalRelativeResidualNorm](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_↔ Real \*norm)
- HYPRE\_Int [HYPRE\\_StructGMRESGetResidual](#) ([HYPRE\\_StructSolver](#) solver, void \*\*residual)

### Struct FlexGMRES Solver

These routines should be used in conjunction with the generic interface in [Krylov Solvers](#).

- HYPRE\_Int [HYPRE\\_StructFlexGMRESCreate](#) (MPI\_Comm comm, [HYPRE\\_StructSolver](#) \*solver)
- HYPRE\_Int [HYPRE\\_StructFlexGMRESDestroy](#) ([HYPRE\\_StructSolver](#) solver)
- HYPRE\_Int [HYPRE\\_StructFlexGMRESSetup](#) ([HYPRE\\_StructSolver](#) solver, [HYPRE\\_StructMatrix](#) A, [HYPRE\\_StructVector](#) b, [HYPRE\\_StructVector](#) x)
- HYPRE\_Int [HYPRE\\_StructFlexGMRESSolve](#) ([HYPRE\\_StructSolver](#) solver, [HYPRE\\_StructMatrix](#) A, [HYPRE\\_StructVector](#) b, [HYPRE\\_StructVector](#) x)
- HYPRE\_Int [HYPRE\\_StructFlexGMRESSetTol](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_StructFlexGMRESSetAbsoluteTol](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_StructFlexGMRESSetMaxIter](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Int max\_iter)
- HYPRE\_Int [HYPRE\\_StructFlexGMRESSetKDim](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Int k\_dim)
- HYPRE\_Int [HYPRE\\_StructFlexGMRESSetPrecond](#) ([HYPRE\\_StructSolver](#) solver, [HYPRE\\_PtrToStructSolverFcn](#) precondition, [HYPRE\\_PtrToStructSolverFcn](#) precondition\_setup, [HYPRE\\_StructSolver](#) precondition\_solver)
- HYPRE\_Int [HYPRE\\_StructFlexGMRESSetLogging](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Int logging)
- HYPRE\_Int [HYPRE\\_StructFlexGMRESSetPrintLevel](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Int level)
- HYPRE\_Int [HYPRE\\_StructFlexGMRESGetNumIterations](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Int \*num\_↔ \_iterations)
- HYPRE\_Int [HYPRE\\_StructFlexGMRESGetFinalRelativeResidualNorm](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Real \*norm)
- HYPRE\_Int [HYPRE\\_StructFlexGMRESGetResidual](#) ([HYPRE\\_StructSolver](#) solver, void \*\*residual)
- HYPRE\_Int [HYPRE\\_StructFlexGMRESSetModifyPC](#) ([HYPRE\\_StructSolver](#) solver, [HYPRE\\_PtrToModifyPCFcn](#) modify\_pc)



## Struct LGMRES Solver

These routines should be used in conjunction with the generic interface in [Krylov Solvers](#).

- HYPRE\_Int [HYPRE\\_StructLGMRESCreate](#) (MPI\_Comm comm, [HYPRE\\_StructSolver](#) \*solver)
- HYPRE\_Int [HYPRE\\_StructLGMRESDestroy](#) ([HYPRE\\_StructSolver](#) solver)
- HYPRE\_Int [HYPRE\\_StructLGMRESSetup](#) ([HYPRE\\_StructSolver](#) solver, [HYPRE\\_StructMatrix](#) A, [HYPRE\\_StructVector](#) b, [HYPRE\\_StructVector](#) x)
- HYPRE\_Int [HYPRE\\_StructLGMRESSolve](#) ([HYPRE\\_StructSolver](#) solver, [HYPRE\\_StructMatrix](#) A, [HYPRE\\_StructVector](#) b, [HYPRE\\_StructVector](#) x)
- HYPRE\_Int [HYPRE\\_StructLGMRESSetTol](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_StructLGMRESSetAbsoluteTol](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_StructLGMRESSetMaxIter](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Int max\_iter)
- HYPRE\_Int [HYPRE\\_StructLGMRESSetKDim](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Int k\_dim)
- HYPRE\_Int [HYPRE\\_StructLGMRESSetAugDim](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Int aug\_dim)
- HYPRE\_Int [HYPRE\\_StructLGMRESSetPrecond](#) ([HYPRE\\_StructSolver](#) solver, [HYPRE\\_PtrToStructSolverFcn](#) precondition, [HYPRE\\_PtrToStructSolverFcn](#) precondition\_setup, [HYPRE\\_StructSolver](#) precondition\_solver)
- HYPRE\_Int [HYPRE\\_StructLGMRESSetLogging](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Int logging)
- HYPRE\_Int [HYPRE\\_StructLGMRESSetPrintLevel](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Int level)
- HYPRE\_Int [HYPRE\\_StructLGMRESGetNumIterations](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Int \*num\_↵ iterations)
- HYPRE\_Int [HYPRE\\_StructLGMRESGetFinalRelativeResidualNorm](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_↵\_Real \*norm)
- HYPRE\_Int [HYPRE\\_StructLGMRESGetResidual](#) ([HYPRE\\_StructSolver](#) solver, void \*\*residual)

## Struct BiCGSTAB Solver

These routines should be used in conjunction with the generic interface in [Krylov Solvers](#).

- HYPRE\_Int [HYPRE\\_StructBiCGSTABCreate](#) (MPI\_Comm comm, [HYPRE\\_StructSolver](#) \*solver)
- HYPRE\_Int [HYPRE\\_StructBiCGSTABDestroy](#) ([HYPRE\\_StructSolver](#) solver)
- HYPRE\_Int [HYPRE\\_StructBiCGSTABSetup](#) ([HYPRE\\_StructSolver](#) solver, [HYPRE\\_StructMatrix](#) A, [HYPRE\\_StructVector](#) b, [HYPRE\\_StructVector](#) x)
- HYPRE\_Int [HYPRE\\_StructBiCGSTABSolve](#) ([HYPRE\\_StructSolver](#) solver, [HYPRE\\_StructMatrix](#) A, [HYPRE\\_StructVector](#) b, [HYPRE\\_StructVector](#) x)
- HYPRE\_Int [HYPRE\\_StructBiCGSTABSetTol](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_StructBiCGSTABSetAbsoluteTol](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_StructBiCGSTABSetMaxIter](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Int max\_iter)
- HYPRE\_Int [HYPRE\\_StructBiCGSTABSetPrecond](#) ([HYPRE\\_StructSolver](#) solver, [HYPRE\\_PtrToStructSolverFcn](#) precondition, [HYPRE\\_PtrToStructSolverFcn](#) precondition\_setup, [HYPRE\\_StructSolver](#) precondition\_solver)
- HYPRE\_Int [HYPRE\\_StructBiCGSTABSetLogging](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Int logging)
- HYPRE\_Int [HYPRE\\_StructBiCGSTABSetPrintLevel](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Int level)
- HYPRE\_Int [HYPRE\\_StructBiCGSTABGetNumIterations](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Int \*num\_↵ iterations)
- HYPRE\_Int [HYPRE\\_StructBiCGSTABGetFinalRelativeResidualNorm](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Real \*norm)
- HYPRE\_Int [HYPRE\\_StructBiCGSTABGetResidual](#) ([HYPRE\\_StructSolver](#) solver, void \*\*residual)



### Struct Hybrid Solver

- HYPRE\_Int [HYPRE\\_StructHybridCreate](#) (MPI\_Comm comm, [HYPRE\\_StructSolver](#) \*solver)
- HYPRE\_Int [HYPRE\\_StructHybridDestroy](#) ([HYPRE\\_StructSolver](#) solver)
- HYPRE\_Int [HYPRE\\_StructHybridSetup](#) ([HYPRE\\_StructSolver](#) solver, [HYPRE\\_StructMatrix](#) A, [HYPRE\\_StructVector](#) b, [HYPRE\\_StructVector](#) x)
- HYPRE\_Int [HYPRE\\_StructHybridSolve](#) ([HYPRE\\_StructSolver](#) solver, [HYPRE\\_StructMatrix](#) A, [HYPRE\\_StructVector](#) b, [HYPRE\\_StructVector](#) x)
- HYPRE\_Int [HYPRE\\_StructHybridSetTol](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_StructHybridSetConvergenceTol](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Real cf\_tol)
- HYPRE\_Int [HYPRE\\_StructHybridSetDSCGMaxIter](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Int ds\_max\_its)
- HYPRE\_Int [HYPRE\\_StructHybridSetPCGMaxIter](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Int pre\_max\_its)
- HYPRE\_Int [HYPRE\\_StructHybridSetTwoNorm](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Int two\_norm)
- HYPRE\_Int [HYPRE\\_StructHybridSetStopCrit](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Int stop\_crit)
- HYPRE\_Int [HYPRE\\_StructHybridSetRelChange](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Int rel\_change)
- HYPRE\_Int [HYPRE\\_StructHybridSetSolverType](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Int solver\_type)
- HYPRE\_Int [HYPRE\\_StructHybridSetRecomputeResidual](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Int recompute\_residual)
- HYPRE\_Int [HYPRE\\_StructHybridGetRecomputeResidual](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Int \*recompute\_residual)
- HYPRE\_Int [HYPRE\\_StructHybridSetRecomputeResidualP](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Int recompute\_residual\_p)
- HYPRE\_Int [HYPRE\\_StructHybridGetRecomputeResidualP](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Int \*recompute\_residual\_p)
- HYPRE\_Int [HYPRE\\_StructHybridSetKDim](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Int k\_dim)
- HYPRE\_Int [HYPRE\\_StructHybridSetPrecond](#) ([HYPRE\\_StructSolver](#) solver, [HYPRE\\_PtrToStructSolverFcn](#) precondition, [HYPRE\\_PtrToStructSolverFcn](#) precondition\_setup, [HYPRE\\_StructSolver](#) precondition\_solver)
- HYPRE\_Int [HYPRE\\_StructHybridSetLogging](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Int logging)
- HYPRE\_Int [HYPRE\\_StructHybridSetPrintLevel](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Int print\_level)
- HYPRE\_Int [HYPRE\\_StructHybridGetNumIterations](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Int \*num\_its)
- HYPRE\_Int [HYPRE\\_StructHybridGetDSCGNumIterations](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Int \*ds\_its)
- HYPRE\_Int [HYPRE\\_StructHybridGetPCGNumIterations](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Int \*pre\_its)
- HYPRE\_Int [HYPRE\\_StructHybridGetFinalRelativeResidualNorm](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Real \*norm)
- HYPRE\_Int [HYPRE\\_StructHybridSetPCGAbsoluteTolFactor](#) ([HYPRE\\_StructSolver](#) solver, HYPRE\_Real pcg\_atolf)

### Struct LOBPCG Eigensolver

These routines should be used in conjunction with the generic interface in [Eigensolvers](#).

- HYPRE\_Int [HYPRE\\_StructSetupInterpreter](#) (mv\_InterfaceInterpreter \*i)
- HYPRE\_Int [HYPRE\\_StructSetupMatvec](#) (HYPRE\_MatvecFunctions \*mv)

#### 3.4.1 Detailed Description

These solvers use matrix/vector storage schemes that are tailored to structured grid problems.

@memo Linear solvers for structured grids

### 3.4.2 Macro Definition Documentation

#### 3.4.2.1 HYPRE\_MODIFYPC

```
#define HYPRE_MODIFYPC
```

#### 3.4.2.2 HYPRE\_SOLVER\_STRUCT

```
#define HYPRE_SOLVER_STRUCT
```

### 3.4.3 Typedef Documentation

#### 3.4.3.1 HYPRE\_PtrToModifyPCFcn

```
typedef HYPRE_Int (* HYPRE_PtrToModifyPCFcn) (HYPRE_Solver, HYPRE_Int, HYPRE_Real)
```

#### 3.4.3.2 HYPRE\_PtrToStructSolverFcn

```
typedef HYPRE_Int (* HYPRE_PtrToStructSolverFcn) (HYPRE_StructSolver, HYPRE_StructMatrix, HYPRE_StructVector, HYPRE_StructVector)
```

#### 3.4.3.3 HYPRE\_Solver

```
typedef struct hypre_Solver_struct* HYPRE_Solver
```

#### 3.4.3.4 HYPRE\_StructSolver

```
typedef struct hypre_StructSolver_struct* HYPRE_StructSolver
```

The solver object.

### 3.4.4 Function Documentation

#### 3.4.4.1 HYPRE\_StructBiCGSTABCreate()

```
HYPRE_Int HYPRE_StructBiCGSTABCreate (
    MPI_Comm comm,
    HYPRE_StructSolver * solver )
```

Create a solver object.

#### 3.4.4.2 HYPRE\_StructBiCGSTABDestroy()

```
HYPRE_Int HYPRE_StructBiCGSTABDestroy (
    HYPRE_StructSolver solver )
```

Destroy a solver object.

#### 3.4.4.3 HYPRE\_StructBiCGSTABGetFinalRelativeResidualNorm()

```
HYPRE_Int HYPRE_StructBiCGSTABGetFinalRelativeResidualNorm (
    HYPRE_StructSolver solver,
    HYPRE_Real * norm )
```

#### 3.4.4.4 HYPRE\_StructBiCGSTABGetNumIterations()

```
HYPRE_Int HYPRE_StructBiCGSTABGetNumIterations (
    HYPRE_StructSolver solver,
    HYPRE_Int * num_iterations )
```

#### 3.4.4.5 HYPRE\_StructBiCGSTABGetResidual()

```
HYPRE_Int HYPRE_StructBiCGSTABGetResidual (
    HYPRE_StructSolver solver,
    void ** residual )
```

#### 3.4.4.6 HYPRE\_StructBiCGSTABSetAbsoluteTol()

```
HYPRE_Int HYPRE_StructBiCGSTABSetAbsoluteTol (
    HYPRE_StructSolver solver,
    HYPRE_Real tol )
```

#### 3.4.4.7 HYPRE\_StructBiCGSTABSetLogging()

```
HYPRE_Int HYPRE_StructBiCGSTABSetLogging (
    HYPRE_StructSolver solver,
    HYPRE_Int logging )
```

#### 3.4.4.8 HYPRE\_StructBiCGSTABSetMaxIter()

```
HYPRE_Int HYPRE_StructBiCGSTABSetMaxIter (
    HYPRE_StructSolver solver,
    HYPRE_Int max_iter )
```

#### 3.4.4.9 HYPRE\_StructBiCGSTABSetPrecond()

```
HYPRE_Int HYPRE_StructBiCGSTABSetPrecond (
    HYPRE_StructSolver solver,
    HYPRE_PtrToStructSolverFcn precond,
    HYPRE_PtrToStructSolverFcn precond_setup,
    HYPRE_StructSolver precond_solver )
```

#### 3.4.4.10 HYPRE\_StructBiCGSTABSetPrintLevel()

```
HYPRE_Int HYPRE_StructBiCGSTABSetPrintLevel (
    HYPRE_StructSolver solver,
    HYPRE_Int level )
```

#### 3.4.4.11 HYPRE\_StructBiCGSTABSetTol()

```
HYPRE_Int HYPRE_StructBiCGSTABSetTol (
    HYPRE_StructSolver solver,
    HYPRE_Real tol )
```

#### 3.4.4.12 HYPRE\_StructBiCGSTABSetup()

```
HYPRE_Int HYPRE_StructBiCGSTABSetup (
    HYPRE_StructSolver solver,
    HYPRE_StructMatrix A,
    HYPRE_StructVector b,
    HYPRE_StructVector x )
```

#### 3.4.4.13 HYPRE\_StructBiCGSTABSolve()

```
HYPRE_Int HYPRE_StructBiCGSTABSolve (
    HYPRE_StructSolver solver,
    HYPRE_StructMatrix A,
    HYPRE_StructVector b,
    HYPRE_StructVector x )
```

#### 3.4.4.14 HYPRE\_StructCycRedCreate()

```
HYPRE_Int HYPRE_StructCycRedCreate (
    MPI_Comm comm,
    HYPRE_StructSolver * solver )
```

Create a solver object.

#### 3.4.4.15 HYPRE\_StructCycRedDestroy()

```
HYPRE_Int HYPRE_StructCycRedDestroy (
    HYPRE_StructSolver solver )
```

Destroy a solver object.

**3.4.4.16 HYPRE\_StructCycRedSetBase()**

```
HYPRE_Int HYPRE_StructCycRedSetBase (
    HYPRE_StructSolver solver,
    HYPRE_Int ndim,
    HYPRE_Int * base_index,
    HYPRE_Int * base_stride )
```

(Optional) Set the base index and stride for the embedded 1D systems. The stride must be equal one in the dimension corresponding to the 1D systems (see [HYPRE\\_StructCycRedSetTDim](#)).

**3.4.4.17 HYPRE\_StructCycRedSetTDim()**

```
HYPRE_Int HYPRE_StructCycRedSetTDim (
    HYPRE_StructSolver solver,
    HYPRE_Int tdim )
```

(Optional) Set the dimension number for the embedded 1D tridiagonal systems. The default is *tdim* = 0.

**3.4.4.18 HYPRE\_StructCycRedSetup()**

```
HYPRE_Int HYPRE_StructCycRedSetup (
    HYPRE_StructSolver solver,
    HYPRE_StructMatrix A,
    HYPRE_StructVector b,
    HYPRE_StructVector x )
```

Prepare to solve the system. The coefficient data in *b* and *x* is ignored here, but information about the layout of the data may be used.

**3.4.4.19 HYPRE\_StructCycRedSolve()**

```
HYPRE_Int HYPRE_StructCycRedSolve (
    HYPRE_StructSolver solver,
    HYPRE_StructMatrix A,
    HYPRE_StructVector b,
    HYPRE_StructVector x )
```

Solve the system.

**3.4.4.20 HYPRE\_StructDiagScale()**

```
HYPRE_Int HYPRE_StructDiagScale (
    HYPRE_StructSolver solver,
    HYPRE_StructMatrix HA,
    HYPRE_StructVector Hy,
    HYPRE_StructVector Hx )
```

Solve routine for diagonal preconditioning.

**3.4.4.21 HYPRE\_StructDiagScaleSetup()**

```
HYPRE_Int HYPRE_StructDiagScaleSetup (
    HYPRE_StructSolver solver,
    HYPRE_StructMatrix A,
    HYPRE_StructVector y,
    HYPRE_StructVector x )
```

Setup routine for diagonal preconditioning.

**3.4.4.22 HYPRE\_StructFlexGMRESCreate()**

```
HYPRE_Int HYPRE_StructFlexGMRESCreate (
    MPI_Comm comm,
    HYPRE_StructSolver * solver )
```

Create a solver object.

**3.4.4.23 HYPRE\_StructFlexGMRESDestroy()**

```
HYPRE_Int HYPRE_StructFlexGMRESDestroy (
    HYPRE_StructSolver solver )
```

Destroy a solver object.

**3.4.4.24 HYPRE\_StructFlexGMRESGetFinalRelativeResidualNorm()**

```
HYPRE_Int HYPRE_StructFlexGMRESGetFinalRelativeResidualNorm (
    HYPRE_StructSolver solver,
    HYPRE_Real * norm )
```

**3.4.4.25 HYPRE\_StructFlexGMRESGetNumIterations()**

```
HYPRE_Int HYPRE_StructFlexGMRESGetNumIterations (
    HYPRE_StructSolver solver,
    HYPRE_Int * num_iterations )
```

**3.4.4.26 HYPRE\_StructFlexGMRESGetResidual()**

```
HYPRE_Int HYPRE_StructFlexGMRESGetResidual (
    HYPRE_StructSolver solver,
    void ** residual )
```

**3.4.4.27 HYPRE\_StructFlexGMRESSetAbsoluteTol()**

```
HYPRE_Int HYPRE_StructFlexGMRESSetAbsoluteTol (
    HYPRE_StructSolver solver,
    HYPRE_Real tol )
```

**3.4.4.28 HYPRE\_StructFlexGMRESSetKDim()**

```
HYPRE_Int HYPRE_StructFlexGMRESSetKDim (
    HYPRE_StructSolver solver,
    HYPRE_Int k_dim )
```

**3.4.4.29 HYPRE\_StructFlexGMRESSetLogging()**

```
HYPRE_Int HYPRE_StructFlexGMRESSetLogging (
    HYPRE_StructSolver solver,
    HYPRE_Int logging )
```

**3.4.4.30 HYPRE\_StructFlexGMRESSetMaxIter()**

```
HYPRE_Int HYPRE_StructFlexGMRESSetMaxIter (
    HYPRE_StructSolver solver,
    HYPRE_Int max_iter )
```

**3.4.4.31 HYPRE\_StructFlexGMRESSetModifyPC()**

```
HYPRE_Int HYPRE_StructFlexGMRESSetModifyPC (
    HYPRE_StructSolver solver,
    HYPRE_PtrToModifyPCFcn modify_pc )
```

**3.4.4.32 HYPRE\_StructFlexGMRESSetPrecond()**

```
HYPRE_Int HYPRE_StructFlexGMRESSetPrecond (
    HYPRE_StructSolver solver,
    HYPRE_PtrToStructSolverFcn precond,
    HYPRE_PtrToStructSolverFcn precond_setup,
    HYPRE_StructSolver precond_solver )
```

**3.4.4.33 HYPRE\_StructFlexGMRESSetPrintLevel()**

```
HYPRE_Int HYPRE_StructFlexGMRESSetPrintLevel (
    HYPRE_StructSolver solver,
    HYPRE_Int level )
```

**3.4.4.34 HYPRE\_StructFlexGMRESSetTol()**

```
HYPRE_Int HYPRE_StructFlexGMRESSetTol (
    HYPRE_StructSolver solver,
    HYPRE_Real tol )
```

**3.4.4.35 HYPRE\_StructFlexGMRESSetup()**

```
HYPRE_Int HYPRE_StructFlexGMRESSetup (
    HYPRE_StructSolver solver,
    HYPRE_StructMatrix A,
    HYPRE_StructVector b,
    HYPRE_StructVector x )
```

**3.4.4.36 HYPRE\_StructFlexGMRESSolve()**

```
HYPRE_Int HYPRE_StructFlexGMRESSolve (
    HYPRE_StructSolver solver,
    HYPRE_StructMatrix A,
    HYPRE_StructVector b,
    HYPRE_StructVector x )
```

**3.4.4.37 HYPRE\_StructGMRESCreate()**

```
HYPRE_Int HYPRE_StructGMRESCreate (
    MPI_Comm comm,
    HYPRE_StructSolver * solver )
```

Create a solver object.

**3.4.4.38 HYPRE\_StructGMRESDestroy()**

```
HYPRE_Int HYPRE_StructGMRESDestroy (
    HYPRE_StructSolver solver )
```

Destroy a solver object.

**3.4.4.39 HYPRE\_StructGMRESGetFinalRelativeResidualNorm()**

```
HYPRE_Int HYPRE_StructGMRESGetFinalRelativeResidualNorm (
    HYPRE_StructSolver solver,
    HYPRE_Real * norm )
```

**3.4.4.40 HYPRE\_StructGMRESGetNumIterations()**

```
HYPRE_Int HYPRE_StructGMRESGetNumIterations (
    HYPRE_StructSolver solver,
    HYPRE_Int * num_iterations )
```

**3.4.4.41 HYPRE\_StructGMRESGetResidual()**

```
HYPRE_Int HYPRE_StructGMRESGetResidual (
    HYPRE_StructSolver solver,
    void ** residual )
```



**3.4.4.42 HYPRE\_StructGMRESSetAbsoluteTol()**

```
HYPRE_Int HYPRE_StructGMRESSetAbsoluteTol (
    HYPRE_StructSolver solver,
    HYPRE_Real tol )
```

**3.4.4.43 HYPRE\_StructGMRESSetKDim()**

```
HYPRE_Int HYPRE_StructGMRESSetKDim (
    HYPRE_StructSolver solver,
    HYPRE_Int k_dim )
```

**3.4.4.44 HYPRE\_StructGMRESSetLogging()**

```
HYPRE_Int HYPRE_StructGMRESSetLogging (
    HYPRE_StructSolver solver,
    HYPRE_Int logging )
```

**3.4.4.45 HYPRE\_StructGMRESSetMaxIter()**

```
HYPRE_Int HYPRE_StructGMRESSetMaxIter (
    HYPRE_StructSolver solver,
    HYPRE_Int max_iter )
```

**3.4.4.46 HYPRE\_StructGMRESSetPrecond()**

```
HYPRE_Int HYPRE_StructGMRESSetPrecond (
    HYPRE_StructSolver solver,
    HYPRE_PtrToStructSolverFcn precond,
    HYPRE_PtrToStructSolverFcn precond_setup,
    HYPRE_StructSolver precond_solver )
```

**3.4.4.47 HYPRE\_StructGMRESSetPrintLevel()**

```
HYPRE_Int HYPRE_StructGMRESSetPrintLevel (
    HYPRE_StructSolver solver,
    HYPRE_Int level )
```

**3.4.4.48 HYPRE\_StructGMRESSetTol()**

```
HYPRE_Int HYPRE_StructGMRESSetTol (
    HYPRE_StructSolver solver,
    HYPRE_Real tol )
```

**3.4.4.49 HYPRE\_StructGMRESSetup()**

```
HYPRE_Int HYPRE_StructGMRESSetup (
    HYPRE_StructSolver solver,
    HYPRE_StructMatrix A,
    HYPRE_StructVector b,
    HYPRE_StructVector x )
```

**3.4.4.50 HYPRE\_StructGMRESSolve()**

```
HYPRE_Int HYPRE_StructGMRESSolve (
    HYPRE_StructSolver solver,
    HYPRE_StructMatrix A,
    HYPRE_StructVector b,
    HYPRE_StructVector x )
```

**3.4.4.51 HYPRE\_StructHybridCreate()**

```
HYPRE_Int HYPRE_StructHybridCreate (
    MPI_Comm comm,
    HYPRE_StructSolver * solver )
```

Create a solver object.

**3.4.4.52 HYPRE\_StructHybridDestroy()**

```
HYPRE_Int HYPRE_StructHybridDestroy (
    HYPRE_StructSolver solver )
```

Destroy a solver object.

**3.4.4.53 HYPRE\_StructHybridGetDSCGNumIterations()**

```
HYPRE_Int HYPRE_StructHybridGetDSCGNumIterations (
    HYPRE_StructSolver solver,
    HYPRE_Int * ds_num_its )
```

Return the number of diagonal scaling iterations taken.

**3.4.4.54 HYPRE\_StructHybridGetFinalRelativeResidualNorm()**

```
HYPRE_Int HYPRE_StructHybridGetFinalRelativeResidualNorm (
    HYPRE_StructSolver solver,
    HYPRE_Real * norm )
```

Return the norm of the final relative residual.

**3.4.4.55 HYPRE\_StructHybridGetNumIterations()**

```
HYPRE_Int HYPRE_StructHybridGetNumIterations (
    HYPRE_StructSolver solver,
    HYPRE_Int * num_its )
```

Return the number of iterations taken.

**3.4.4.56 HYPRE\_StructHybridGetPCGNumIterations()**

```
HYPRE_Int HYPRE_StructHybridGetPCGNumIterations (
    HYPRE_StructSolver solver,
    HYPRE_Int * pre_num_its )
```

Return the number of general preconditioning iterations taken.

**3.4.4.57 HYPRE\_StructHybridGetRecomputeResidual()**

```
HYPRE_Int HYPRE_StructHybridGetRecomputeResidual (
    HYPRE_StructSolver solver,
    HYPRE_Int * recompute_residual )
```

(Optional) Get recompute residual option.

**3.4.4.58 HYPRE\_StructHybridGetRecomputeResidualP()**

```
HYPRE_Int HYPRE_StructHybridGetRecomputeResidualP (
    HYPRE_StructSolver solver,
    HYPRE_Int * recompute_residual_p )
```

(Optional) Get recompute residual period option.

**3.4.4.59 HYPRE\_StructHybridSetConvergenceTol()**

```
HYPRE_Int HYPRE_StructHybridSetConvergenceTol (
    HYPRE_StructSolver solver,
    HYPRE_Real cf_tol )
```

(Optional) Set an accepted convergence tolerance for diagonal scaling (DS). The solver will switch preconditioners if the convergence of DS is slower than *cf\_tol*.

**3.4.4.60 HYPRE\_StructHybridSetDSCGMaxIter()**

```
HYPRE_Int HYPRE_StructHybridSetDSCGMaxIter (
    HYPRE_StructSolver solver,
    HYPRE_Int ds_max_its )
```

(Optional) Set maximum number of iterations for diagonal scaling (DS). The solver will switch preconditioners if DS reaches *ds\_max\_its*.

**3.4.4.61 HYPRE\_StructHybridSetKDim()**

```
HYPRE_Int HYPRE_StructHybridSetKDim (
    HYPRE_StructSolver solver,
    HYPRE_Int k_dim )
```

(Optional) Set the maximum size of the Krylov space when using GMRES.

**3.4.4.62 HYPRE\_StructHybridSetLogging()**

```
HYPRE_Int HYPRE_StructHybridSetLogging (
    HYPRE_StructSolver solver,
    HYPRE_Int logging )
```

(Optional) Set the amount of logging to do.

**3.4.4.63 HYPRE\_StructHybridSetPCGAbsoluteTolFactor()**

```
HYPRE_Int HYPRE_StructHybridSetPCGAbsoluteTolFactor (
    HYPRE_StructSolver solver,
    HYPRE_Real pcg_atolf )
```

**3.4.4.64 HYPRE\_StructHybridSetPCGMaxIter()**

```
HYPRE_Int HYPRE_StructHybridSetPCGMaxIter (
    HYPRE_StructSolver solver,
    HYPRE_Int pre_max_its )
```

(Optional) Set maximum number of iterations for general preconditioner (PRE). The solver will stop if PRE reaches *pre\_max\_its*.

**3.4.4.65 HYPRE\_StructHybridSetPrecond()**

```
HYPRE_Int HYPRE_StructHybridSetPrecond (
    HYPRE_StructSolver solver,
    HYPRE_PtrToStructSolverFcn precondition,
    HYPRE_PtrToStructSolverFcn precondition_setup,
    HYPRE_StructSolver precondition_solver )
```

(Optional) Set the preconditioner to use.

**3.4.4.66 HYPRE\_StructHybridSetPrintLevel()**

```
HYPRE_Int HYPRE_StructHybridSetPrintLevel (
    HYPRE_StructSolver solver,
    HYPRE_Int print_level )
```

(Optional) Set the amount of printing to do to the screen.

**3.4.4.67 HYPRE\_StructHybridSetRecomputeResidual()**

```
HYPRE_Int HYPRE_StructHybridSetRecomputeResidual (
    HYPRE_StructSolver solver,
    HYPRE_Int recompute_residual )
```

(Optional) Set recompute residual (don't rely on 3-term recurrence).

**3.4.4.68 HYPRE\_StructHybridSetRecomputeResidualP()**

```
HYPRE_Int HYPRE_StructHybridSetRecomputeResidualP (
    HYPRE_StructSolver solver,
    HYPRE_Int recompute_residual_p )
```

(Optional) Set recompute residual period (don't rely on 3-term recurrence).

Recomputes residual after every specified number of iterations.

**3.4.4.69 HYPRE\_StructHybridSetRelChange()**

```
HYPRE_Int HYPRE_StructHybridSetRelChange (
    HYPRE_StructSolver solver,
    HYPRE_Int rel_change )
```

(Optional) Additionally require that the relative difference in successive iterates be small.

**3.4.4.70 HYPRE\_StructHybridSetSolverType()**

```
HYPRE_Int HYPRE_StructHybridSetSolverType (
    HYPRE_StructSolver solver,
    HYPRE_Int solver_type )
```

(Optional) Set the type of Krylov solver to use.

Current krylov methods set by *solver\_type* are:

- 0 : PCG (default)
- 1 : GMRES
- 2 : BiCGSTAB

**3.4.4.71 HYPRE\_StructHybridSetStopCrit()**

```
HYPRE_Int HYPRE_StructHybridSetStopCrit (
    HYPRE_StructSolver solver,
    HYPRE_Int stop_crit )
```

**3.4.4.72 HYPRE\_StructHybridSetTol()**

```
HYPRE_Int HYPRE_StructHybridSetTol (
    HYPRE_StructSolver solver,
    HYPRE_Real tol )
```

(Optional) Set the convergence tolerance.

**3.4.4.73 HYPRE\_StructHybridSetTwoNorm()**

```
HYPRE_Int HYPRE_StructHybridSetTwoNorm (
    HYPRE_StructSolver solver,
    HYPRE_Int two_norm )
```

(Optional) Use the two-norm in stopping criteria.

**3.4.4.74 HYPRE\_StructHybridSetup()**

```
HYPRE_Int HYPRE_StructHybridSetup (
    HYPRE_StructSolver solver,
    HYPRE_StructMatrix A,
    HYPRE_StructVector b,
    HYPRE_StructVector x )
```

Prepare to solve the system. The coefficient data in *b* and *x* is ignored here, but information about the layout of the data may be used.

**3.4.4.75 HYPRE\_StructHybridSolve()**

```
HYPRE_Int HYPRE_StructHybridSolve (
    HYPRE_StructSolver solver,
    HYPRE_StructMatrix A,
    HYPRE_StructVector b,
    HYPRE_StructVector x )
```

Solve the system.

**3.4.4.76 HYPRE\_StructJacobiCreate()**

```
HYPRE_Int HYPRE_StructJacobiCreate (
    MPI_Comm comm,
    HYPRE_StructSolver * solver )
```

Create a solver object.

#### 3.4.4.77 HYPRE\_StructJacobiDestroy()

```
HYPRE_Int HYPRE_StructJacobiDestroy (
    HYPRE_StructSolver solver )
```

Destroy a solver object. An object should be explicitly destroyed using this destructor when the user's code no longer needs direct access to it. Once destroyed, the object must not be referenced again. Note that the object may not be deallocated at the completion of this call, since there may be internal package references to the object. The object will then be destroyed when all internal reference counts go to zero.

#### 3.4.4.78 HYPRE\_StructJacobiGetFinalRelativeResidualNorm()

```
HYPRE_Int HYPRE_StructJacobiGetFinalRelativeResidualNorm (
    HYPRE_StructSolver solver,
    HYPRE_Real * norm )
```

Return the norm of the final relative residual.

#### 3.4.4.79 HYPRE\_StructJacobiGetMaxIter()

```
HYPRE_Int HYPRE_StructJacobiGetMaxIter (
    HYPRE_StructSolver solver,
    HYPRE_Int * max_iter )
```

#### 3.4.4.80 HYPRE\_StructJacobiGetNumIterations()

```
HYPRE_Int HYPRE_StructJacobiGetNumIterations (
    HYPRE_StructSolver solver,
    HYPRE_Int * num_iterations )
```

Return the number of iterations taken.

#### 3.4.4.81 HYPRE\_StructJacobiGetTol()

```
HYPRE_Int HYPRE_StructJacobiGetTol (
    HYPRE_StructSolver solver,
    HYPRE_Real * tol )
```

#### 3.4.4.82 HYPRE\_StructJacobiGetZeroGuess()

```
HYPRE_Int HYPRE_StructJacobiGetZeroGuess (
    HYPRE_StructSolver solver,
    HYPRE_Int * zeroguess )
```

**3.4.4.83 HYPRE\_StructJacobiSetMaxIter()**

```
HYPRE_Int HYPRE_StructJacobiSetMaxIter (
    HYPRE_StructSolver solver,
    HYPRE_Int max_iter )
```

(Optional) Set maximum number of iterations.

**3.4.4.84 HYPRE\_StructJacobiSetNonZeroGuess()**

```
HYPRE_Int HYPRE_StructJacobiSetNonZeroGuess (
    HYPRE_StructSolver solver )
```

(Optional) Use a nonzero initial guess. This is the default behavior, but this routine allows the user to switch back after using *SetZeroGuess*.

**3.4.4.85 HYPRE\_StructJacobiSetTol()**

```
HYPRE_Int HYPRE_StructJacobiSetTol (
    HYPRE_StructSolver solver,
    HYPRE_Real tol )
```

(Optional) Set the convergence tolerance.

**3.4.4.86 HYPRE\_StructJacobiSetup()**

```
HYPRE_Int HYPRE_StructJacobiSetup (
    HYPRE_StructSolver solver,
    HYPRE_StructMatrix A,
    HYPRE_StructVector b,
    HYPRE_StructVector x )
```

Prepare to solve the system. The coefficient data in *b* and *x* is ignored here, but information about the layout of the data may be used.

**3.4.4.87 HYPRE\_StructJacobiSetZeroGuess()**

```
HYPRE_Int HYPRE_StructJacobiSetZeroGuess (
    HYPRE_StructSolver solver )
```

(Optional) Use a zero initial guess. This allows the solver to cut corners in the case where a zero initial guess is needed (e.g., for preconditioning) to reduce computational cost.

**3.4.4.88 HYPRE\_StructJacobiSolve()**

```
HYPRE_Int HYPRE_StructJacobiSolve (
    HYPRE_StructSolver solver,
    HYPRE_StructMatrix A,
    HYPRE_StructVector b,
    HYPRE_StructVector x )
```

Solve the system.



**3.4.4.89 HYPRE\_StructLGMRESCreate()**

```
HYPRE_Int HYPRE_StructLGMRESCreate (
    MPI_Comm comm,
    HYPRE_StructSolver * solver )
```

Create a solver object.

**3.4.4.90 HYPRE\_StructLGMRESDestroy()**

```
HYPRE_Int HYPRE_StructLGMRESDestroy (
    HYPRE_StructSolver solver )
```

Destroy a solver object.

**3.4.4.91 HYPRE\_StructLGMRESGetFinalRelativeResidualNorm()**

```
HYPRE_Int HYPRE_StructLGMRESGetFinalRelativeResidualNorm (
    HYPRE_StructSolver solver,
    HYPRE_Real * norm )
```

**3.4.4.92 HYPRE\_StructLGMRESGetNumIterations()**

```
HYPRE_Int HYPRE_StructLGMRESGetNumIterations (
    HYPRE_StructSolver solver,
    HYPRE_Int * num_iterations )
```

**3.4.4.93 HYPRE\_StructLGMRESGetResidual()**

```
HYPRE_Int HYPRE_StructLGMRESGetResidual (
    HYPRE_StructSolver solver,
    void ** residual )
```

**3.4.4.94 HYPRE\_StructLGMRESSetAbsoluteTol()**

```
HYPRE_Int HYPRE_StructLGMRESSetAbsoluteTol (
    HYPRE_StructSolver solver,
    HYPRE_Real tol )
```

**3.4.4.95 HYPRE\_StructLGMRESSetAugDim()**

```
HYPRE_Int HYPRE_StructLGMRESSetAugDim (
    HYPRE_StructSolver solver,
    HYPRE_Int aug_dim )
```

#### 3.4.4.96 HYPRE\_StructLGMRESSetKDim()

```
HYPRE_Int HYPRE_StructLGMRESSetKDim (
    HYPRE_StructSolver solver,
    HYPRE_Int k_dim )
```

#### 3.4.4.97 HYPRE\_StructLGMRESSetLogging()

```
HYPRE_Int HYPRE_StructLGMRESSetLogging (
    HYPRE_StructSolver solver,
    HYPRE_Int logging )
```

#### 3.4.4.98 HYPRE\_StructLGMRESSetMaxIter()

```
HYPRE_Int HYPRE_StructLGMRESSetMaxIter (
    HYPRE_StructSolver solver,
    HYPRE_Int max_iter )
```

#### 3.4.4.99 HYPRE\_StructLGMRESSetPrecond()

```
HYPRE_Int HYPRE_StructLGMRESSetPrecond (
    HYPRE_StructSolver solver,
    HYPRE_PtrToStructSolverFcn precond,
    HYPRE_PtrToStructSolverFcn precond_setup,
    HYPRE_StructSolver precond_solver )
```

#### 3.4.4.100 HYPRE\_StructLGMRESSetPrintLevel()

```
HYPRE_Int HYPRE_StructLGMRESSetPrintLevel (
    HYPRE_StructSolver solver,
    HYPRE_Int level )
```

#### 3.4.4.101 HYPRE\_StructLGMRESSetTol()

```
HYPRE_Int HYPRE_StructLGMRESSetTol (
    HYPRE_StructSolver solver,
    HYPRE_Real tol )
```

#### 3.4.4.102 HYPRE\_StructLGMRESSetup()

```
HYPRE_Int HYPRE_StructLGMRESSetup (
    HYPRE_StructSolver solver,
    HYPRE_StructMatrix A,
    HYPRE_StructVector b,
    HYPRE_StructVector x )
```

**3.4.4.103 HYPRE\_StructLGMRESSolve()**

```
HYPRE_Int HYPRE_StructLGMRESSolve (
    HYPRE_StructSolver solver,
    HYPRE_StructMatrix A,
    HYPRE_StructVector b,
    HYPRE_StructVector x )
```

**3.4.4.104 HYPRE\_StructPCGCreate()**

```
HYPRE_Int HYPRE_StructPCGCreate (
    MPI_Comm comm,
    HYPRE_StructSolver * solver )
```

Create a solver object.

**3.4.4.105 HYPRE\_StructPCGDestroy()**

```
HYPRE_Int HYPRE_StructPCGDestroy (
    HYPRE_StructSolver solver )
```

Destroy a solver object.

**3.4.4.106 HYPRE\_StructPCGGetFinalRelativeResidualNorm()**

```
HYPRE_Int HYPRE_StructPCGGetFinalRelativeResidualNorm (
    HYPRE_StructSolver solver,
    HYPRE_Real * norm )
```

**3.4.4.107 HYPRE\_StructPCGGetNumIterations()**

```
HYPRE_Int HYPRE_StructPCGGetNumIterations (
    HYPRE_StructSolver solver,
    HYPRE_Int * num_iterations )
```

**3.4.4.108 HYPRE\_StructPCGGetResidual()**

```
HYPRE_Int HYPRE_StructPCGGetResidual (
    HYPRE_StructSolver solver,
    void ** residual )
```

**3.4.4.109 HYPRE\_StructPCGSetAbsoluteTol()**

```
HYPRE_Int HYPRE_StructPCGSetAbsoluteTol (
    HYPRE_StructSolver solver,
    HYPRE_Real tol )
```

#### 3.4.4.110 HYPRE\_StructPCGSetLogging()

```
HYPRE_Int HYPRE_StructPCGSetLogging (
    HYPRE_StructSolver solver,
    HYPRE_Int logging )
```

#### 3.4.4.111 HYPRE\_StructPCGSetMaxIter()

```
HYPRE_Int HYPRE_StructPCGSetMaxIter (
    HYPRE_StructSolver solver,
    HYPRE_Int max_iter )
```

#### 3.4.4.112 HYPRE\_StructPCGSetPrecond()

```
HYPRE_Int HYPRE_StructPCGSetPrecond (
    HYPRE_StructSolver solver,
    HYPRE_PtrToStructSolverFcn precondition,
    HYPRE_PtrToStructSolverFcn precondition_setup,
    HYPRE_StructSolver precondition_solver )
```

#### 3.4.4.113 HYPRE\_StructPCGSetPrintLevel()

```
HYPRE_Int HYPRE_StructPCGSetPrintLevel (
    HYPRE_StructSolver solver,
    HYPRE_Int level )
```

#### 3.4.4.114 HYPRE\_StructPCGSetRelChange()

```
HYPRE_Int HYPRE_StructPCGSetRelChange (
    HYPRE_StructSolver solver,
    HYPRE_Int rel_change )
```

#### 3.4.4.115 HYPRE\_StructPCGSetTol()

```
HYPRE_Int HYPRE_StructPCGSetTol (
    HYPRE_StructSolver solver,
    HYPRE_Real tol )
```

#### 3.4.4.116 HYPRE\_StructPCGSetTwoNorm()

```
HYPRE_Int HYPRE_StructPCGSetTwoNorm (
    HYPRE_StructSolver solver,
    HYPRE_Int two_norm )
```

**3.4.4.117 HYPRE\_StructPCGSetup()**

```
HYPRE_Int HYPRE_StructPCGSetup (
    HYPRE_StructSolver solver,
    HYPRE_StructMatrix A,
    HYPRE_StructVector b,
    HYPRE_StructVector x )
```

**3.4.4.118 HYPRE\_StructPCGSolve()**

```
HYPRE_Int HYPRE_StructPCGSolve (
    HYPRE_StructSolver solver,
    HYPRE_StructMatrix A,
    HYPRE_StructVector b,
    HYPRE_StructVector x )
```

**3.4.4.119 HYPRE\_StructPFMGCreate()**

```
HYPRE_Int HYPRE_StructPFMGCreate (
    MPI_Comm comm,
    HYPRE_StructSolver * solver )
```

Create a solver object.

**3.4.4.120 HYPRE\_StructPFMGDestroy()**

```
HYPRE_Int HYPRE_StructPFMGDestroy (
    HYPRE_StructSolver solver )
```

Destroy a solver object.

**3.4.4.121 HYPRE\_StructPFMGGetFinalRelativeResidualNorm()**

```
HYPRE_Int HYPRE_StructPFMGGetFinalRelativeResidualNorm (
    HYPRE_StructSolver solver,
    HYPRE_Real * norm )
```

Return the norm of the final relative residual.

**3.4.4.122 HYPRE\_StructPFMGGetJacobiWeight()**

```
HYPRE_Int HYPRE_StructPFMGGetJacobiWeight (
    HYPRE_StructSolver solver,
    HYPRE_Real * weight )
```

#### 3.4.4.123 HYPRE\_StructPFMGGetLogging()

```
HYPRE_Int HYPRE_StructPFMGGetLogging (
    HYPRE_StructSolver solver,
    HYPRE_Int * logging )
```

#### 3.4.4.124 HYPRE\_StructPFMGGetMaxIter()

```
HYPRE_Int HYPRE_StructPFMGGetMaxIter (
    HYPRE_StructSolver solver,
    HYPRE_Int * max_iter )
```

#### 3.4.4.125 HYPRE\_StructPFMGGetMaxLevels()

```
HYPRE_Int HYPRE_StructPFMGGetMaxLevels (
    HYPRE_StructSolver solver,
    HYPRE_Int * max_levels )
```

#### 3.4.4.126 HYPRE\_StructPFMGGetNumIterations()

```
HYPRE_Int HYPRE_StructPFMGGetNumIterations (
    HYPRE_StructSolver solver,
    HYPRE_Int * num_iterations )
```

Return the number of iterations taken.

#### 3.4.4.127 HYPRE\_StructPFMGGetNumPostRelax()

```
HYPRE_Int HYPRE_StructPFMGGetNumPostRelax (
    HYPRE_StructSolver solver,
    HYPRE_Int * num_post_relax )
```

#### 3.4.4.128 HYPRE\_StructPFMGGetNumPreRelax()

```
HYPRE_Int HYPRE_StructPFMGGetNumPreRelax (
    HYPRE_StructSolver solver,
    HYPRE_Int * num_pre_relax )
```

#### 3.4.4.129 HYPRE\_StructPFMGGetPrintLevel()

```
HYPRE_Int HYPRE_StructPFMGGetPrintLevel (
    HYPRE_StructSolver solver,
    HYPRE_Int * print_level )
```

**3.4.4.130 HYPRE\_StructPFMGGetRAPType()**

```
HYPRE_Int HYPRE_StructPFMGGetRAPType (
    HYPRE_StructSolver solver,
    HYPRE_Int * rap_type )
```

**3.4.4.131 HYPRE\_StructPFMGGetRelaxType()**

```
HYPRE_Int HYPRE_StructPFMGGetRelaxType (
    HYPRE_StructSolver solver,
    HYPRE_Int * relax_type )
```

**3.4.4.132 HYPRE\_StructPFMGGetRelChange()**

```
HYPRE_Int HYPRE_StructPFMGGetRelChange (
    HYPRE_StructSolver solver,
    HYPRE_Int * rel_change )
```

**3.4.4.133 HYPRE\_StructPFMGGetSkipRelax()**

```
HYPRE_Int HYPRE_StructPFMGGetSkipRelax (
    HYPRE_StructSolver solver,
    HYPRE_Int * skip_relax )
```

**3.4.4.134 HYPRE\_StructPFMGGetTol()**

```
HYPRE_Int HYPRE_StructPFMGGetTol (
    HYPRE_StructSolver solver,
    HYPRE_Real * tol )
```

**3.4.4.135 HYPRE\_StructPFMGGetZeroGuess()**

```
HYPRE_Int HYPRE_StructPFMGGetZeroGuess (
    HYPRE_StructSolver solver,
    HYPRE_Int * zeroguess )
```

**3.4.4.136 HYPRE\_StructPFMGSetDxyz()**

```
HYPRE_Int HYPRE_StructPFMGSetDxyz (
    HYPRE_StructSolver solver,
    HYPRE_Real * dxyz )
```

**3.4.4.137 HYPRE\_StructPFMGSetJacobiWeight()**

```
HYPRE_Int HYPRE_StructPFMGSetJacobiWeight (
    HYPRE_StructSolver solver,
    HYPRE_Real weight )
```

#### 3.4.4.138 HYPRE\_StructPFMGSetLogging()

```
HYPRE_Int HYPRE_StructPFMGSetLogging (
    HYPRE_StructSolver solver,
    HYPRE_Int logging )
```

(Optional) Set the amount of logging to do.

#### 3.4.4.139 HYPRE\_StructPFMGSetMaxIter()

```
HYPRE_Int HYPRE_StructPFMGSetMaxIter (
    HYPRE_StructSolver solver,
    HYPRE_Int max_iter )
```

(Optional) Set maximum number of iterations.

#### 3.4.4.140 HYPRE\_StructPFMGSetMaxLevels()

```
HYPRE_Int HYPRE_StructPFMGSetMaxLevels (
    HYPRE_StructSolver solver,
    HYPRE_Int max_levels )
```

(Optional) Set maximum number of multigrid grid levels.

#### 3.4.4.141 HYPRE\_StructPFMGSetNonZeroGuess()

```
HYPRE_Int HYPRE_StructPFMGSetNonZeroGuess (
    HYPRE_StructSolver solver )
```

(Optional) Use a nonzero initial guess. This is the default behavior, but this routine allows the user to switch back after using *SetZeroGuess*.

#### 3.4.4.142 HYPRE\_StructPFMGSetNumPostRelax()

```
HYPRE_Int HYPRE_StructPFMGSetNumPostRelax (
    HYPRE_StructSolver solver,
    HYPRE_Int num_post_relax )
```

(Optional) Set number of relaxation sweeps after coarse-grid correction.

#### 3.4.4.143 HYPRE\_StructPFMGSetNumPreRelax()

```
HYPRE_Int HYPRE_StructPFMGSetNumPreRelax (
    HYPRE_StructSolver solver,
    HYPRE_Int num_pre_relax )
```

(Optional) Set number of relaxation sweeps before coarse-grid correction.



**3.4.4.144 HYPRE\_StructPFMGSetPrintLevel()**

```
HYPRE_Int HYPRE_StructPFMGSetPrintLevel (
    HYPRE_StructSolver solver,
    HYPRE_Int print_level )
```

(Optional) Set the amount of printing to do to the screen.

**3.4.4.145 HYPRE\_StructPFMGSetRAPType()**

```
HYPRE_Int HYPRE_StructPFMGSetRAPType (
    HYPRE_StructSolver solver,
    HYPRE_Int rap_type )
```

(Optional) Set type of coarse-grid operator to use.

Current operators set by *rap\_type* are:

- 0 : Galerkin (default)
- 1 : non-Galerkin 5-pt or 7-pt stencils

Both operators are constructed algebraically. The non-Galerkin option maintains a 5-pt stencil in 2D and a 7-pt stencil in 3D on all grid levels. The stencil coefficients are computed by averaging techniques.

**3.4.4.146 HYPRE\_StructPFMGSetRelaxType()**

```
HYPRE_Int HYPRE_StructPFMGSetRelaxType (
    HYPRE_StructSolver solver,
    HYPRE_Int relax_type )
```

(Optional) Set relaxation type.

Current relaxation methods set by *relax\_type* are:

- 0 : Jacobi
- 1 : Weighted Jacobi (default)
- 2 : Red/Black Gauss-Seidel (symmetric: RB pre-relaxation, BR post-relaxation)
- 3 : Red/Black Gauss-Seidel (nonsymmetric: RB pre- and post-relaxation)

**3.4.4.147 HYPRE\_StructPFMGSetRelChange()**

```
HYPRE_Int HYPRE_StructPFMGSetRelChange (
    HYPRE_StructSolver solver,
    HYPRE_Int rel_change )
```

(Optional) Additionally require that the relative difference in successive iterates be small.

**3.4.4.148 HYPRE\_StructPFMGSetSkipRelax()**

```
HYPRE_Int HYPRE_StructPFMGSetSkipRelax (
    HYPRE_StructSolver solver,
    HYPRE_Int skip_relax )
```

(Optional) Skip relaxation on certain grids for isotropic problems. This can greatly improve efficiency by eliminating unnecessary relaxations when the underlying problem is isotropic.

**3.4.4.149 HYPRE\_StructPFMGSetTol()**

```
HYPRE_Int HYPRE_StructPFMGSetTol (
    HYPRE_StructSolver solver,
    HYPRE_Real tol )
```

(Optional) Set the convergence tolerance.

**3.4.4.150 HYPRE\_StructPFMGSetup()**

```
HYPRE_Int HYPRE_StructPFMGSetup (
    HYPRE_StructSolver solver,
    HYPRE_StructMatrix A,
    HYPRE_StructVector b,
    HYPRE_StructVector x )
```

Prepare to solve the system. The coefficient data in *b* and *x* is ignored here, but information about the layout of the data may be used.

**3.4.4.151 HYPRE\_StructPFMGSetZeroGuess()**

```
HYPRE_Int HYPRE_StructPFMGSetZeroGuess (
    HYPRE_StructSolver solver )
```

(Optional) Use a zero initial guess. This allows the solver to cut corners in the case where a zero initial guess is needed (e.g., for preconditioning) to reduce computational cost.

**3.4.4.152 HYPRE\_StructPFMGsolve()**

```
HYPRE_Int HYPRE_StructPFMGsolve (
    HYPRE_StructSolver solver,
    HYPRE_StructMatrix A,
    HYPRE_StructVector b,
    HYPRE_StructVector x )
```

Solve the system.

**3.4.4.153 HYPRE\_StructSetupInterpreter()**

```
HYPRE_Int HYPRE_StructSetupInterpreter (
    mv_InterfaceInterpreter * i )
```

Load interface interpreter. Vector part loaded with hypre\_StructKrylov functions and multivector part loaded with mv\_TempMultiVector functions.

**3.4.4.154 HYPRE\_StructSetupMatvec()**

```
HYPRE_Int HYPRE_StructSetupMatvec (
    HYPRE_MatvecFunctions * mv )
```

Load Matvec interpreter with hypre\_StructKrylov functions.

**3.4.4.155 HYPRE\_StructSMGCreate()**

```
HYPRE_Int HYPRE_StructSMGCreate (
    MPI_Comm comm,
    HYPRE_StructSolver * solver )
```

Create a solver object.

**3.4.4.156 HYPRE\_StructSMGDestroy()**

```
HYPRE_Int HYPRE_StructSMGDestroy (
    HYPRE_StructSolver solver )
```

Destroy a solver object.

**3.4.4.157 HYPRE\_StructSMGGetFinalRelativeResidualNorm()**

```
HYPRE_Int HYPRE_StructSMGGetFinalRelativeResidualNorm (
    HYPRE_StructSolver solver,
    HYPRE_Real * norm )
```

Return the norm of the final relative residual.

**3.4.4.158 HYPRE\_StructSMGGetLogging()**

```
HYPRE_Int HYPRE_StructSMGGetLogging (
    HYPRE_StructSolver solver,
    HYPRE_Int * logging )
```

**3.4.4.159 HYPRE\_StructSMGGetMaxIter()**

```
HYPRE_Int HYPRE_StructSMGGetMaxIter (
    HYPRE_StructSolver solver,
    HYPRE_Int * max_iter )
```

#### 3.4.4.160 HYPRE\_StructSMGGetMemoryUse()

```
HYPRE_Int HYPRE_StructSMGGetMemoryUse (
    HYPRE_StructSolver solver,
    HYPRE_Int * memory_use )
```

#### 3.4.4.161 HYPRE\_StructSMGGetNumIterations()

```
HYPRE_Int HYPRE_StructSMGGetNumIterations (
    HYPRE_StructSolver solver,
    HYPRE_Int * num_iterations )
```

Return the number of iterations taken.

#### 3.4.4.162 HYPRE\_StructSMGGetNumPostRelax()

```
HYPRE_Int HYPRE_StructSMGGetNumPostRelax (
    HYPRE_StructSolver solver,
    HYPRE_Int * num_post_relax )
```

#### 3.4.4.163 HYPRE\_StructSMGGetNumPreRelax()

```
HYPRE_Int HYPRE_StructSMGGetNumPreRelax (
    HYPRE_StructSolver solver,
    HYPRE_Int * num_pre_relax )
```

#### 3.4.4.164 HYPRE\_StructSMGGetPrintLevel()

```
HYPRE_Int HYPRE_StructSMGGetPrintLevel (
    HYPRE_StructSolver solver,
    HYPRE_Int * print_level )
```

#### 3.4.4.165 HYPRE\_StructSMGGetRelChange()

```
HYPRE_Int HYPRE_StructSMGGetRelChange (
    HYPRE_StructSolver solver,
    HYPRE_Int * rel_change )
```

#### 3.4.4.166 HYPRE\_StructSMGGetTol()

```
HYPRE_Int HYPRE_StructSMGGetTol (
    HYPRE_StructSolver solver,
    HYPRE_Real * tol )
```

**3.4.4.167 HYPRE\_StructSMGGetZeroGuess()**

```
HYPRE_Int HYPRE_StructSMGGetZeroGuess (
    HYPRE_StructSolver solver,
    HYPRE_Int * zeroguess )
```

**3.4.4.168 HYPRE\_StructSMGSetLogging()**

```
HYPRE_Int HYPRE_StructSMGSetLogging (
    HYPRE_StructSolver solver,
    HYPRE_Int logging )
```

(Optional) Set the amount of logging to do.

**3.4.4.169 HYPRE\_StructSMGSetMaxIter()**

```
HYPRE_Int HYPRE_StructSMGSetMaxIter (
    HYPRE_StructSolver solver,
    HYPRE_Int max_iter )
```

(Optional) Set maximum number of iterations.

**3.4.4.170 HYPRE\_StructSMGSetMemoryUse()**

```
HYPRE_Int HYPRE_StructSMGSetMemoryUse (
    HYPRE_StructSolver solver,
    HYPRE_Int memory_use )
```

**3.4.4.171 HYPRE\_StructSMGSetNonZeroGuess()**

```
HYPRE_Int HYPRE_StructSMGSetNonZeroGuess (
    HYPRE_StructSolver solver )
```

(Optional) Use a nonzero initial guess. This is the default behavior, but this routine allows the user to switch back after using *SetZeroGuess*.

**3.4.4.172 HYPRE\_StructSMGSetNumPostRelax()**

```
HYPRE_Int HYPRE_StructSMGSetNumPostRelax (
    HYPRE_StructSolver solver,
    HYPRE_Int num_post_relax )
```

(Optional) Set number of relaxation sweeps after coarse-grid correction.

**3.4.4.173 HYPRE\_StructSMGSetNumPreRelax()**

```
HYPRE_Int HYPRE_StructSMGSetNumPreRelax (
    HYPRE_StructSolver solver,
    HYPRE_Int num_pre_relax )
```

(Optional) Set number of relaxation sweeps before coarse-grid correction.

**3.4.4.174 HYPRE\_StructSMGSetPrintLevel()**

```
HYPRE_Int HYPRE_StructSMGSetPrintLevel (
    HYPRE_StructSolver solver,
    HYPRE_Int print_level )
```

(Optional) Set the amount of printing to do to the screen.

**3.4.4.175 HYPRE\_StructSMGSetRelChange()**

```
HYPRE_Int HYPRE_StructSMGSetRelChange (
    HYPRE_StructSolver solver,
    HYPRE_Int rel_change )
```

(Optional) Additionally require that the relative difference in successive iterates be small.

**3.4.4.176 HYPRE\_StructSMGSetTol()**

```
HYPRE_Int HYPRE_StructSMGSetTol (
    HYPRE_StructSolver solver,
    HYPRE_Real tol )
```

(Optional) Set the convergence tolerance.

**3.4.4.177 HYPRE\_StructSMGSetup()**

```
HYPRE_Int HYPRE_StructSMGSetup (
    HYPRE_StructSolver solver,
    HYPRE_StructMatrix A,
    HYPRE_StructVector b,
    HYPRE_StructVector x )
```

Prepare to solve the system. The coefficient data in *b* and *x* is ignored here, but information about the layout of the data may be used.

**3.4.4.178 HYPRE\_StructSMGSetZeroGuess()**

```
HYPRE_Int HYPRE_StructSMGSetZeroGuess (
    HYPRE_StructSolver solver )
```

(Optional) Use a zero initial guess. This allows the solver to cut corners in the case where a zero initial guess is needed (e.g., for preconditioning) to reduce computational cost.

**3.4.4.179 HYPRE\_StructSMGSolve()**

```
HYPRE_Int HYPRE_StructSMGSolve (
    HYPRE_StructSolver solver,
    HYPRE_StructMatrix A,
    HYPRE_StructVector b,
    HYPRE_StructVector x )
```

Solve the system.

**3.4.4.180 HYPRE\_StructSparseMSGCreate()**

```
HYPRE_Int HYPRE_StructSparseMSGCreate (
    MPI_Comm comm,
    HYPRE_StructSolver * solver )
```

**3.4.4.181 HYPRE\_StructSparseMSGDestroy()**

```
HYPRE_Int HYPRE_StructSparseMSGDestroy (
    HYPRE_StructSolver solver )
```

**3.4.4.182 HYPRE\_StructSparseMSGGetFinalRelativeResidualNorm()**

```
HYPRE_Int HYPRE_StructSparseMSGGetFinalRelativeResidualNorm (
    HYPRE_StructSolver solver,
    HYPRE_Real * norm )
```

**3.4.4.183 HYPRE\_StructSparseMSGGetNumIterations()**

```
HYPRE_Int HYPRE_StructSparseMSGGetNumIterations (
    HYPRE_StructSolver solver,
    HYPRE_Int * num_iterations )
```

**3.4.4.184 HYPRE\_StructSparseMSGSetJacobiWeight()**

```
HYPRE_Int HYPRE_StructSparseMSGSetJacobiWeight (
    HYPRE_StructSolver solver,
    HYPRE_Real weight )
```

**3.4.4.185 HYPRE\_StructSparseMSGSetJump()**

```
HYPRE_Int HYPRE_StructSparseMSGSetJump (
    HYPRE_StructSolver solver,
    HYPRE_Int jump )
```

#### 3.4.4.186 HYPRE\_StructSparseMSGSetLogging()

```
HYPRE_Int HYPRE_StructSparseMSGSetLogging (
    HYPRE_StructSolver solver,
    HYPRE_Int logging )
```

#### 3.4.4.187 HYPRE\_StructSparseMSGSetMaxIter()

```
HYPRE_Int HYPRE_StructSparseMSGSetMaxIter (
    HYPRE_StructSolver solver,
    HYPRE_Int max_iter )
```

#### 3.4.4.188 HYPRE\_StructSparseMSGSetNonZeroGuess()

```
HYPRE_Int HYPRE_StructSparseMSGSetNonZeroGuess (
    HYPRE_StructSolver solver )
```

#### 3.4.4.189 HYPRE\_StructSparseMSGSetNumFineRelax()

```
HYPRE_Int HYPRE_StructSparseMSGSetNumFineRelax (
    HYPRE_StructSolver solver,
    HYPRE_Int num_fine_relax )
```

#### 3.4.4.190 HYPRE\_StructSparseMSGSetNumPostRelax()

```
HYPRE_Int HYPRE_StructSparseMSGSetNumPostRelax (
    HYPRE_StructSolver solver,
    HYPRE_Int num_post_relax )
```

#### 3.4.4.191 HYPRE\_StructSparseMSGSetNumPreRelax()

```
HYPRE_Int HYPRE_StructSparseMSGSetNumPreRelax (
    HYPRE_StructSolver solver,
    HYPRE_Int num_pre_relax )
```

#### 3.4.4.192 HYPRE\_StructSparseMSGSetPrintLevel()

```
HYPRE_Int HYPRE_StructSparseMSGSetPrintLevel (
    HYPRE_StructSolver solver,
    HYPRE_Int print_level )
```

#### 3.4.4.193 HYPRE\_StructSparseMSGSetRelaxType()

```
HYPRE_Int HYPRE_StructSparseMSGSetRelaxType (
    HYPRE_StructSolver solver,
    HYPRE_Int relax_type )
```



**3.4.4.194 HYPRE\_StructSparseMSGSetRelChange()**

```
HYPRE_Int HYPRE_StructSparseMSGSetRelChange (
    HYPRE_StructSolver solver,
    HYPRE_Int rel_change )
```

**3.4.4.195 HYPRE\_StructSparseMSGSetTol()**

```
HYPRE_Int HYPRE_StructSparseMSGSetTol (
    HYPRE_StructSolver solver,
    HYPRE_Real tol )
```

**3.4.4.196 HYPRE\_StructSparseMSGSetup()**

```
HYPRE_Int HYPRE_StructSparseMSGSetup (
    HYPRE_StructSolver solver,
    HYPRE_StructMatrix A,
    HYPRE_StructVector b,
    HYPRE_StructVector x )
```

**3.4.4.197 HYPRE\_StructSparseMSGSetZeroGuess()**

```
HYPRE_Int HYPRE_StructSparseMSGSetZeroGuess (
    HYPRE_StructSolver solver )
```

**3.4.4.198 HYPRE\_StructSparseMSGSolve()**

```
HYPRE_Int HYPRE_StructSparseMSGSolve (
    HYPRE_StructSolver solver,
    HYPRE_StructMatrix A,
    HYPRE_StructVector b,
    HYPRE_StructVector x )
```

**3.5 SStruct Solvers****SStruct Solvers**

- typedef struct hypre\_SStructSolver\_struct \* [HYPRE\\_SStructSolver](#)
- typedef HYPRE\_Int(\* [HYPRE\\_PtrToSStructSolverFcn](#)) (HYPRE\_SStructSolver, [HYPRE\\_SStructMatrix](#), [HYPRE\\_SStructVector](#), [HYPRE\\_SStructVector](#))
- typedef struct hypre\_Solver\_struct \* [HYPRE\\_Solver](#)
- typedef HYPRE\_Int(\* [HYPRE\\_PtrToModifyPCFcn](#)) (HYPRE\_Solver, HYPRE\_Int, HYPRE\_Real)
- #define [HYPRE\\_MODIFYPC](#)
- #define [HYPRE\\_SOLVER\\_STRUCT](#)

## SStruct SysPFMG Solver

SysPFMG is a semicoarsening multigrid solver similar to PFMG, but for systems of PDEs. For periodic problems, users should try to set the grid size in periodic dimensions to be as close to a power-of-two as possible (for more details, see Struct PFMG Solver).

- HYPRE\_Int [HYPRE\\_SStructSysPFMGCreate](#) (MPI\_Comm comm, [HYPRE\\_SStructSolver](#) \*solver)
- HYPRE\_Int [HYPRE\\_SStructSysPFMGDestroy](#) ([HYPRE\\_SStructSolver](#) solver)
- HYPRE\_Int [HYPRE\\_SStructSysPFMGSetup](#) ([HYPRE\\_SStructSolver](#) solver, [HYPRE\\_SStructMatrix](#) A, [HYPRE\\_SStructVector](#) b, [HYPRE\\_SStructVector](#) x)
- HYPRE\_Int [HYPRE\\_SStructSysPFMGsolve](#) ([HYPRE\\_SStructSolver](#) solver, [HYPRE\\_SStructMatrix](#) A, [HYPRE\\_SStructVector](#) b, [HYPRE\\_SStructVector](#) x)
- HYPRE\_Int [HYPRE\\_SStructSysPFMGSetTol](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_SStructSysPFMGSetMaxIter](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Int max\_iter)
- HYPRE\_Int [HYPRE\\_SStructSysPFMGSetRelChange](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Int rel\_change)
- HYPRE\_Int [HYPRE\\_SStructSysPFMGSetZeroGuess](#) ([HYPRE\\_SStructSolver](#) solver)
- HYPRE\_Int [HYPRE\\_SStructSysPFMGSetNonZeroGuess](#) ([HYPRE\\_SStructSolver](#) solver)
- HYPRE\_Int [HYPRE\\_SStructSysPFMGSetRelaxType](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Int relax\_type)
- HYPRE\_Int [HYPRE\\_SStructSysPFMGSetJacobiWeight](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Real weight)
- HYPRE\_Int [HYPRE\\_SStructSysPFMGSetNumPreRelax](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Int num\_pre\_relax)
- HYPRE\_Int [HYPRE\\_SStructSysPFMGSetNumPostRelax](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Int num\_post\_relax)
- HYPRE\_Int [HYPRE\\_SStructSysPFMGSetSkipRelax](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Int skip\_relax)
- HYPRE\_Int [HYPRE\\_SStructSysPFMGSetDxyz](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Real \*dxyz)
- HYPRE\_Int [HYPRE\\_SStructSysPFMGSetLogging](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Int logging)
- HYPRE\_Int [HYPRE\\_SStructSysPFMGSetPrintLevel](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Int print\_level)
- HYPRE\_Int [HYPRE\\_SStructSysPFMGGetNumIterations](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Int \*num\_iterations)
- HYPRE\_Int [HYPRE\\_SStructSysPFMGGetFinalRelativeResidualNorm](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Real \*norm)

## SStruct Split Solver

- HYPRE\_Int [HYPRE\\_SStructSplitCreate](#) (MPI\_Comm comm, [HYPRE\\_SStructSolver](#) \*solver)
- HYPRE\_Int [HYPRE\\_SStructSplitDestroy](#) ([HYPRE\\_SStructSolver](#) solver)
- HYPRE\_Int [HYPRE\\_SStructSplitSetup](#) ([HYPRE\\_SStructSolver](#) solver, [HYPRE\\_SStructMatrix](#) A, [HYPRE\\_SStructVector](#) b, [HYPRE\\_SStructVector](#) x)
- HYPRE\_Int [HYPRE\\_SStructSplitSolve](#) ([HYPRE\\_SStructSolver](#) solver, [HYPRE\\_SStructMatrix](#) A, [HYPRE\\_SStructVector](#) b, [HYPRE\\_SStructVector](#) x)
- HYPRE\_Int [HYPRE\\_SStructSplitSetTol](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_SStructSplitSetMaxIter](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Int max\_iter)
- HYPRE\_Int [HYPRE\\_SStructSplitSetZeroGuess](#) ([HYPRE\\_SStructSolver](#) solver)
- HYPRE\_Int [HYPRE\\_SStructSplitSetNonZeroGuess](#) ([HYPRE\\_SStructSolver](#) solver)
- HYPRE\_Int [HYPRE\\_SStructSplitSetStructSolver](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Int ssolver)
- HYPRE\_Int [HYPRE\\_SStructSplitGetNumIterations](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Int \*num\_iterations)
- HYPRE\_Int [HYPRE\\_SStructSplitGetFinalRelativeResidualNorm](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Real \*norm)
- #define [HYPRE\\_PFMG](#) 10
- #define [HYPRE\\_SMG](#) 11
- #define [HYPRE\\_Jacobi](#) 17

**SStruct FAC Solver**

- HYPRE\_Int [HYPRE\\_SStructFACCreate](#) (MPI\_Comm comm, [HYPRE\\_SStructSolver](#) \*solver)
- HYPRE\_Int [HYPRE\\_SStructFACDestroy2](#) ([HYPRE\\_SStructSolver](#) solver)
- HYPRE\_Int [HYPRE\\_SStructFACAMR\\_RAP](#) ([HYPRE\\_SStructMatrix](#) A, HYPRE\_Int(\*rfactors)[HYPRE\_↵  
MAXDIM], [HYPRE\\_SStructMatrix](#) \*fac\_A)
- HYPRE\_Int [HYPRE\\_SStructFACSetup2](#) ([HYPRE\\_SStructSolver](#) solver, [HYPRE\\_SStructMatrix](#) A,  
[HYPRE\\_SStructVector](#) b, [HYPRE\\_SStructVector](#) x)
- HYPRE\_Int [HYPRE\\_SStructFAColve3](#) ([HYPRE\\_SStructSolver](#) solver, [HYPRE\\_SStructMatrix](#) A,  
[HYPRE\\_SStructVector](#) b, [HYPRE\\_SStructVector](#) x)
- HYPRE\_Int [HYPRE\\_SStructFACSetPLevels](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Int nparts, HYPRE\_Int  
\*plevels)
- HYPRE\_Int [HYPRE\\_SStructFACSetPRefinements](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Int nparts,  
HYPRE\_Int(\*rfactors)[HYPRE\_MAXDIM])
- HYPRE\_Int [HYPRE\\_SStructFACZeroCFSten](#) ([HYPRE\\_SStructMatrix](#) A, [HYPRE\\_SStructGrid](#) grid,  
HYPRE\_Int part, HYPRE\_Int rfactors[HYPRE\_MAXDIM])
- HYPRE\_Int [HYPRE\\_SStructFACZeroFCSten](#) ([HYPRE\\_SStructMatrix](#) A, [HYPRE\\_SStructGrid](#) grid,  
HYPRE\_Int part)
- HYPRE\_Int [HYPRE\\_SStructFACZeroAMRMatrixData](#) ([HYPRE\\_SStructMatrix](#) A, HYPRE\_Int part\_crse,  
HYPRE\_Int rfactors[HYPRE\_MAXDIM])
- HYPRE\_Int [HYPRE\\_SStructFACZeroAMRVectorData](#) ([HYPRE\\_SStructVector](#) b, HYPRE\_Int \*plevels,  
HYPRE\_Int(\*rfactors)[HYPRE\_MAXDIM])
- HYPRE\_Int [HYPRE\\_SStructFACSetMaxLevels](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Int max\_levels)
- HYPRE\_Int [HYPRE\\_SStructFACSetTol](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_SStructFACSetMaxIter](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Int max\_iter)
- HYPRE\_Int [HYPRE\\_SStructFACSetRelChange](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Int rel\_change)
- HYPRE\_Int [HYPRE\\_SStructFACSetZeroGuess](#) ([HYPRE\\_SStructSolver](#) solver)
- HYPRE\_Int [HYPRE\\_SStructFACSetNonZeroGuess](#) ([HYPRE\\_SStructSolver](#) solver)
- HYPRE\_Int [HYPRE\\_SStructFACSetRelaxType](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Int relax\_type)
- HYPRE\_Int [HYPRE\\_SStructFACSetJacobiWeight](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Real weight)
- HYPRE\_Int [HYPRE\\_SStructFACSetNumPreRelax](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Int num\_pre\_↵  
relax)
- HYPRE\_Int [HYPRE\\_SStructFACSetNumPostRelax](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Int num\_post\_↵  
\_relax)
- HYPRE\_Int [HYPRE\\_SStructFACSetCoarseSolverType](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Int csolver\_↵  
\_type)
- HYPRE\_Int [HYPRE\\_SStructFACSetLogging](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Int logging)
- HYPRE\_Int [HYPRE\\_SStructFACGetNumIterations](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Int \*num\_↵  
iterations)
- HYPRE\_Int [HYPRE\\_SStructFACGetFinalRelativeResidualNorm](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_↵  
Real \*norm)

**SStruct Maxwell Solver**

- HYPRE\_Int [HYPRE\\_SStructMaxwellCreate](#) (MPI\_Comm comm, [HYPRE\\_SStructSolver](#) \*solver)
- HYPRE\_Int [HYPRE\\_SStructMaxwellDestroy](#) ([HYPRE\\_SStructSolver](#) solver)
- HYPRE\_Int [HYPRE\\_SStructMaxwellSetup](#) ([HYPRE\\_SStructSolver](#) solver, [HYPRE\\_SStructMatrix](#) A,  
[HYPRE\\_SStructVector](#) b, [HYPRE\\_SStructVector](#) x)
- HYPRE\_Int [HYPRE\\_SStructMaxwellSolve](#) ([HYPRE\\_SStructSolver](#) solver, [HYPRE\\_SStructMatrix](#) A,  
[HYPRE\\_SStructVector](#) b, [HYPRE\\_SStructVector](#) x)
- HYPRE\_Int [HYPRE\\_SStructMaxwellSolve2](#) ([HYPRE\\_SStructSolver](#) solver, [HYPRE\\_SStructMatrix](#) A,  
[HYPRE\\_SStructVector](#) b, [HYPRE\\_SStructVector](#) x)
- HYPRE\_Int [HYPRE\\_SStructMaxwellSetGrad](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_ParCSRMatrix T)
- HYPRE\_Int [HYPRE\\_SStructMaxwellSetRfactors](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Int rfactors[HYPRE\_↵  
\_MAXDIM])

- HYPRE\_Int [HYPRE\\_SStructMaxwellPhysBdy](#) (HYPRE\_SStructGrid \*grid\_I, HYPRE\_Int num\_levels, HYPRE\_Int rfactors[HYPRE\_MAXDIM], HYPRE\_Int \*\*\*BdryRanks\_ptr, HYPRE\_Int \*\*BdryRanksCnt↵\_ptr)
- HYPRE\_Int [HYPRE\\_SStructMaxwellEliminateRowsCols](#) (HYPRE\_ParCSRMatrix parA, HYPRE\_Int nrows, HYPRE\_Int \*rows)
- HYPRE\_Int [HYPRE\\_SStructMaxwellZeroVector](#) (HYPRE\_ParVector b, HYPRE\_Int \*rows, HYPRE\_Int nrows)
- HYPRE\_Int [HYPRE\\_SStructMaxwellSetSetConstantCoef](#) (HYPRE\_SStructSolver solver, HYPRE\_Int flag)
- HYPRE\_Int [HYPRE\\_SStructMaxwellGrad](#) (HYPRE\_SStructGrid grid, HYPRE\_ParCSRMatrix \*T)
- HYPRE\_Int [HYPRE\\_SStructMaxwellSetTol](#) (HYPRE\_SStructSolver solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_SStructMaxwellSetMaxIter](#) (HYPRE\_SStructSolver solver, HYPRE\_Int max\_iter)
- HYPRE\_Int [HYPRE\\_SStructMaxwellSetRelChange](#) (HYPRE\_SStructSolver solver, HYPRE\_Int rel\_change)
- HYPRE\_Int [HYPRE\\_SStructMaxwellSetNumPreRelax](#) (HYPRE\_SStructSolver solver, HYPRE\_Int num\_↵pre\_relax)
- HYPRE\_Int [HYPRE\\_SStructMaxwellSetNumPostRelax](#) (HYPRE\_SStructSolver solver, HYPRE\_Int num\_↵post\_relax)
- HYPRE\_Int [HYPRE\\_SStructMaxwellSetLogging](#) (HYPRE\_SStructSolver solver, HYPRE\_Int logging)
- HYPRE\_Int [HYPRE\\_SStructMaxwellGetNumIterations](#) (HYPRE\_SStructSolver solver, HYPRE\_Int \*num\_↵iterations)
- HYPRE\_Int [HYPRE\\_SStructMaxwellGetFinalRelativeResidualNorm](#) (HYPRE\_SStructSolver solver, HYPRE\_Real \*norm)

## SStruct PCG Solver

These routines should be used in conjunction with the generic interface in [Krylov Solvers](#).

- HYPRE\_Int [HYPRE\\_SStructPCGCreate](#) (MPI\_Comm comm, HYPRE\_SStructSolver \*solver)
- HYPRE\_Int [HYPRE\\_SStructPCGDestroy](#) (HYPRE\_SStructSolver solver)
- HYPRE\_Int [HYPRE\\_SStructPCGSetup](#) (HYPRE\_SStructSolver solver, HYPRE\_SStructMatrix A, HYPRE\_SStructVector b, HYPRE\_SStructVector x)
- HYPRE\_Int [HYPRE\\_SStructPCGSolve](#) (HYPRE\_SStructSolver solver, HYPRE\_SStructMatrix A, HYPRE\_SStructVector b, HYPRE\_SStructVector x)
- HYPRE\_Int [HYPRE\\_SStructPCGSetTol](#) (HYPRE\_SStructSolver solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_SStructPCGSetAbsoluteTol](#) (HYPRE\_SStructSolver solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_SStructPCGSetMaxIter](#) (HYPRE\_SStructSolver solver, HYPRE\_Int max\_iter)
- HYPRE\_Int [HYPRE\\_SStructPCGSetTwoNorm](#) (HYPRE\_SStructSolver solver, HYPRE\_Int two\_norm)
- HYPRE\_Int [HYPRE\\_SStructPCGSetRelChange](#) (HYPRE\_SStructSolver solver, HYPRE\_Int rel\_change)
- HYPRE\_Int [HYPRE\\_SStructPCGSetPrecond](#) (HYPRE\_SStructSolver solver, HYPRE\_PtrToSStructSolverFcn precondition, HYPRE\_PtrToSStructSolverFcn precondition\_setup, void \*precond\_solver)
- HYPRE\_Int [HYPRE\\_SStructPCGSetLogging](#) (HYPRE\_SStructSolver solver, HYPRE\_Int logging)
- HYPRE\_Int [HYPRE\\_SStructPCGSetPrintLevel](#) (HYPRE\_SStructSolver solver, HYPRE\_Int level)
- HYPRE\_Int [HYPRE\\_SStructPCGGetNumIterations](#) (HYPRE\_SStructSolver solver, HYPRE\_Int \*num\_↵iterations)
- HYPRE\_Int [HYPRE\\_SStructPCGGetFinalRelativeResidualNorm](#) (HYPRE\_SStructSolver solver, HYPRE\_↵Real \*norm)
- HYPRE\_Int [HYPRE\\_SStructPCGGetResidual](#) (HYPRE\_SStructSolver solver, void \*\*residual)
- HYPRE\_Int [HYPRE\\_SStructDiagScaleSetup](#) (HYPRE\_SStructSolver solver, HYPRE\_SStructMatrix A, HYPRE\_SStructVector y, HYPRE\_SStructVector x)
- HYPRE\_Int [HYPRE\\_SStructDiagScale](#) (HYPRE\_SStructSolver solver, HYPRE\_SStructMatrix A, HYPRE\_SStructVector y, HYPRE\_SStructVector x)

### SStruct GMRES Solver

These routines should be used in conjunction with the generic interface in [Krylov Solvers](#).

- HYPRE\_Int [HYPRE\\_SStructGMRESCreate](#) (MPI\_Comm comm, [HYPRE\\_SStructSolver](#) \*solver)
- HYPRE\_Int [HYPRE\\_SStructGMRESDestroy](#) ([HYPRE\\_SStructSolver](#) solver)
- HYPRE\_Int [HYPRE\\_SStructGMRESSetup](#) ([HYPRE\\_SStructSolver](#) solver, [HYPRE\\_SStructMatrix](#) A, [HYPRE\\_SStructVector](#) b, [HYPRE\\_SStructVector](#) x)
- HYPRE\_Int [HYPRE\\_SStructGMRESSolve](#) ([HYPRE\\_SStructSolver](#) solver, [HYPRE\\_SStructMatrix](#) A, [HYPRE\\_SStructVector](#) b, [HYPRE\\_SStructVector](#) x)
- HYPRE\_Int [HYPRE\\_SStructGMRESSetTol](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_SStructGMRESSetAbsoluteTol](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_SStructGMRESSetMinIter](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Int min\_iter)
- HYPRE\_Int [HYPRE\\_SStructGMRESSetMaxIter](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Int max\_iter)
- HYPRE\_Int [HYPRE\\_SStructGMRESSetKDim](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Int k\_dim)
- HYPRE\_Int [HYPRE\\_SStructGMRESSetStopCrit](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Int stop\_crit)
- HYPRE\_Int [HYPRE\\_SStructGMRESSetPrecond](#) ([HYPRE\\_SStructSolver](#) solver, [HYPRE\\_PtrToSStructSolverFcn](#) precondition, [HYPRE\\_PtrToSStructSolverFcn](#) precondition\_setup, void \*precond\_solver)
- HYPRE\_Int [HYPRE\\_SStructGMRESSetLogging](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Int logging)
- HYPRE\_Int [HYPRE\\_SStructGMRESSetPrintLevel](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Int print\_level)
- HYPRE\_Int [HYPRE\\_SStructGMRESGetNumIterations](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Int \*num\_↵ iterations)
- HYPRE\_Int [HYPRE\\_SStructGMRESGetFinalRelativeResidualNorm](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Real \*norm)
- HYPRE\_Int [HYPRE\\_SStructGMRESGetResidual](#) ([HYPRE\\_SStructSolver](#) solver, void \*\*residual)

### SStruct FlexGMRES Solver

These routines should be used in conjunction with the generic interface in [Krylov Solvers](#).

- HYPRE\_Int [HYPRE\\_SStructFlexGMRESCreate](#) (MPI\_Comm comm, [HYPRE\\_SStructSolver](#) \*solver)
- HYPRE\_Int [HYPRE\\_SStructFlexGMRESDestroy](#) ([HYPRE\\_SStructSolver](#) solver)
- HYPRE\_Int [HYPRE\\_SStructFlexGMRESSetup](#) ([HYPRE\\_SStructSolver](#) solver, [HYPRE\\_SStructMatrix](#) A, [HYPRE\\_SStructVector](#) b, [HYPRE\\_SStructVector](#) x)
- HYPRE\_Int [HYPRE\\_SStructFlexGMRESSolve](#) ([HYPRE\\_SStructSolver](#) solver, [HYPRE\\_SStructMatrix](#) A, [HYPRE\\_SStructVector](#) b, [HYPRE\\_SStructVector](#) x)
- HYPRE\_Int [HYPRE\\_SStructFlexGMRESSetTol](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_SStructFlexGMRESSetAbsoluteTol](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_SStructFlexGMRESSetMinIter](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Int min\_iter)
- HYPRE\_Int [HYPRE\\_SStructFlexGMRESSetMaxIter](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Int max\_iter)
- HYPRE\_Int [HYPRE\\_SStructFlexGMRESSetKDim](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Int k\_dim)
- HYPRE\_Int [HYPRE\\_SStructFlexGMRESSetPrecond](#) ([HYPRE\\_SStructSolver](#) solver, [HYPRE\\_PtrToSStructSolverFcn](#) precondition, [HYPRE\\_PtrToSStructSolverFcn](#) precondition\_setup, void \*precond\_solver)
- HYPRE\_Int [HYPRE\\_SStructFlexGMRESSetLogging](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Int logging)
- HYPRE\_Int [HYPRE\\_SStructFlexGMRESSetPrintLevel](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Int print\_↵ level)
- HYPRE\_Int [HYPRE\\_SStructFlexGMRESGetNumIterations](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Int \*num\_↵ iterations)
- HYPRE\_Int [HYPRE\\_SStructFlexGMRESGetFinalRelativeResidualNorm](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Real \*norm)
- HYPRE\_Int [HYPRE\\_SStructFlexGMRESGetResidual](#) ([HYPRE\\_SStructSolver](#) solver, void \*\*residual)
- HYPRE\_Int [HYPRE\\_SStructFlexGMRESSetModifyPC](#) ([HYPRE\\_SStructSolver](#) solver, [HYPRE\\_PtrToModifyPCFcn](#) modify\_pc)

## SStruct LGMRES Solver

These routines should be used in conjunction with the generic interface in [Krylov Solvers](#).

- HYPRE\_Int [HYPRE\\_SStructLGMRESCreate](#) (MPI\_Comm comm, [HYPRE\\_SStructSolver](#) \*solver)
- HYPRE\_Int [HYPRE\\_SStructLGMRESDestroy](#) ([HYPRE\\_SStructSolver](#) solver)
- HYPRE\_Int [HYPRE\\_SStructLGMRESSetup](#) ([HYPRE\\_SStructSolver](#) solver, [HYPRE\\_SStructMatrix](#) A, [HYPRE\\_SStructVector](#) b, [HYPRE\\_SStructVector](#) x)
- HYPRE\_Int [HYPRE\\_SStructLGMRESSolve](#) ([HYPRE\\_SStructSolver](#) solver, [HYPRE\\_SStructMatrix](#) A, [HYPRE\\_SStructVector](#) b, [HYPRE\\_SStructVector](#) x)
- HYPRE\_Int [HYPRE\\_SStructLGMRESSetTol](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_SStructLGMRESSetAbsoluteTol](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_SStructLGMRESSetMinIter](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Int min\_iter)
- HYPRE\_Int [HYPRE\\_SStructLGMRESSetMaxIter](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Int max\_iter)
- HYPRE\_Int [HYPRE\\_SStructLGMRESSetKDim](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Int k\_dim)
- HYPRE\_Int [HYPRE\\_SStructLGMRESSetAugDim](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Int aug\_dim)
- HYPRE\_Int [HYPRE\\_SStructLGMRESSetPrecond](#) ([HYPRE\\_SStructSolver](#) solver, [HYPRE\\_PtrToSStructSolverFcn](#) precondition, [HYPRE\\_PtrToSStructSolverFcn](#) precondition\_setup, void \*precond\_solver)
- HYPRE\_Int [HYPRE\\_SStructLGMRESSetLogging](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Int logging)
- HYPRE\_Int [HYPRE\\_SStructLGMRESSetPrintLevel](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Int print\_level)
- HYPRE\_Int [HYPRE\\_SStructLGMRESGetNumIterations](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Int \*num\_↵\_iterations)
- HYPRE\_Int [HYPRE\\_SStructLGMRESGetFinalRelativeResidualNorm](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Real \*norm)
- HYPRE\_Int [HYPRE\\_SStructLGMRESGetResidual](#) ([HYPRE\\_SStructSolver](#) solver, void \*\*residual)

## SStruct BiCGSTAB Solver

These routines should be used in conjunction with the generic interface in [Krylov Solvers](#).

- HYPRE\_Int [HYPRE\\_SStructBiCGSTABCreate](#) (MPI\_Comm comm, [HYPRE\\_SStructSolver](#) \*solver)
- HYPRE\_Int [HYPRE\\_SStructBiCGSTABDestroy](#) ([HYPRE\\_SStructSolver](#) solver)
- HYPRE\_Int [HYPRE\\_SStructBiCGSTABSetup](#) ([HYPRE\\_SStructSolver](#) solver, [HYPRE\\_SStructMatrix](#) A, [HYPRE\\_SStructVector](#) b, [HYPRE\\_SStructVector](#) x)
- HYPRE\_Int [HYPRE\\_SStructBiCGSTABSolve](#) ([HYPRE\\_SStructSolver](#) solver, [HYPRE\\_SStructMatrix](#) A, [HYPRE\\_SStructVector](#) b, [HYPRE\\_SStructVector](#) x)
- HYPRE\_Int [HYPRE\\_SStructBiCGSTABSetTol](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_SStructBiCGSTABSetAbsoluteTol](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_SStructBiCGSTABSetMinIter](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Int min\_iter)
- HYPRE\_Int [HYPRE\\_SStructBiCGSTABSetMaxIter](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Int max\_iter)
- HYPRE\_Int [HYPRE\\_SStructBiCGSTABSetStopCrit](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Int stop\_crit)
- HYPRE\_Int [HYPRE\\_SStructBiCGSTABSetPrecond](#) ([HYPRE\\_SStructSolver](#) solver, [HYPRE\\_PtrToSStructSolverFcn](#) precondition, [HYPRE\\_PtrToSStructSolverFcn](#) precondition\_setup, void \*precond\_solver)
- HYPRE\_Int [HYPRE\\_SStructBiCGSTABSetLogging](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Int logging)
- HYPRE\_Int [HYPRE\\_SStructBiCGSTABSetPrintLevel](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Int level)
- HYPRE\_Int [HYPRE\\_SStructBiCGSTABGetNumIterations](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Int \*num\_↵\_iterations)
- HYPRE\_Int [HYPRE\\_SStructBiCGSTABGetFinalRelativeResidualNorm](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Real \*norm)
- HYPRE\_Int [HYPRE\\_SStructBiCGSTABGetResidual](#) ([HYPRE\\_SStructSolver](#) solver, void \*\*residual)

### SStruct LOBPCG Eigensolver

These routines should be used in conjunction with the generic interface in [Eigensolvers](#).

- HYPRE\_Int [HYPRE\\_SStructSetupInterpreter](#) (mv\_InterfaceInterpreter \*i)
- HYPRE\_Int [HYPRE\\_SStructSetupMatvec](#) (HYPRE\_MatvecFunctions \*mv)

### 3.5.1 Detailed Description

These solvers use matrix/vector storage schemes that are tailored to semi-structured grid problems.

@memo Linear solvers for semi-structured grids

### 3.5.2 Macro Definition Documentation

#### 3.5.2.1 HYPRE\_Jacobi

```
#define HYPRE_Jacobi 17
```

#### 3.5.2.2 HYPRE\_MODIFYPC

```
#define HYPRE_MODIFYPC
```

#### 3.5.2.3 HYPRE\_PFMG

```
#define HYPRE_PFMG 10
```

#### 3.5.2.4 HYPRE\_SMG

```
#define HYPRE_SMG 11
```

#### 3.5.2.5 HYPRE\_SOLVER\_STRUCT

```
#define HYPRE_SOLVER_STRUCT
```

### 3.5.3 Typedef Documentation

#### 3.5.3.1 HYPRE\_PtrToModifyPCFcn

```
typedef HYPRE_Int (* HYPRE_PtrToModifyPCFcn) (HYPRE_Solver, HYPRE_Int, HYPRE_Real)
```

### 3.5.3.2 HYPRE\_PtrToSStructSolverFcn

```
typedef HYPRE_Int (* HYPRE_PtrToSStructSolverFcn) (HYPRE_SStructSolver, HYPRE_SStructMatrix,
HYPRE_SStructVector, HYPRE_SStructVector)
```

### 3.5.3.3 HYPRE\_Solver

```
typedef struct hypre_Solver_struct* HYPRE_Solver
```

### 3.5.3.4 HYPRE\_SStructSolver

```
typedef struct hypre_SStructSolver_struct* HYPRE_SStructSolver
```

The solver object.

## 3.5.4 Function Documentation

### 3.5.4.1 HYPRE\_SStructBiCGSTABCreate()

```
HYPRE_Int HYPRE_SStructBiCGSTABCreate (
    MPI_Comm comm,
    HYPRE_SStructSolver * solver )
```

Create a solver object.

### 3.5.4.2 HYPRE\_SStructBiCGSTABDestroy()

```
HYPRE_Int HYPRE_SStructBiCGSTABDestroy (
    HYPRE_SStructSolver solver )
```

Destroy a solver object. An object should be explicitly destroyed using this destructor when the user's code no longer needs direct access to it. Once destroyed, the object must not be referenced again. Note that the object may not be deallocated at the completion of this call, since there may be internal package references to the object. The object will then be destroyed when all internal reference counts go to zero.

### 3.5.4.3 HYPRE\_SStructBiCGSTABGetFinalRelativeResidualNorm()

```
HYPRE_Int HYPRE_SStructBiCGSTABGetFinalRelativeResidualNorm (
    HYPRE_SStructSolver solver,
    HYPRE_Real * norm )
```

### 3.5.4.4 HYPRE\_SStructBiCGSTABGetNumIterations()

```
HYPRE_Int HYPRE_SStructBiCGSTABGetNumIterations (
    HYPRE_SStructSolver solver,
    HYPRE_Int * num_iterations )
```



#### 3.5.4.5 HYPRE\_SStructBiCGSTABGetResidual()

```
HYPRE_Int HYPRE_SStructBiCGSTABGetResidual (
    HYPRE_SStructSolver solver,
    void ** residual )
```

#### 3.5.4.6 HYPRE\_SStructBiCGSTABSetAbsoluteTol()

```
HYPRE_Int HYPRE_SStructBiCGSTABSetAbsoluteTol (
    HYPRE_SStructSolver solver,
    HYPRE_Real tol )
```

#### 3.5.4.7 HYPRE\_SStructBiCGSTABSetLogging()

```
HYPRE_Int HYPRE_SStructBiCGSTABSetLogging (
    HYPRE_SStructSolver solver,
    HYPRE_Int logging )
```

#### 3.5.4.8 HYPRE\_SStructBiCGSTABSetMaxIter()

```
HYPRE_Int HYPRE_SStructBiCGSTABSetMaxIter (
    HYPRE_SStructSolver solver,
    HYPRE_Int max_iter )
```

#### 3.5.4.9 HYPRE\_SStructBiCGSTABSetMinIter()

```
HYPRE_Int HYPRE_SStructBiCGSTABSetMinIter (
    HYPRE_SStructSolver solver,
    HYPRE_Int min_iter )
```

#### 3.5.4.10 HYPRE\_SStructBiCGSTABSetPrecond()

```
HYPRE_Int HYPRE_SStructBiCGSTABSetPrecond (
    HYPRE_SStructSolver solver,
    HYPRE_PtrToSStructSolverFcn precondition,
    HYPRE_PtrToSStructSolverFcn precondition_setup,
    void * precondition_solver )
```

#### 3.5.4.11 HYPRE\_SStructBiCGSTABSetPrintLevel()

```
HYPRE_Int HYPRE_SStructBiCGSTABSetPrintLevel (
    HYPRE_SStructSolver solver,
    HYPRE_Int level )
```

**3.5.4.12 HYPRE\_SStructBiCGSTABSetStopCrit()**

```
HYPRE_Int HYPRE_SStructBiCGSTABSetStopCrit (
    HYPRE_SStructSolver solver,
    HYPRE_Int stop_crit )
```

**3.5.4.13 HYPRE\_SStructBiCGSTABSetTol()**

```
HYPRE_Int HYPRE_SStructBiCGSTABSetTol (
    HYPRE_SStructSolver solver,
    HYPRE_Real tol )
```

**3.5.4.14 HYPRE\_SStructBiCGSTABSetup()**

```
HYPRE_Int HYPRE_SStructBiCGSTABSetup (
    HYPRE_SStructSolver solver,
    HYPRE_SStructMatrix A,
    HYPRE_SStructVector b,
    HYPRE_SStructVector x )
```

**3.5.4.15 HYPRE\_SStructBiCGSTABSolve()**

```
HYPRE_Int HYPRE_SStructBiCGSTABSolve (
    HYPRE_SStructSolver solver,
    HYPRE_SStructMatrix A,
    HYPRE_SStructVector b,
    HYPRE_SStructVector x )
```

**3.5.4.16 HYPRE\_SStructDiagScale()**

```
HYPRE_Int HYPRE_SStructDiagScale (
    HYPRE_SStructSolver solver,
    HYPRE_SStructMatrix A,
    HYPRE_SStructVector y,
    HYPRE_SStructVector x )
```

Solve routine for diagonal preconditioning.

**3.5.4.17 HYPRE\_SStructDiagScaleSetup()**

```
HYPRE_Int HYPRE_SStructDiagScaleSetup (
    HYPRE_SStructSolver solver,
    HYPRE_SStructMatrix A,
    HYPRE_SStructVector y,
    HYPRE_SStructVector x )
```

Setup routine for diagonal preconditioning.

**3.5.4.18 HYPRE\_SStructFACAMR\_RAP()**

```

HYPRE_Int HYPRE_SStructFACAMR_RAP (
    HYPRE_SStructMatrix A,
    HYPRE_Int(*) rfactrors[HYPRE_MAXDIM],
    HYPRE_SStructMatrix * fac_A )

```

Re-distribute the composite matrix so that the amr hierachy is approximately nested. Coarse underlying operators are also formed.

**3.5.4.19 HYPRE\_SStructFACCreate()**

```

HYPRE_Int HYPRE_SStructFACCreate (
    MPI_Comm comm,
    HYPRE_SStructSolver * solver )

```

Create a solver object.

**3.5.4.20 HYPRE\_SStructFACDestroy2()**

```

HYPRE_Int HYPRE_SStructFACDestroy2 (
    HYPRE_SStructSolver solver )

```

Destroy a solver object. An object should be explicitly destroyed using this destructor when the user's code no longer needs direct access to it. Once destroyed, the object must not be referenced again. Note that the object may not be deallocated at the completion of this call, since there may be internal package references to the object. The object will then be destroyed when all internal reference counts go to zero.

**3.5.4.21 HYPRE\_SStructFACGetFinalRelativeResidualNorm()**

```

HYPRE_Int HYPRE_SStructFACGetFinalRelativeResidualNorm (
    HYPRE_SStructSolver solver,
    HYPRE_Real * norm )

```

Return the norm of the final relative residual.

**3.5.4.22 HYPRE\_SStructFACGetNumIterations()**

```

HYPRE_Int HYPRE_SStructFACGetNumIterations (
    HYPRE_SStructSolver solver,
    HYPRE_Int * num_iterations )

```

Return the number of iterations taken.

#### 3.5.4.23 HYPRE\_SStructFACSetCoarseSolverType()

```
HYPRE_Int HYPRE_SStructFACSetCoarseSolverType (
    HYPRE_SStructSolver solver,
    HYPRE_Int csolver_type )
```

(Optional) Set coarsest solver type.

Current solver types set by *csolver\_type* are:

- 1 : SysPFMG-PCG (default)
- 2 : SysPFMG

#### 3.5.4.24 HYPRE\_SStructFACSetJacobiWeight()

```
HYPRE_Int HYPRE_SStructFACSetJacobiWeight (
    HYPRE_SStructSolver solver,
    HYPRE_Real weight )
```

(Optional) Set Jacobi weight if weighted Jacobi is used.

#### 3.5.4.25 HYPRE\_SStructFACSetLogging()

```
HYPRE_Int HYPRE_SStructFACSetLogging (
    HYPRE_SStructSolver solver,
    HYPRE_Int logging )
```

(Optional) Set the amount of logging to do.

#### 3.5.4.26 HYPRE\_SStructFACSetMaxIter()

```
HYPRE_Int HYPRE_SStructFACSetMaxIter (
    HYPRE_SStructSolver solver,
    HYPRE_Int max_iter )
```

(Optional) Set maximum number of iterations.

#### 3.5.4.27 HYPRE\_SStructFACSetMaxLevels()

```
HYPRE_Int HYPRE_SStructFACSetMaxLevels (
    HYPRE_SStructSolver solver,
    HYPRE_Int max_levels )
```

(Optional) Set maximum number of FAC levels.

**3.5.4.28 HYPRE\_SStructFACSetNonZeroGuess()**

```
HYPRE_Int HYPRE_SStructFACSetNonZeroGuess (
    HYPRE_SStructSolver solver )
```

(Optional) Use a nonzero initial guess. This is the default behavior, but this routine allows the user to switch back after using *SetZeroGuess*.

**3.5.4.29 HYPRE\_SStructFACSetNumPostRelax()**

```
HYPRE_Int HYPRE_SStructFACSetNumPostRelax (
    HYPRE_SStructSolver solver,
    HYPRE_Int num_post_relax )
```

(Optional) Set number of relaxation sweeps after coarse-grid correction.

**3.5.4.30 HYPRE\_SStructFACSetNumPreRelax()**

```
HYPRE_Int HYPRE_SStructFACSetNumPreRelax (
    HYPRE_SStructSolver solver,
    HYPRE_Int num_pre_relax )
```

(Optional) Set number of relaxation sweeps before coarse-grid correction.

**3.5.4.31 HYPRE\_SStructFACSetPLevels()**

```
HYPRE_Int HYPRE_SStructFACSetPLevels (
    HYPRE_SStructSolver solver,
    HYPRE_Int nparts,
    HYPRE_Int * plevels )
```

Set up amr structure

**3.5.4.32 HYPRE\_SStructFACSetPRefinements()**

```
HYPRE_Int HYPRE_SStructFACSetPRefinements (
    HYPRE_SStructSolver solver,
    HYPRE_Int nparts,
    HYPRE_Int (*) rfactors[HYPRE_MAXDIM] )
```

Set up amr refinement factors

**3.5.4.33 HYPRE\_SStructFACSetRelaxType()**

```
HYPRE_Int HYPRE_SStructFACSetRelaxType (
    HYPRE_SStructSolver solver,
    HYPRE_Int relax_type )
```

(Optional) Set relaxation type. See [HYPRE\\_SStructSysPFMGSetRelaxType](#) for appropriate values of *relax\_type*.

**3.5.4.34 HYPRE\_SStructFACSetRelChange()**

```
HYPRE_Int HYPRE_SStructFACSetRelChange (
    HYPRE_SStructSolver solver,
    HYPRE_Int rel_change )
```

(Optional) Additionally require that the relative difference in successive iterates be small.

**3.5.4.35 HYPRE\_SStructFACSetTol()**

```
HYPRE_Int HYPRE_SStructFACSetTol (
    HYPRE_SStructSolver solver,
    HYPRE_Real tol )
```

(Optional) Set the convergence tolerance.

**3.5.4.36 HYPRE\_SStructFACSetup2()**

```
HYPRE_Int HYPRE_SStructFACSetup2 (
    HYPRE_SStructSolver solver,
    HYPRE_SStructMatrix A,
    HYPRE_SStructVector b,
    HYPRE_SStructVector x )
```

Set up the FAC solver structure .

**3.5.4.37 HYPRE\_SStructFACSetZeroGuess()**

```
HYPRE_Int HYPRE_SStructFACSetZeroGuess (
    HYPRE_SStructSolver solver )
```

(Optional) Use a zero initial guess. This allows the solver to cut corners in the case where a zero initial guess is needed (e.g., for preconditioning) to reduce computational cost.

**3.5.4.38 HYPRE\_SStructFACSolve3()**

```
HYPRE_Int HYPRE_SStructFACSolve3 (
    HYPRE_SStructSolver solver,
    HYPRE_SStructMatrix A,
    HYPRE_SStructVector b,
    HYPRE_SStructVector x )
```

Solve the system.

**3.5.4.39 HYPRE\_SStructFACZeroAMRMatrixData()**

```
HYPRE_Int HYPRE_SStructFACZeroAMRMatrixData (
    HYPRE_SStructMatrix A,
    HYPRE_Int part_crse,
    HYPRE_Int rfactors[HYPRE_MAXDIM] )
```

(Optional, but user must make sure that they do this function otherwise.) Places the identity in the coarse grid matrix underlying the fine patches. Required between each pair of amr levels.

**3.5.4.40 HYPRE\_SStructFACZeroAMRVectorData()**

```

HYPRE_Int HYPRE_SStructFACZeroAMRVectorData (
    HYPRE_SStructVector b,
    HYPRE_Int * plevels,
    HYPRE_Int (*) rfactors[HYPRE_MAXDIM] )

```

(Optional, but user must make sure that they do this function otherwise.) Places zeros in the coarse grid vector underlying the fine patches. Required between each pair of amr levels.

**3.5.4.41 HYPRE\_SStructFACZeroCFSten()**

```

HYPRE_Int HYPRE_SStructFACZeroCFSten (
    HYPRE_SStructMatrix A,
    HYPRE_SStructGrid grid,
    HYPRE_Int part,
    HYPRE_Int rfactors[HYPRE_MAXDIM] )

```

(Optional, but user must make sure that they do this function otherwise.) Zero off the coarse level stencils reaching into a fine level grid.

**3.5.4.42 HYPRE\_SStructFACZeroFCSten()**

```

HYPRE_Int HYPRE_SStructFACZeroFCSten (
    HYPRE_SStructMatrix A,
    HYPRE_SStructGrid grid,
    HYPRE_Int part )

```

(Optional, but user must make sure that they do this function otherwise.) Zero off the fine level stencils reaching into a coarse level grid.

**3.5.4.43 HYPRE\_SStructFlexGMRESCreate()**

```

HYPRE_Int HYPRE_SStructFlexGMRESCreate (
    MPI_Comm comm,
    HYPRE_SStructSolver * solver )

```

Create a solver object.

**3.5.4.44 HYPRE\_SStructFlexGMRESDestroy()**

```

HYPRE_Int HYPRE_SStructFlexGMRESDestroy (
    HYPRE_SStructSolver solver )

```

Destroy a solver object. An object should be explicitly destroyed using this destructor when the user's code no longer needs direct access to it. Once destroyed, the object must not be referenced again. Note that the object may not be deallocated at the completion of this call, since there may be internal package references to the object. The object will then be destroyed when all internal reference counts go to zero.

#### 3.5.4.45 HYPRE\_SStructFlexGMRESGetFinalRelativeResidualNorm()

```
HYPRE_Int HYPRE_SStructFlexGMRESGetFinalRelativeResidualNorm (
    HYPRE_SStructSolver solver,
    HYPRE_Real * norm )
```

#### 3.5.4.46 HYPRE\_SStructFlexGMRESGetNumIterations()

```
HYPRE_Int HYPRE_SStructFlexGMRESGetNumIterations (
    HYPRE_SStructSolver solver,
    HYPRE_Int * num_iterations )
```

#### 3.5.4.47 HYPRE\_SStructFlexGMRESGetResidual()

```
HYPRE_Int HYPRE_SStructFlexGMRESGetResidual (
    HYPRE_SStructSolver solver,
    void ** residual )
```

#### 3.5.4.48 HYPRE\_SStructFlexGMRESSetAbsoluteTol()

```
HYPRE_Int HYPRE_SStructFlexGMRESSetAbsoluteTol (
    HYPRE_SStructSolver solver,
    HYPRE_Real tol )
```

#### 3.5.4.49 HYPRE\_SStructFlexGMRESSetKDim()

```
HYPRE_Int HYPRE_SStructFlexGMRESSetKDim (
    HYPRE_SStructSolver solver,
    HYPRE_Int k_dim )
```

#### 3.5.4.50 HYPRE\_SStructFlexGMRESSetLogging()

```
HYPRE_Int HYPRE_SStructFlexGMRESSetLogging (
    HYPRE_SStructSolver solver,
    HYPRE_Int logging )
```

#### 3.5.4.51 HYPRE\_SStructFlexGMRESSetMaxIter()

```
HYPRE_Int HYPRE_SStructFlexGMRESSetMaxIter (
    HYPRE_SStructSolver solver,
    HYPRE_Int max_iter )
```

#### 3.5.4.52 HYPRE\_SStructFlexGMRESSetMinIter()

```
HYPRE_Int HYPRE_SStructFlexGMRESSetMinIter (
    HYPRE_SStructSolver solver,
    HYPRE_Int min_iter )
```



**3.5.4.53 HYPRE\_SStructFlexGMRESSetModifyPC()**

```
HYPRE_Int HYPRE_SStructFlexGMRESSetModifyPC (
    HYPRE_SStructSolver solver,
    HYPRE_PtrToModifyPCFcn modify_pc )
```

**3.5.4.54 HYPRE\_SStructFlexGMRESSetPrecond()**

```
HYPRE_Int HYPRE_SStructFlexGMRESSetPrecond (
    HYPRE_SStructSolver solver,
    HYPRE_PtrToSStructSolverFcn precondition,
    HYPRE_PtrToSStructSolverFcn precondition_setup,
    void * precondition_solver )
```

**3.5.4.55 HYPRE\_SStructFlexGMRESSetPrintLevel()**

```
HYPRE_Int HYPRE_SStructFlexGMRESSetPrintLevel (
    HYPRE_SStructSolver solver,
    HYPRE_Int print_level )
```

**3.5.4.56 HYPRE\_SStructFlexGMRESSetTol()**

```
HYPRE_Int HYPRE_SStructFlexGMRESSetTol (
    HYPRE_SStructSolver solver,
    HYPRE_Real tol )
```

**3.5.4.57 HYPRE\_SStructFlexGMRESSetup()**

```
HYPRE_Int HYPRE_SStructFlexGMRESSetup (
    HYPRE_SStructSolver solver,
    HYPRE_SStructMatrix A,
    HYPRE_SStructVector b,
    HYPRE_SStructVector x )
```

**3.5.4.58 HYPRE\_SStructFlexGMRESSolve()**

```
HYPRE_Int HYPRE_SStructFlexGMRESSolve (
    HYPRE_SStructSolver solver,
    HYPRE_SStructMatrix A,
    HYPRE_SStructVector b,
    HYPRE_SStructVector x )
```

**3.5.4.59 HYPRE\_SStructGMRESCreate()**

```
HYPRE_Int HYPRE_SStructGMRESCreate (
    MPI_Comm comm,
    HYPRE_SStructSolver * solver )
```

Create a solver object.

**3.5.4.60 HYPRE\_SStructGMRESDestroy()**

```
HYPRE_Int HYPRE_SStructGMRESDestroy (
    HYPRE_SStructSolver solver )
```

Destroy a solver object. An object should be explicitly destroyed using this destructor when the user's code no longer needs direct access to it. Once destroyed, the object must not be referenced again. Note that the object may not be deallocated at the completion of this call, since there may be internal package references to the object. The object will then be destroyed when all internal reference counts go to zero.

**3.5.4.61 HYPRE\_SStructGMRESGetFinalRelativeResidualNorm()**

```
HYPRE_Int HYPRE_SStructGMRESGetFinalRelativeResidualNorm (
    HYPRE_SStructSolver solver,
    HYPRE_Real * norm )
```

**3.5.4.62 HYPRE\_SStructGMRESGetNumIterations()**

```
HYPRE_Int HYPRE_SStructGMRESGetNumIterations (
    HYPRE_SStructSolver solver,
    HYPRE_Int * num_iterations )
```

**3.5.4.63 HYPRE\_SStructGMRESGetResidual()**

```
HYPRE_Int HYPRE_SStructGMRESGetResidual (
    HYPRE_SStructSolver solver,
    void ** residual )
```

**3.5.4.64 HYPRE\_SStructGMRESSetAbsoluteTol()**

```
HYPRE_Int HYPRE_SStructGMRESSetAbsoluteTol (
    HYPRE_SStructSolver solver,
    HYPRE_Real tol )
```

**3.5.4.65 HYPRE\_SStructGMRESSetKDim()**

```
HYPRE_Int HYPRE_SStructGMRESSetKDim (
    HYPRE_SStructSolver solver,
    HYPRE_Int k_dim )
```

**3.5.4.66 HYPRE\_SStructGMRESSetLogging()**

```
HYPRE_Int HYPRE_SStructGMRESSetLogging (
    HYPRE_SStructSolver solver,
    HYPRE_Int logging )
```

**3.5.4.67 HYPRE\_SStructGMRESSetMaxIter()**

```
HYPRE_Int HYPRE_SStructGMRESSetMaxIter (
    HYPRE_SStructSolver solver,
    HYPRE_Int max_iter )
```

**3.5.4.68 HYPRE\_SStructGMRESSetMinIter()**

```
HYPRE_Int HYPRE_SStructGMRESSetMinIter (
    HYPRE_SStructSolver solver,
    HYPRE_Int min_iter )
```

**3.5.4.69 HYPRE\_SStructGMRESSetPrecond()**

```
HYPRE_Int HYPRE_SStructGMRESSetPrecond (
    HYPRE_SStructSolver solver,
    HYPRE_PtrToSStructSolverFcn precondition,
    HYPRE_PtrToSStructSolverFcn precondition_setup,
    void * precondition_solver )
```

**3.5.4.70 HYPRE\_SStructGMRESSetPrintLevel()**

```
HYPRE_Int HYPRE_SStructGMRESSetPrintLevel (
    HYPRE_SStructSolver solver,
    HYPRE_Int print_level )
```

**3.5.4.71 HYPRE\_SStructGMRESSetStopCrit()**

```
HYPRE_Int HYPRE_SStructGMRESSetStopCrit (
    HYPRE_SStructSolver solver,
    HYPRE_Int stop_crit )
```

**3.5.4.72 HYPRE\_SStructGMRESSetTol()**

```
HYPRE_Int HYPRE_SStructGMRESSetTol (
    HYPRE_SStructSolver solver,
    HYPRE_Real tol )
```

**3.5.4.73 HYPRE\_SStructGMRESSetup()**

```
HYPRE_Int HYPRE_SStructGMRESSetup (
    HYPRE_SStructSolver solver,
    HYPRE_SStructMatrix A,
    HYPRE_SStructVector b,
    HYPRE_SStructVector x )
```

**3.5.4.74 HYPRE\_SStructGMRESSolve()**

```
HYPRE_Int HYPRE_SStructGMRESSolve (
    HYPRE_SStructSolver solver,
    HYPRE_SStructMatrix A,
    HYPRE_SStructVector b,
    HYPRE_SStructVector x )
```

**3.5.4.75 HYPRE\_SStructLGMRESCreate()**

```
HYPRE_Int HYPRE_SStructLGMRESCreate (
    MPI_Comm comm,
    HYPRE_SStructSolver * solver )
```

Create a solver object.

**3.5.4.76 HYPRE\_SStructLGMRESDestroy()**

```
HYPRE_Int HYPRE_SStructLGMRESDestroy (
    HYPRE_SStructSolver solver )
```

Destroy a solver object. An object should be explicitly destroyed using this destructor when the user's code no longer needs direct access to it. Once destroyed, the object must not be referenced again. Note that the object may not be deallocated at the completion of this call, since there may be internal package references to the object. The object will then be destroyed when all internal reference counts go to zero.

**3.5.4.77 HYPRE\_SStructLGMRESGetFinalRelativeResidualNorm()**

```
HYPRE_Int HYPRE_SStructLGMRESGetFinalRelativeResidualNorm (
    HYPRE_SStructSolver solver,
    HYPRE_Real * norm )
```

**3.5.4.78 HYPRE\_SStructLGMRESGetNumIterations()**

```
HYPRE_Int HYPRE_SStructLGMRESGetNumIterations (
    HYPRE_SStructSolver solver,
    HYPRE_Int * num_iterations )
```

**3.5.4.79 HYPRE\_SStructLGMRESGetResidual()**

```
HYPRE_Int HYPRE_SStructLGMRESGetResidual (
    HYPRE_SStructSolver solver,
    void ** residual )
```

**3.5.4.80 HYPRE\_SStructLGMRESSetAbsoluteTol()**

```
HYPRE_Int HYPRE_SStructLGMRESSetAbsoluteTol (
    HYPRE_SStructSolver solver,
    HYPRE_Real tol )
```

**3.5.4.81 HYPRE\_SStructLGMRESSetAugDim()**

```
HYPRE_Int HYPRE_SStructLGMRESSetAugDim (
    HYPRE_SStructSolver solver,
    HYPRE_Int aug_dim )
```

**3.5.4.82 HYPRE\_SStructLGMRESSetKDim()**

```
HYPRE_Int HYPRE_SStructLGMRESSetKDim (
    HYPRE_SStructSolver solver,
    HYPRE_Int k_dim )
```

**3.5.4.83 HYPRE\_SStructLGMRESSetLogging()**

```
HYPRE_Int HYPRE_SStructLGMRESSetLogging (
    HYPRE_SStructSolver solver,
    HYPRE_Int logging )
```

**3.5.4.84 HYPRE\_SStructLGMRESSetMaxIter()**

```
HYPRE_Int HYPRE_SStructLGMRESSetMaxIter (
    HYPRE_SStructSolver solver,
    HYPRE_Int max_iter )
```

**3.5.4.85 HYPRE\_SStructLGMRESSetMinIter()**

```
HYPRE_Int HYPRE_SStructLGMRESSetMinIter (
    HYPRE_SStructSolver solver,
    HYPRE_Int min_iter )
```

**3.5.4.86 HYPRE\_SStructLGMRESSetPrecond()**

```
HYPRE_Int HYPRE_SStructLGMRESSetPrecond (
    HYPRE_SStructSolver solver,
    HYPRE_PtrToSStructSolverFcn precond,
    HYPRE_PtrToSStructSolverFcn precond_setup,
    void * precond_solver )
```

**3.5.4.87 HYPRE\_SStructLGMRESSetPrintLevel()**

```
HYPRE_Int HYPRE_SStructLGMRESSetPrintLevel (
    HYPRE_SStructSolver solver,
    HYPRE_Int print_level )
```

**3.5.4.88 HYPRE\_SStructLGMRESSTol()**

```
HYPRE_Int HYPRE_SStructLGMRESSTol (
    HYPRE_SStructSolver solver,
    HYPRE_Real tol )
```

**3.5.4.89 HYPRE\_SStructLGMRESSTolSetup()**

```
HYPRE_Int HYPRE_SStructLGMRESSTolSetup (
    HYPRE_SStructSolver solver,
    HYPRE_SStructMatrix A,
    HYPRE_SStructVector b,
    HYPRE_SStructVector x )
```

**3.5.4.90 HYPRE\_SStructLGMRESSolve()**

```
HYPRE_Int HYPRE_SStructLGMRESSolve (
    HYPRE_SStructSolver solver,
    HYPRE_SStructMatrix A,
    HYPRE_SStructVector b,
    HYPRE_SStructVector x )
```

**3.5.4.91 HYPRE\_SStructMaxwellCreate()**

```
HYPRE_Int HYPRE_SStructMaxwellCreate (
    MPI_Comm comm,
    HYPRE_SStructSolver * solver )
```

Create a solver object.

**3.5.4.92 HYPRE\_SStructMaxwellDestroy()**

```
HYPRE_Int HYPRE_SStructMaxwellDestroy (
    HYPRE_SStructSolver solver )
```

Destroy a solver object. An object should be explicitly destroyed using this destructor when the user's code no longer needs direct access to it. Once destroyed, the object must not be referenced again. Note that the object may not be deallocated at the completion of this call, since there may be internal package references to the object. The object will then be destroyed when all internal reference counts go to zero.

**3.5.4.93 HYPRE\_SStructMaxwellEliminateRowsCols()**

```
HYPRE_Int HYPRE_SStructMaxwellEliminateRowsCols (
    HYPRE_ParCSRMatrix para,
    HYPRE_Int nrows,
    HYPRE_Int * rows )
```

Eliminates the rows and cols corresponding to the physical boundary in a parcsr matrix.

**3.5.4.94 HYPRE\_SStructMaxwellGetFinalRelativeResidualNorm()**

```
HYPRE_Int HYPRE_SStructMaxwellGetFinalRelativeResidualNorm (
    HYPRE_SStructSolver solver,
    HYPRE_Real * norm )
```

Return the norm of the final relative residual.

**3.5.4.95 HYPRE\_SStructMaxwellGetNumIterations()**

```
HYPRE_Int HYPRE_SStructMaxwellGetNumIterations (
    HYPRE_SStructSolver solver,
    HYPRE_Int * num_iterations )
```

Return the number of iterations taken.

**3.5.4.96 HYPRE\_SStructMaxwellGrad()**

```
HYPRE_Int HYPRE_SStructMaxwellGrad (
    HYPRE_SStructGrid grid,
    HYPRE_ParCSRMatrix * T )
```

(Optional) Creates a gradient matrix from the grid. This presupposes a particular orientation of the edge elements.

**3.5.4.97 HYPRE\_SStructMaxwellPhysBdy()**

```
HYPRE_Int HYPRE_SStructMaxwellPhysBdy (
    HYPRE_SStructGrid * grid_l,
    HYPRE_Int num_levels,
    HYPRE_Int rfactors[HYPRE_MAXDIM],
    HYPRE_Int *** BdryRanks_ptr,
    HYPRE_Int ** BdryRanksCnt_ptr )
```

Finds the physical boundary row ranks on all levels.

**3.5.4.98 HYPRE\_SStructMaxwellSetGrad()**

```
HYPRE_Int HYPRE_SStructMaxwellSetGrad (
    HYPRE_SStructSolver solver,
    HYPRE_ParCSRMatrix T )
```

Sets the gradient operator in the Maxwell solver.

**3.5.4.99 HYPRE\_SStructMaxwellSetLogging()**

```
HYPRE_Int HYPRE_SStructMaxwellSetLogging (
    HYPRE_SStructSolver solver,
    HYPRE_Int logging )
```

(Optional) Set the amount of logging to do.

**3.5.4.100 HYPRE\_SStructMaxwellSetMaxIter()**

```
HYPRE_Int HYPRE_SStructMaxwellSetMaxIter (
    HYPRE_SStructSolver solver,
    HYPRE_Int max_iter )
```

(Optional) Set maximum number of iterations.

**3.5.4.101 HYPRE\_SStructMaxwellSetNumPostRelax()**

```
HYPRE_Int HYPRE_SStructMaxwellSetNumPostRelax (
    HYPRE_SStructSolver solver,
    HYPRE_Int num_post_relax )
```

(Optional) Set number of relaxation sweeps after coarse-grid correction.

**3.5.4.102 HYPRE\_SStructMaxwellSetNumPreRelax()**

```
HYPRE_Int HYPRE_SStructMaxwellSetNumPreRelax (
    HYPRE_SStructSolver solver,
    HYPRE_Int num_pre_relax )
```

(Optional) Set number of relaxation sweeps before coarse-grid correction.

**3.5.4.103 HYPRE\_SStructMaxwellSetRelChange()**

```
HYPRE_Int HYPRE_SStructMaxwellSetRelChange (
    HYPRE_SStructSolver solver,
    HYPRE_Int rel_change )
```

(Optional) Additionally require that the relative difference in successive iterates be small.

**3.5.4.104 HYPRE\_SStructMaxwellSetRfactors()**

```
HYPRE_Int HYPRE_SStructMaxwellSetRfactors (
    HYPRE_SStructSolver solver,
    HYPRE_Int rfactors[HYPRE_MAXDIM] )
```

Sets the coarsening factor.

**3.5.4.105 HYPRE\_SStructMaxwellSetSetConstantCoef()**

```
HYPRE_Int HYPRE_SStructMaxwellSetSetConstantCoef (
    HYPRE_SStructSolver solver,
    HYPRE_Int flag )
```

(Optional) Set the constant coefficient flag- Nedelec interpolation used.



**3.5.4.106 HYPRE\_SStructMaxwellSetTol()**

```
HYPRE_Int HYPRE_SStructMaxwellSetTol (
    HYPRE_SStructSolver solver,
    HYPRE_Real tol )
```

(Optional) Set the convergence tolerance.

**3.5.4.107 HYPRE\_SStructMaxwellSetup()**

```
HYPRE_Int HYPRE_SStructMaxwellSetup (
    HYPRE_SStructSolver solver,
    HYPRE_SStructMatrix A,
    HYPRE_SStructVector b,
    HYPRE_SStructVector x )
```

Prepare to solve the system. The coefficient data in *b* and *x* is ignored here, but information about the layout of the data may be used.

**3.5.4.108 HYPRE\_SStructMaxwellSolve()**

```
HYPRE_Int HYPRE_SStructMaxwellSolve (
    HYPRE_SStructSolver solver,
    HYPRE_SStructMatrix A,
    HYPRE_SStructVector b,
    HYPRE_SStructVector x )
```

Solve the system. Full coupling of the augmented system used throughout the multigrid hierarchy.

**3.5.4.109 HYPRE\_SStructMaxwellSolve2()**

```
HYPRE_Int HYPRE_SStructMaxwellSolve2 (
    HYPRE_SStructSolver solver,
    HYPRE_SStructMatrix A,
    HYPRE_SStructVector b,
    HYPRE_SStructVector x )
```

Solve the system. Full coupling of the augmented system used only on the finest level, i.e., the node and edge multigrid cycles are coupled only on the finest level.

**3.5.4.110 HYPRE\_SStructMaxwellZeroVector()**

```
HYPRE_Int HYPRE_SStructMaxwellZeroVector (
    HYPRE_ParVector b,
    HYPRE_Int * rows,
    HYPRE_Int nrows )
```

Zeros the rows corresponding to the physical boundary in a par vector.

**3.5.4.111 HYPRE\_SStructPCGCreate()**

```
HYPRE_Int HYPRE_SStructPCGCreate (
    MPI_Comm comm,
    HYPRE_SStructSolver * solver )
```

Create a solver object.

**3.5.4.112 HYPRE\_SStructPCGDestroy()**

```
HYPRE_Int HYPRE_SStructPCGDestroy (
    HYPRE_SStructSolver solver )
```

Destroy a solver object. An object should be explicitly destroyed using this destructor when the user's code no longer needs direct access to it. Once destroyed, the object must not be referenced again. Note that the object may not be deallocated at the completion of this call, since there may be internal package references to the object. The object will then be destroyed when all internal reference counts go to zero.

**3.5.4.113 HYPRE\_SStructPCGGetFinalRelativeResidualNorm()**

```
HYPRE_Int HYPRE_SStructPCGGetFinalRelativeResidualNorm (
    HYPRE_SStructSolver solver,
    HYPRE_Real * norm )
```

**3.5.4.114 HYPRE\_SStructPCGGetNumIterations()**

```
HYPRE_Int HYPRE_SStructPCGGetNumIterations (
    HYPRE_SStructSolver solver,
    HYPRE_Int * num_iterations )
```

**3.5.4.115 HYPRE\_SStructPCGGetResidual()**

```
HYPRE_Int HYPRE_SStructPCGGetResidual (
    HYPRE_SStructSolver solver,
    void ** residual )
```

**3.5.4.116 HYPRE\_SStructPCGSetAbsoluteTol()**

```
HYPRE_Int HYPRE_SStructPCGSetAbsoluteTol (
    HYPRE_SStructSolver solver,
    HYPRE_Real tol )
```

**3.5.4.117 HYPRE\_SStructPCGSetLogging()**

```
HYPRE_Int HYPRE_SStructPCGSetLogging (
    HYPRE_SStructSolver solver,
    HYPRE_Int logging )
```

**3.5.4.118 HYPRE\_SStructPCGSetMaxIter()**

```
HYPRE_Int HYPRE_SStructPCGSetMaxIter (
    HYPRE_SStructSolver solver,
    HYPRE_Int max_iter )
```

**3.5.4.119 HYPRE\_SStructPCGSetPrecond()**

```
HYPRE_Int HYPRE_SStructPCGSetPrecond (
    HYPRE_SStructSolver solver,
    HYPRE_PtrToSStructSolverFcn precondition,
    HYPRE_PtrToSStructSolverFcn precondition_setup,
    void * precondition_solver )
```

**3.5.4.120 HYPRE\_SStructPCGSetPrintLevel()**

```
HYPRE_Int HYPRE_SStructPCGSetPrintLevel (
    HYPRE_SStructSolver solver,
    HYPRE_Int level )
```

**3.5.4.121 HYPRE\_SStructPCGSetRelChange()**

```
HYPRE_Int HYPRE_SStructPCGSetRelChange (
    HYPRE_SStructSolver solver,
    HYPRE_Int rel_change )
```

**3.5.4.122 HYPRE\_SStructPCGSetTol()**

```
HYPRE_Int HYPRE_SStructPCGSetTol (
    HYPRE_SStructSolver solver,
    HYPRE_Real tol )
```

**3.5.4.123 HYPRE\_SStructPCGSetTwoNorm()**

```
HYPRE_Int HYPRE_SStructPCGSetTwoNorm (
    HYPRE_SStructSolver solver,
    HYPRE_Int two_norm )
```

**3.5.4.124 HYPRE\_SStructPCGSetup()**

```
HYPRE_Int HYPRE_SStructPCGSetup (
    HYPRE_SStructSolver solver,
    HYPRE_SStructMatrix A,
    HYPRE_SStructVector b,
    HYPRE_SStructVector x )
```

**3.5.4.125 HYPRE\_SStructPCGSolve()**

```
HYPRE_Int HYPRE_SStructPCGSolve (
    HYPRE_SStructSolver solver,
    HYPRE_SStructMatrix A,
    HYPRE_SStructVector b,
    HYPRE_SStructVector x )
```

**3.5.4.126 HYPRE\_SStructSetupInterpreter()**

```
HYPRE_Int HYPRE_SStructSetupInterpreter (
    mv_InterfaceInterpreter * i )
```

Load interface interpreter. Vector part loaded with hypre\_SStructKrylov functions and multivector part loaded with mv\_TempMultiVector functions.

**3.5.4.127 HYPRE\_SStructSetupMatvec()**

```
HYPRE_Int HYPRE_SStructSetupMatvec (
    HYPRE_MatvecFunctions * mv )
```

Load Matvec interpreter with hypre\_SStructKrylov functions.

**3.5.4.128 HYPRE\_SStructSplitCreate()**

```
HYPRE_Int HYPRE_SStructSplitCreate (
    MPI_Comm comm,
    HYPRE_SStructSolver * solver )
```

Create a solver object.

**3.5.4.129 HYPRE\_SStructSplitDestroy()**

```
HYPRE_Int HYPRE_SStructSplitDestroy (
    HYPRE_SStructSolver solver )
```

Destroy a solver object. An object should be explicitly destroyed using this destructor when the user's code no longer needs direct access to it. Once destroyed, the object must not be referenced again. Note that the object may not be deallocated at the completion of this call, since there may be internal package references to the object. The object will then be destroyed when all internal reference counts go to zero.

**3.5.4.130 HYPRE\_SStructSplitGetFinalRelativeResidualNorm()**

```
HYPRE_Int HYPRE_SStructSplitGetFinalRelativeResidualNorm (
    HYPRE_SStructSolver solver,
    HYPRE_Real * norm )
```

Return the norm of the final relative residual.

**3.5.4.131 HYPRE\_SStructSplitGetNumIterations()**

```
HYPRE_Int HYPRE_SStructSplitGetNumIterations (
    HYPRE_SStructSolver solver,
    HYPRE_Int * num_iterations )
```

Return the number of iterations taken.

**3.5.4.132 HYPRE\_SStructSplitSetMaxIter()**

```
HYPRE_Int HYPRE_SStructSplitSetMaxIter (
    HYPRE_SStructSolver solver,
    HYPRE_Int max_iter )
```

(Optional) Set maximum number of iterations.

**3.5.4.133 HYPRE\_SStructSplitSetNonZeroGuess()**

```
HYPRE_Int HYPRE_SStructSplitSetNonZeroGuess (
    HYPRE_SStructSolver solver )
```

(Optional) Use a nonzero initial guess. This is the default behavior, but this routine allows the user to switch back after using *SetZeroGuess*.

**3.5.4.134 HYPRE\_SStructSplitSetStructSolver()**

```
HYPRE_Int HYPRE_SStructSplitSetStructSolver (
    HYPRE_SStructSolver solver,
    HYPRE_Int ssolver )
```

(Optional) Set up the type of diagonal struct solver. Either *ssolver* is set to *HYPRE\_SMG* or *HYPRE\_PFMG*.

**3.5.4.135 HYPRE\_SStructSplitSetTol()**

```
HYPRE_Int HYPRE_SStructSplitSetTol (
    HYPRE_SStructSolver solver,
    HYPRE_Real tol )
```

(Optional) Set the convergence tolerance.

**3.5.4.136 HYPRE\_SStructSplitSetup()**

```
HYPRE_Int HYPRE_SStructSplitSetup (
    HYPRE_SStructSolver solver,
    HYPRE_SStructMatrix A,
    HYPRE_SStructVector b,
    HYPRE_SStructVector x )
```

Prepare to solve the system. The coefficient data in *b* and *x* is ignored here, but information about the layout of the data may be used.

**3.5.4.137 HYPRE\_SStructSplitSetZeroGuess()**

```
HYPRE_Int HYPRE_SStructSplitSetZeroGuess (
    HYPRE_SStructSolver solver )
```

(Optional) Use a zero initial guess. This allows the solver to cut corners in the case where a zero initial guess is needed (e.g., for preconditioning) to reduce computational cost.

**3.5.4.138 HYPRE\_SStructSplitSolve()**

```
HYPRE_Int HYPRE_SStructSplitSolve (
    HYPRE_SStructSolver solver,
    HYPRE_SStructMatrix A,
    HYPRE_SStructVector b,
    HYPRE_SStructVector x )
```

Solve the system.

**3.5.4.139 HYPRE\_SStructSysPFMGCreate()**

```
HYPRE_Int HYPRE_SStructSysPFMGCreate (
    MPI_Comm comm,
    HYPRE_SStructSolver * solver )
```

Create a solver object.

**3.5.4.140 HYPRE\_SStructSysPFMGDestroy()**

```
HYPRE_Int HYPRE_SStructSysPFMGDestroy (
    HYPRE_SStructSolver solver )
```

Destroy a solver object. An object should be explicitly destroyed using this destructor when the user's code no longer needs direct access to it. Once destroyed, the object must not be referenced again. Note that the object may not be deallocated at the completion of this call, since there may be internal package references to the object. The object will then be destroyed when all internal reference counts go to zero.

**3.5.4.141 HYPRE\_SStructSysPFMGGetFinalRelativeResidualNorm()**

```
HYPRE_Int HYPRE_SStructSysPFMGGetFinalRelativeResidualNorm (
    HYPRE_SStructSolver solver,
    HYPRE_Real * norm )
```

Return the norm of the final relative residual.

**3.5.4.142 HYPRE\_SStructSysPFMGGetNumIterations()**

```
HYPRE_Int HYPRE_SStructSysPFMGGetNumIterations (
    HYPRE_SStructSolver solver,
    HYPRE_Int * num_iterations )
```

Return the number of iterations taken.

**3.5.4.143 HYPRE\_SStructSysPFMGSetDxyz()**

```
HYPRE_Int HYPRE_SStructSysPFMGSetDxyz (
    HYPRE_SStructSolver solver,
    HYPRE_Real * dxyz )
```

**3.5.4.144 HYPRE\_SStructSysPFMGSetJacobiWeight()**

```
HYPRE_Int HYPRE_SStructSysPFMGSetJacobiWeight (
    HYPRE_SStructSolver solver,
    HYPRE_Real weight )
```

(Optional) Set Jacobi Weight.

**3.5.4.145 HYPRE\_SStructSysPFMGSetLogging()**

```
HYPRE_Int HYPRE_SStructSysPFMGSetLogging (
    HYPRE_SStructSolver solver,
    HYPRE_Int logging )
```

(Optional) Set the amount of logging to do.

**3.5.4.146 HYPRE\_SStructSysPFMGSetMaxIter()**

```
HYPRE_Int HYPRE_SStructSysPFMGSetMaxIter (
    HYPRE_SStructSolver solver,
    HYPRE_Int max_iter )
```

(Optional) Set maximum number of iterations.

**3.5.4.147 HYPRE\_SStructSysPFMGSetNonZeroGuess()**

```
HYPRE_Int HYPRE_SStructSysPFMGSetNonZeroGuess (
    HYPRE_SStructSolver solver )
```

(Optional) Use a nonzero initial guess. This is the default behavior, but this routine allows the user to switch back after using *SetZeroGuess*.

**3.5.4.148 HYPRE\_SStructSysPFMGSetNumPostRelax()**

```
HYPRE_Int HYPRE_SStructSysPFMGSetNumPostRelax (
    HYPRE_SStructSolver solver,
    HYPRE_Int num_post_relax )
```

(Optional) Set number of relaxation sweeps after coarse-grid correction.

**3.5.4.149 HYPRE\_SStructSysPFMGSetNumPreRelax()**

```
HYPRE_Int HYPRE_SStructSysPFMGSetNumPreRelax (
    HYPRE_SStructSolver solver,
    HYPRE_Int num_pre_relax )
```

(Optional) Set number of relaxation sweeps before coarse-grid correction.

**3.5.4.150 HYPRE\_SStructSysPFMGSetPrintLevel()**

```
HYPRE_Int HYPRE_SStructSysPFMGSetPrintLevel (
    HYPRE_SStructSolver solver,
    HYPRE_Int print_level )
```

(Optional) Set the amount of printing to do to the screen.

**3.5.4.151 HYPRE\_SStructSysPFMGSetRelaxType()**

```
HYPRE_Int HYPRE_SStructSysPFMGSetRelaxType (
    HYPRE_SStructSolver solver,
    HYPRE_Int relax_type )
```

(Optional) Set relaxation type.

Current relaxation methods set by *relax\_type* are:

- 0 : Jacobi
- 1 : Weighted Jacobi (default)
- 2 : Red/Black Gauss-Seidel (symmetric: RB pre-relaxation, BR post-relaxation)

**3.5.4.152 HYPRE\_SStructSysPFMGSetRelChange()**

```
HYPRE_Int HYPRE_SStructSysPFMGSetRelChange (
    HYPRE_SStructSolver solver,
    HYPRE_Int rel_change )
```

(Optional) Additionally require that the relative difference in successive iterates be small.

**3.5.4.153 HYPRE\_SStructSysPFMGSetSkipRelax()**

```
HYPRE_Int HYPRE_SStructSysPFMGSetSkipRelax (
    HYPRE_SStructSolver solver,
    HYPRE_Int skip_relax )
```

(Optional) Skip relaxation on certain grids for isotropic problems. This can greatly improve efficiency by eliminating unnecessary relaxations when the underlying problem is isotropic.



**3.5.4.154 HYPRE\_SStructSysPFMGSetTol()**

```
HYPRE_Int HYPRE_SStructSysPFMGSetTol (
    HYPRE_SStructSolver solver,
    HYPRE_Real tol )
```

(Optional) Set the convergence tolerance.

**3.5.4.155 HYPRE\_SStructSysPFMGSetup()**

```
HYPRE_Int HYPRE_SStructSysPFMGSetup (
    HYPRE_SStructSolver solver,
    HYPRE_SStructMatrix A,
    HYPRE_SStructVector b,
    HYPRE_SStructVector x )
```

Prepare to solve the system. The coefficient data in *b* and *x* is ignored here, but information about the layout of the data may be used.

**3.5.4.156 HYPRE\_SStructSysPFMGSetZeroGuess()**

```
HYPRE_Int HYPRE_SStructSysPFMGSetZeroGuess (
    HYPRE_SStructSolver solver )
```

(Optional) Use a zero initial guess. This allows the solver to cut corners in the case where a zero initial guess is needed (e.g., for preconditioning) to reduce computational cost.

**3.5.4.157 HYPRE\_SStructSysPFMGsolve()**

```
HYPRE_Int HYPRE_SStructSysPFMGsolve (
    HYPRE_SStructSolver solver,
    HYPRE_SStructMatrix A,
    HYPRE_SStructVector b,
    HYPRE_SStructVector x )
```

Solve the system.

**3.6 ParCSR Solvers****Functions**

- HYPRE\_Int [HYPRE\\_SchwarzCreate](#) (HYPRE\_Solver \*solver)
- HYPRE\_Int [HYPRE\\_SchwarzDestroy](#) (HYPRE\_Solver solver)
- HYPRE\_Int [HYPRE\\_SchwarzSetup](#) (HYPRE\_Solver solver, HYPRE\_ParCSRMatrix A, HYPRE\_ParVector b, HYPRE\_ParVector x)
- HYPRE\_Int [HYPRE\\_SchwarzSolve](#) (HYPRE\_Solver solver, HYPRE\_ParCSRMatrix A, HYPRE\_ParVector b, HYPRE\_ParVector x)
- HYPRE\_Int [HYPRE\\_SchwarzSetVariant](#) (HYPRE\_Solver solver, HYPRE\_Int variant)
- HYPRE\_Int [HYPRE\\_SchwarzSetOverlap](#) (HYPRE\_Solver solver, HYPRE\_Int overlap)
- HYPRE\_Int [HYPRE\\_SchwarzSetDomainType](#) (HYPRE\_Solver solver, HYPRE\_Int domain\_type)

- HYPRE\_Int [HYPRE\\_SchwarzSetRelaxWeight](#) (HYPRE\_Solver solver, HYPRE\_Real relax\_weight)
- HYPRE\_Int [HYPRE\\_SchwarzSetDomainStructure](#) (HYPRE\_Solver solver, HYPRE\_CSRMatrix domain\_↵ structure)
- HYPRE\_Int [HYPRE\\_SchwarzSetNumFunctions](#) (HYPRE\_Solver solver, HYPRE\_Int num\_functions)
- HYPRE\_Int [HYPRE\\_SchwarzSetDofFunc](#) (HYPRE\_Solver solver, HYPRE\_Int \*dof\_func)
- HYPRE\_Int [HYPRE\\_SchwarzSetNonSymm](#) (HYPRE\_Solver solver, HYPRE\_Int use\_nonsymm)
- HYPRE\_Int [HYPRE\\_ParCSRCreate](#) (MPI\_Comm comm, HYPRE\_Solver \*solver)
- HYPRE\_Int [HYPRE\\_ParCSRDestroy](#) (HYPRE\_Solver solver)
- HYPRE\_Int [HYPRE\\_ParCSRSetup](#) (HYPRE\_Solver solver, HYPRE\_ParCSRMatrix A, HYPRE\_Par↵ Vector b, HYPRE\_ParVector x)
- HYPRE\_Int [HYPRE\\_ParCSRSolve](#) (HYPRE\_Solver solver, HYPRE\_ParCSRMatrix A, HYPRE\_Par↵ Vector b, HYPRE\_ParVector x)
- HYPRE\_Int [HYPRE\\_ParCSRSetTol](#) (HYPRE\_Solver solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_ParCSRSetMinIter](#) (HYPRE\_Solver solver, HYPRE\_Int min\_iter)
- HYPRE\_Int [HYPRE\\_ParCSRSetMaxIter](#) (HYPRE\_Solver solver, HYPRE\_Int max\_iter)
- HYPRE\_Int [HYPRE\\_ParCSRSetStopCrit](#) (HYPRE\_Solver solver, HYPRE\_Int stop\_crit)
- HYPRE\_Int [HYPRE\\_ParCSRSetPrecond](#) (HYPRE\_Solver solver, HYPRE\_PtrToParSolverFcn pre↵ cond, HYPRE\_PtrToParSolverFcn preconditionT, HYPRE\_PtrToParSolverFcn precondition\_setup, HYPRE\_Solver precondition\_solver)
- HYPRE\_Int [HYPRE\\_ParCSRGetPrecond](#) (HYPRE\_Solver solver, HYPRE\_Solver \*precond\_data)
- HYPRE\_Int [HYPRE\\_ParCSRSetLogging](#) (HYPRE\_Solver solver, HYPRE\_Int logging)
- HYPRE\_Int [HYPRE\\_ParCSRGetNumIterations](#) (HYPRE\_Solver solver, HYPRE\_Int \*num\_iterations)
- HYPRE\_Int [HYPRE\\_ParCSRGetFinalRelativeResidualNorm](#) (HYPRE\_Solver solver, HYPRE\_Real \*norm)

## ParCSR Solvers

- typedef struct hypre\_Solver\_struct \* [HYPRE\\_Solver](#)
- typedef HYPRE\_Int(\* [HYPRE\\_PtrToParSolverFcn](#)) (HYPRE\_Solver, HYPRE\_ParCSRMatrix, HYPRE\_Par↵ Vector, HYPRE\_ParVector)
- typedef HYPRE\_Int(\* [HYPRE\\_PtrToModifyPCFcn](#)) (HYPRE\_Solver, HYPRE\_Int, HYPRE\_Real)
- #define [HYPRE\\_SOLVER\\_STRUCT](#)
- #define [HYPRE\\_MODIFYPC](#)

## ParCSR BoomerAMG Solver and Preconditioner

Parallel unstructured algebraic multigrid solver and preconditioner

- HYPRE\_Int [HYPRE\\_BoomerAMGCreate](#) (HYPRE\_Solver \*solver)
- HYPRE\_Int [HYPRE\\_BoomerAMGDestroy](#) (HYPRE\_Solver solver)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetup](#) (HYPRE\_Solver solver, HYPRE\_ParCSRMatrix A, HYPRE\_Par↵ Vector b, HYPRE\_ParVector x)
- HYPRE\_Int [HYPRE\\_BoomerAMGSolve](#) (HYPRE\_Solver solver, HYPRE\_ParCSRMatrix A, HYPRE\_Par↵ Vector b, HYPRE\_ParVector x)
- HYPRE\_Int [HYPRE\\_BoomerAMGSolveT](#) (HYPRE\_Solver solver, HYPRE\_ParCSRMatrix A, HYPRE\_Par↵ Vector b, HYPRE\_ParVector x)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetOldDefault](#) (HYPRE\_Solver solver)
- HYPRE\_Int [HYPRE\\_BoomerAMGGetResidual](#) (HYPRE\_Solver solver, HYPRE\_ParVector \*residual)
- HYPRE\_Int [HYPRE\\_BoomerAMGGetNumIterations](#) (HYPRE\_Solver solver, HYPRE\_Int \*num\_iterations)
- HYPRE\_Int [HYPRE\\_BoomerAMGGetFinalRelativeResidualNorm](#) (HYPRE\_Solver solver, HYPRE\_Real \*rel\_resid\_norm)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetNumFunctions](#) (HYPRE\_Solver solver, HYPRE\_Int num\_functions)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetDofFunc](#) (HYPRE\_Solver solver, HYPRE\_Int \*dof\_func)

- HYPRE\_Int [HYPRE\\_BoomerAMGSetConvergeType](#) (HYPRE\_Solver solver, HYPRE\_Int type)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetTol](#) (HYPRE\_Solver solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetMaxIter](#) (HYPRE\_Solver solver, HYPRE\_Int max\_iter)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetMinIter](#) (HYPRE\_Solver solver, HYPRE\_Int min\_iter)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetMaxCoarseSize](#) (HYPRE\_Solver solver, HYPRE\_Int max\_coarse\_size)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetMinCoarseSize](#) (HYPRE\_Solver solver, HYPRE\_Int min\_coarse\_size)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetMaxLevels](#) (HYPRE\_Solver solver, HYPRE\_Int max\_levels)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetCoarsenCutFactor](#) (HYPRE\_Solver solver, HYPRE\_Int coarsen\_cut\_factor)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetStrongThreshold](#) (HYPRE\_Solver solver, HYPRE\_Real strong\_threshold)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetStrongThresholdR](#) (HYPRE\_Solver solver, HYPRE\_Real strong\_threshold)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetFilterThresholdR](#) (HYPRE\_Solver solver, HYPRE\_Real filter\_threshold)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetSCommPkgSwitch](#) (HYPRE\_Solver solver, HYPRE\_Real Scommpkg\_switch)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetMaxRowSum](#) (HYPRE\_Solver solver, HYPRE\_Real max\_row\_sum)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetCoarsenType](#) (HYPRE\_Solver solver, HYPRE\_Int coarsen\_type)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetNonGalerkinTol](#) (HYPRE\_Solver solver, HYPRE\_Real nongalerkin\_tol)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetLevelNonGalerkinTol](#) (HYPRE\_Solver solver, HYPRE\_Real nongalerkin\_tol, HYPRE\_Int level)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetNonGalerkTol](#) (HYPRE\_Solver solver, HYPRE\_Int nongalerk\_num\_tol, HYPRE\_Real \*nongalerk\_tol)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetMeasureType](#) (HYPRE\_Solver solver, HYPRE\_Int measure\_type)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetAggNumLevels](#) (HYPRE\_Solver solver, HYPRE\_Int agg\_num\_levels)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetNumPaths](#) (HYPRE\_Solver solver, HYPRE\_Int num\_paths)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetCGCIts](#) (HYPRE\_Solver solver, HYPRE\_Int its)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetNodal](#) (HYPRE\_Solver solver, HYPRE\_Int nodal)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetNodalDiag](#) (HYPRE\_Solver solver, HYPRE\_Int nodal\_diag)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetKeepSameSign](#) (HYPRE\_Solver solver, HYPRE\_Int keep\_same\_sign)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetInterpType](#) (HYPRE\_Solver solver, HYPRE\_Int interp\_type)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetTruncFactor](#) (HYPRE\_Solver solver, HYPRE\_Real trunc\_factor)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetPMaxElmts](#) (HYPRE\_Solver solver, HYPRE\_Int P\_max\_elmts)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetSepWeight](#) (HYPRE\_Solver solver, HYPRE\_Int sep\_weight)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetAggInterpType](#) (HYPRE\_Solver solver, HYPRE\_Int agg\_interp\_type)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetAggTruncFactor](#) (HYPRE\_Solver solver, HYPRE\_Real agg\_trunc\_factor)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetAggP12TruncFactor](#) (HYPRE\_Solver solver, HYPRE\_Real agg\_P12\_trunc\_factor)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetAggPMaxElmts](#) (HYPRE\_Solver solver, HYPRE\_Int agg\_P\_max\_elmts)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetAggP12MaxElmts](#) (HYPRE\_Solver solver, HYPRE\_Int agg\_P12\_max\_elmts)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetInterpVectors](#) (HYPRE\_Solver solver, HYPRE\_Int num\_vectors, HYPRE\_ParVector \*interp\_vectors)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetInterpVecVariant](#) (HYPRE\_Solver solver, HYPRE\_Int var)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetInterpVecQMax](#) (HYPRE\_Solver solver, HYPRE\_Int q\_max)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetInterpVecAbsQTrunc](#) (HYPRE\_Solver solver, HYPRE\_Real q\_trunc)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetGSMG](#) (HYPRE\_Solver solver, HYPRE\_Int gsmg)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetNumSamples](#) (HYPRE\_Solver solver, HYPRE\_Int num\_samples)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetCycleType](#) (HYPRE\_Solver solver, HYPRE\_Int cycle\_type)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetFCycle](#) (HYPRE\_Solver solver, HYPRE\_Int fcycle)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetAdditive](#) (HYPRE\_Solver solver, HYPRE\_Int addlvl)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetMultAdditive](#) (HYPRE\_Solver solver, HYPRE\_Int addlvl)

- HYPRE\_Int [HYPRE\\_BoomerAMGSetSimple](#) (HYPRE\_Solver solver, HYPRE\_Int addlvl)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetAddLastLvl](#) (HYPRE\_Solver solver, HYPRE\_Int add\_last\_lvl)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetMultAddTruncFactor](#) (HYPRE\_Solver solver, HYPRE\_Real add\_↵trunc\_factor)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetMultAddPMaxElmts](#) (HYPRE\_Solver solver, HYPRE\_Int add\_P\_max\_↵elmts)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetAddRelaxType](#) (HYPRE\_Solver solver, HYPRE\_Int add\_rlx\_type)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetAddRelaxWt](#) (HYPRE\_Solver solver, HYPRE\_Real add\_rlx\_wt)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetSeqThreshold](#) (HYPRE\_Solver solver, HYPRE\_Int seq\_threshold)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetRedundant](#) (HYPRE\_Solver solver, HYPRE\_Int redundant)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetNumGridSweeps](#) (HYPRE\_Solver solver, HYPRE\_Int \*num\_grid\_↵sweeps)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetNumSweeps](#) (HYPRE\_Solver solver, HYPRE\_Int num\_sweeps)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetCycleNumSweeps](#) (HYPRE\_Solver solver, HYPRE\_Int num\_sweeps, HYPRE\_Int k)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetGridRelaxType](#) (HYPRE\_Solver solver, HYPRE\_Int \*grid\_relax\_type)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetRelaxType](#) (HYPRE\_Solver solver, HYPRE\_Int relax\_type)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetCycleRelaxType](#) (HYPRE\_Solver solver, HYPRE\_Int relax\_type, HYPRE\_Int k)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetRelaxOrder](#) (HYPRE\_Solver solver, HYPRE\_Int relax\_order)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetGridRelaxPoints](#) (HYPRE\_Solver solver, HYPRE\_Int \*\*grid\_relax\_↵points)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetRelaxWeight](#) (HYPRE\_Solver solver, HYPRE\_Real \*relax\_weight)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetRelaxWt](#) (HYPRE\_Solver solver, HYPRE\_Real relax\_weight)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetLevelRelaxWt](#) (HYPRE\_Solver solver, HYPRE\_Real relax\_weight, HYPRE\_Int level)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetOmega](#) (HYPRE\_Solver solver, HYPRE\_Real \*omega)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetOuterWt](#) (HYPRE\_Solver solver, HYPRE\_Real omega)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetLevelOuterWt](#) (HYPRE\_Solver solver, HYPRE\_Real omega, HYPRE\_↵Int level)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetChebyOrder](#) (HYPRE\_Solver solver, HYPRE\_Int order)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetChebyFraction](#) (HYPRE\_Solver solver, HYPRE\_Real ratio)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetChebyScale](#) (HYPRE\_Solver solver, HYPRE\_Int scale)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetChebyVariant](#) (HYPRE\_Solver solver, HYPRE\_Int variant)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetChebyEigEst](#) (HYPRE\_Solver solver, HYPRE\_Int eig\_est)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetSmoothType](#) (HYPRE\_Solver solver, HYPRE\_Int smooth\_type)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetSmoothNumLevels](#) (HYPRE\_Solver solver, HYPRE\_Int smooth\_num\_↵levels)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetSmoothNumSweeps](#) (HYPRE\_Solver solver, HYPRE\_Int smooth\_↵num\_sweeps)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetVariant](#) (HYPRE\_Solver solver, HYPRE\_Int variant)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetOverlap](#) (HYPRE\_Solver solver, HYPRE\_Int overlap)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetDomainType](#) (HYPRE\_Solver solver, HYPRE\_Int domain\_type)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetSchwarzRlxWeight](#) (HYPRE\_Solver solver, HYPRE\_Real schwarz\_↵rlx\_weight)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetSchwarzUseNonSymm](#) (HYPRE\_Solver solver, HYPRE\_Int use\_↵nonsymm)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetSym](#) (HYPRE\_Solver solver, HYPRE\_Int sym)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetLevel](#) (HYPRE\_Solver solver, HYPRE\_Int level)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetThreshold](#) (HYPRE\_Solver solver, HYPRE\_Real threshold)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetFilter](#) (HYPRE\_Solver solver, HYPRE\_Real filter)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetDropTol](#) (HYPRE\_Solver solver, HYPRE\_Real drop\_tol)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetMaxNzPerRow](#) (HYPRE\_Solver solver, HYPRE\_Int max\_nz\_per\_row)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetEuclidFile](#) (HYPRE\_Solver solver, char \*euclidfile)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetEuLevel](#) (HYPRE\_Solver solver, HYPRE\_Int eu\_level)

- HYPRE\_Int [HYPRE\\_BoomerAMGSetEuSparseA](#) (HYPRE\_Solver solver, HYPRE\_Real eu\_sparse\_A)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetEuBJ](#) (HYPRE\_Solver solver, HYPRE\_Int eu\_bj)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetILUType](#) (HYPRE\_Solver solver, HYPRE\_Int ilu\_type)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetILULevel](#) (HYPRE\_Solver solver, HYPRE\_Int ilu\_lfil)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetILUMaxRowNnz](#) (HYPRE\_Solver solver, HYPRE\_Int ilu\_max\_row\_↵  
nnz)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetILUMaxIter](#) (HYPRE\_Solver solver, HYPRE\_Int ilu\_max\_iter)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetILUDroptol](#) (HYPRE\_Solver solver, HYPRE\_Real ilu\_droptol)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetRestriction](#) (HYPRE\_Solver solver, HYPRE\_Int restr\_par)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetIsTriangular](#) (HYPRE\_Solver solver, HYPRE\_Int is\_triangular)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetGMRESSwitchR](#) (HYPRE\_Solver solver, HYPRE\_Int gmres\_switch)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetADropTol](#) (HYPRE\_Solver solver, HYPRE\_Real A\_drop\_tol)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetADropType](#) (HYPRE\_Solver solver, HYPRE\_Int A\_drop\_type)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetPrintFileName](#) (HYPRE\_Solver solver, const char \*print\_file\_name)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetPrintLevel](#) (HYPRE\_Solver solver, HYPRE\_Int print\_level)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetLogging](#) (HYPRE\_Solver solver, HYPRE\_Int logging)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetDebugFlag](#) (HYPRE\_Solver solver, HYPRE\_Int debug\_flag)
- HYPRE\_Int [HYPRE\\_BoomerAMGInitGridRelaxation](#) (HYPRE\_Int \*\*num\_grid\_sweeps\_ptr, HYPRE\_↵  
Int \*\*grid\_relax\_type\_ptr, HYPRE\_Int \*\*\*grid\_relax\_points\_ptr, HYPRE\_Int coarsen\_type, HYPRE\_Real  
\*\*relax\_weights\_ptr, HYPRE\_Int max\_levels)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetRAP2](#) (HYPRE\_Solver solver, HYPRE\_Int rap2)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetModuleRAP2](#) (HYPRE\_Solver solver, HYPRE\_Int mod\_rap2)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetKeepTranspose](#) (HYPRE\_Solver solver, HYPRE\_Int keepTranspose)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetPlotGrids](#) (HYPRE\_Solver solver, HYPRE\_Int plotgrids)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetPlotFileName](#) (HYPRE\_Solver solver, const char \*plotfilename)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetCoordDim](#) (HYPRE\_Solver solver, HYPRE\_Int coorddim)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetCoordinates](#) (HYPRE\_Solver solver, float \*coordinates)
- HYPRE\_Int [HYPRE\\_BoomerAMGGetGridHierarchy](#) (HYPRE\_Solver solver, HYPRE\_Int \*cgrid)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetCPoints](#) (HYPRE\_Solver solver, HYPRE\_Int cpt\_coarse\_level,  
HYPRE\_Int num\_cpt\_coarse, HYPRE\_BigInt \*cpt\_coarse\_index)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetCpointsToKeep](#) (HYPRE\_Solver solver, HYPRE\_Int cpt\_coarse\_level,  
HYPRE\_Int num\_cpt\_coarse, HYPRE\_BigInt \*cpt\_coarse\_index)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetFPoints](#) (HYPRE\_Solver solver, HYPRE\_Int num\_fpt, HYPRE\_BigInt  
\*fpt\_index)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetIsolatedFPoints](#) (HYPRE\_Solver solver, HYPRE\_Int num\_isolated\_fpt,  
HYPRE\_BigInt \*isolated\_fpt\_index)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetSabs](#) (HYPRE\_Solver solver, HYPRE\_Int Sabs)

### ParCSR BoomerAMGDD Solver and Preconditioner

Communication reducing solver and preconditioner built on top of algebraic multigrid

- HYPRE\_Int [HYPRE\\_BoomerAMGDDCreate](#) (HYPRE\_Solver \*solver)
- HYPRE\_Int [HYPRE\\_BoomerAMGDDDestroy](#) (HYPRE\_Solver solver)
- HYPRE\_Int [HYPRE\\_BoomerAMGDDSetup](#) (HYPRE\_Solver solver, HYPRE\_ParCSRMatrix A, HYPRE\_↵  
ParVector b, HYPRE\_ParVector x)
- HYPRE\_Int [HYPRE\\_BoomerAMGDDsolve](#) (HYPRE\_Solver solver, HYPRE\_ParCSRMatrix A, HYPRE\_↵  
ParVector b, HYPRE\_ParVector x)
- HYPRE\_Int [HYPRE\\_BoomerAMGDDSetFACNumRelax](#) (HYPRE\_Solver solver, HYPRE\_Int amgdd\_fac\_↵  
num\_relax)
- HYPRE\_Int [HYPRE\\_BoomerAMGDDSetFACNumCycles](#) (HYPRE\_Solver solver, HYPRE\_Int amgdd\_fac\_↵  
num\_cycles)

- HYPRE\_Int [HYPRE\\_BoomerAMGDDSetFACCycleType](#) (HYPRE\_Solver solver, HYPRE\_Int amgdd\_fac\_↵ cycle\_type)
- HYPRE\_Int [HYPRE\\_BoomerAMGDDSetFACRelaxType](#) (HYPRE\_Solver solver, HYPRE\_Int amgdd\_fac\_↵ relax\_type)
- HYPRE\_Int [HYPRE\\_BoomerAMGDDSetFACRelaxWeight](#) (HYPRE\_Solver solver, HYPRE\_Real amgdd\_↵ fac\_relax\_weight)
- HYPRE\_Int [HYPRE\\_BoomerAMGDDSetStartLevel](#) (HYPRE\_Solver solver, HYPRE\_Int start\_level)
- HYPRE\_Int [HYPRE\\_BoomerAMGDDSetPadding](#) (HYPRE\_Solver solver, HYPRE\_Int padding)
- HYPRE\_Int [HYPRE\\_BoomerAMGDDSetNumGhostLayers](#) (HYPRE\_Solver solver, HYPRE\_Int num\_ghost\_↵ layers)
- HYPRE\_Int [HYPRE\\_BoomerAMGDDSetUserFACRelaxation](#) (HYPRE\_Solver solver, HYPRE\_Int(\*user\_↵ FACRelaxation)(void \*amgdd\_vdata, HYPRE\_Int level, HYPRE\_Int cycle\_param))
- HYPRE\_Int [HYPRE\\_BoomerAMGDDGetAMG](#) (HYPRE\_Solver solver, HYPRE\_Solver \*amg\_solver)
- HYPRE\_Int [HYPRE\\_BoomerAMGDDGetFinalRelativeResidualNorm](#) (HYPRE\_Solver solver, HYPRE\_Real \*rel\_resid\_norm)
- HYPRE\_Int [HYPRE\\_BoomerAMGDDGetNumIterations](#) (HYPRE\_Solver solver, HYPRE\_Int \*num\_iterations)

### ParCSR ParaSails Preconditioner

Parallel sparse approximate inverse preconditioner for the ParCSR matrix format.

- HYPRE\_Int [HYPRE\\_ParaSailsCreate](#) (MPI\_Comm comm, HYPRE\_Solver \*solver)
- HYPRE\_Int [HYPRE\\_ParaSailsDestroy](#) (HYPRE\_Solver solver)
- HYPRE\_Int [HYPRE\\_ParaSailsSetup](#) (HYPRE\_Solver solver, HYPRE\_ParCSRMatrix A, HYPRE\_ParVector b, HYPRE\_ParVector x)
- HYPRE\_Int [HYPRE\\_ParaSailsSolve](#) (HYPRE\_Solver solver, HYPRE\_ParCSRMatrix A, HYPRE\_ParVector b, HYPRE\_ParVector x)
- HYPRE\_Int [HYPRE\\_ParaSailsSetParams](#) (HYPRE\_Solver solver, HYPRE\_Real thresh, HYPRE\_Int nlevels)
- HYPRE\_Int [HYPRE\\_ParaSailsSetFilter](#) (HYPRE\_Solver solver, HYPRE\_Real filter)
- HYPRE\_Int [HYPRE\\_ParaSailsSetSym](#) (HYPRE\_Solver solver, HYPRE\_Int sym)
- HYPRE\_Int [HYPRE\\_ParaSailsSetLoadbal](#) (HYPRE\_Solver solver, HYPRE\_Real loadbal)
- HYPRE\_Int [HYPRE\\_ParaSailsSetReuse](#) (HYPRE\_Solver solver, HYPRE\_Int reuse)
- HYPRE\_Int [HYPRE\\_ParaSailsSetLogging](#) (HYPRE\_Solver solver, HYPRE\_Int logging)
- HYPRE\_Int [HYPRE\\_ParaSailsBuildIJMatrix](#) (HYPRE\_Solver solver, HYPRE\_IJMatrix \*pij\_A)
- HYPRE\_Int [HYPRE\\_ParCSRParaSailsCreate](#) (MPI\_Comm comm, HYPRE\_Solver \*solver)
- HYPRE\_Int [HYPRE\\_ParCSRParaSailsDestroy](#) (HYPRE\_Solver solver)
- HYPRE\_Int [HYPRE\\_ParCSRParaSailsSetup](#) (HYPRE\_Solver solver, HYPRE\_ParCSRMatrix A, HYPRE\_↵ ParVector b, HYPRE\_ParVector x)
- HYPRE\_Int [HYPRE\\_ParCSRParaSailsSolve](#) (HYPRE\_Solver solver, HYPRE\_ParCSRMatrix A, HYPRE\_↵ ParVector b, HYPRE\_ParVector x)
- HYPRE\_Int [HYPRE\\_ParCSRParaSailsSetParams](#) (HYPRE\_Solver solver, HYPRE\_Real thresh, HYPRE\_Int nlevels)
- HYPRE\_Int [HYPRE\\_ParCSRParaSailsSetFilter](#) (HYPRE\_Solver solver, HYPRE\_Real filter)
- HYPRE\_Int [HYPRE\\_ParCSRParaSailsSetSym](#) (HYPRE\_Solver solver, HYPRE\_Int sym)
- HYPRE\_Int [HYPRE\\_ParCSRParaSailsSetLoadbal](#) (HYPRE\_Solver solver, HYPRE\_Real loadbal)
- HYPRE\_Int [HYPRE\\_ParCSRParaSailsSetReuse](#) (HYPRE\_Solver solver, HYPRE\_Int reuse)
- HYPRE\_Int [HYPRE\\_ParCSRParaSailsSetLogging](#) (HYPRE\_Solver solver, HYPRE\_Int logging)

### ParCSR Euclid Preconditioner

MPI Parallel ILU preconditioner

Options summary:



Option	Default	Synopsis
-level	1	ILU(k) factorization level
-bj	0 (false)	Use Block Jacobi ILU instead of PILU
-eu_stats	0 (false)	Print internal timing and statistics
-eu_mem	0 (false)	Print internal memory usage

- HYPRE\_Int [HYPRE\\_EuclidCreate](#) (MPI\_Comm comm, [HYPRE\\_Solver](#) \*solver)
- HYPRE\_Int [HYPRE\\_EuclidDestroy](#) ([HYPRE\\_Solver](#) solver)
- HYPRE\_Int [HYPRE\\_EuclidSetup](#) ([HYPRE\\_Solver](#) solver, HYPRE\_ParCSRMatrix A, HYPRE\_ParVector b, HYPRE\_ParVector x)
- HYPRE\_Int [HYPRE\\_EuclidSolve](#) ([HYPRE\\_Solver](#) solver, HYPRE\_ParCSRMatrix A, HYPRE\_ParVector b, HYPRE\_ParVector x)
- HYPRE\_Int [HYPRE\\_EuclidSetParams](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int argc, char \*argv[])
- HYPRE\_Int [HYPRE\\_EuclidSetParamsFromFile](#) ([HYPRE\\_Solver](#) solver, char \*filename)
- HYPRE\_Int [HYPRE\\_EuclidSetLevel](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int level)
- HYPRE\_Int [HYPRE\\_EuclidSetBJ](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int bj)
- HYPRE\_Int [HYPRE\\_EuclidSetStats](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int eu\_stats)
- HYPRE\_Int [HYPRE\\_EuclidSetMem](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int eu\_mem)
- HYPRE\_Int [HYPRE\\_EuclidSetSparseA](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Real sparse\_A)
- HYPRE\_Int [HYPRE\\_EuclidSetRowScale](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int row\_scale)
- HYPRE\_Int [HYPRE\\_EuclidSetILUT](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Real drop\_tol)

#### ParCSR Pilut Preconditioner

- HYPRE\_Int [HYPRE\\_ParCSRPilutCreate](#) (MPI\_Comm comm, [HYPRE\\_Solver](#) \*solver)
- HYPRE\_Int [HYPRE\\_ParCSRPilutDestroy](#) ([HYPRE\\_Solver](#) solver)
- HYPRE\_Int [HYPRE\\_ParCSRPilutSetup](#) ([HYPRE\\_Solver](#) solver, HYPRE\_ParCSRMatrix A, HYPRE\_ParVector b, HYPRE\_ParVector x)
- HYPRE\_Int [HYPRE\\_ParCSRPilutSolve](#) ([HYPRE\\_Solver](#) solver, HYPRE\_ParCSRMatrix A, HYPRE\_ParVector b, HYPRE\_ParVector x)
- HYPRE\_Int [HYPRE\\_ParCSRPilutSetMaxIter](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int max\_iter)
- HYPRE\_Int [HYPRE\\_ParCSRPilutSetDropTolerance](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_ParCSRPilutSetFactorRowSize](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int size)
- HYPRE\_Int [HYPRE\\_ParCSRPilutSetLogging](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int logging)

#### ParCSR AMS Solver and Preconditioner

Parallel auxiliary space Maxwell solver and preconditioner

- HYPRE\_Int [HYPRE\\_AMSCreate](#) ([HYPRE\\_Solver](#) \*solver)
- HYPRE\_Int [HYPRE\\_AMSDestroy](#) ([HYPRE\\_Solver](#) solver)
- HYPRE\_Int [HYPRE\\_AMSSetup](#) ([HYPRE\\_Solver](#) solver, HYPRE\_ParCSRMatrix A, HYPRE\_ParVector b, HYPRE\_ParVector x)
- HYPRE\_Int [HYPRE\\_AMSSolve](#) ([HYPRE\\_Solver](#) solver, HYPRE\_ParCSRMatrix A, HYPRE\_ParVector b, HYPRE\_ParVector x)
- HYPRE\_Int [HYPRE\\_AMSSetDimension](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int dim)
- HYPRE\_Int [HYPRE\\_AMSSetDiscreteGradient](#) ([HYPRE\\_Solver](#) solver, HYPRE\_ParCSRMatrix G)
- HYPRE\_Int [HYPRE\\_AMSSetCoordinateVectors](#) ([HYPRE\\_Solver](#) solver, HYPRE\_ParVector x, HYPRE\_ParVector y, HYPRE\_ParVector z)
- HYPRE\_Int [HYPRE\\_AMSSetEdgeConstantVectors](#) ([HYPRE\\_Solver](#) solver, HYPRE\_ParVector Gx, HYPRE\_ParVector Gy, HYPRE\_ParVector Gz)

- HYPRE\_Int [HYPRE\\_AMSSetInterpolations](#) (HYPRE\_Solver solver, HYPRE\_ParCSRMatrix Pi, HYPRE\_ParCSRMatrix Pix, HYPRE\_ParCSRMatrix Piy, HYPRE\_ParCSRMatrix Piz)
- HYPRE\_Int [HYPRE\\_AMSSetAlphaPoissonMatrix](#) (HYPRE\_Solver solver, HYPRE\_ParCSRMatrix A\_alpha)
- HYPRE\_Int [HYPRE\\_AMSSetBetaPoissonMatrix](#) (HYPRE\_Solver solver, HYPRE\_ParCSRMatrix A\_beta)
- HYPRE\_Int [HYPRE\\_AMSSetInteriorNodes](#) (HYPRE\_Solver solver, HYPRE\_ParVector interior\_nodes)
- HYPRE\_Int [HYPRE\\_AMSSetProjectionFrequency](#) (HYPRE\_Solver solver, HYPRE\_Int projection\_frequency)
- HYPRE\_Int [HYPRE\\_AMSSetMaxIter](#) (HYPRE\_Solver solver, HYPRE\_Int maxit)
- HYPRE\_Int [HYPRE\\_AMSSetTol](#) (HYPRE\_Solver solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_AMSSetCycleType](#) (HYPRE\_Solver solver, HYPRE\_Int cycle\_type)
- HYPRE\_Int [HYPRE\\_AMSSetPrintLevel](#) (HYPRE\_Solver solver, HYPRE\_Int print\_level)
- HYPRE\_Int [HYPRE\\_AMSSetSmoothingOptions](#) (HYPRE\_Solver solver, HYPRE\_Int relax\_type, HYPRE\_Int relax\_times, HYPRE\_Real relax\_weight, HYPRE\_Real omega)
- HYPRE\_Int [HYPRE\\_AMSSetAlphaAMGOptions](#) (HYPRE\_Solver solver, HYPRE\_Int alpha\_coarsen\_type, HYPRE\_Int alpha\_agg\_levels, HYPRE\_Int alpha\_relax\_type, HYPRE\_Real alpha\_strength\_threshold, HYPRE\_Int alpha\_interp\_type, HYPRE\_Int alpha\_Pmax)
- HYPRE\_Int [HYPRE\\_AMSSetAlphaAMGCoarseRelaxType](#) (HYPRE\_Solver solver, HYPRE\_Int alpha\_coarse\_relax\_type)
- HYPRE\_Int [HYPRE\\_AMSSetBetaAMGOptions](#) (HYPRE\_Solver solver, HYPRE\_Int beta\_coarsen\_type, HYPRE\_Int beta\_agg\_levels, HYPRE\_Int beta\_relax\_type, HYPRE\_Real beta\_strength\_threshold, HYPRE\_Int beta\_interp\_type, HYPRE\_Int beta\_Pmax)
- HYPRE\_Int [HYPRE\\_AMSSetBetaAMGCoarseRelaxType](#) (HYPRE\_Solver solver, HYPRE\_Int beta\_coarse\_relax\_type)
- HYPRE\_Int [HYPRE\\_AMSGetNumIterations](#) (HYPRE\_Solver solver, HYPRE\_Int \*num\_iterations)
- HYPRE\_Int [HYPRE\\_AMSGetFinalRelativeResidualNorm](#) (HYPRE\_Solver solver, HYPRE\_Real \*rel\_resid\_norm)
- HYPRE\_Int [HYPRE\\_AMSProjectOutGradients](#) (HYPRE\_Solver solver, HYPRE\_ParVector x)
- HYPRE\_Int [HYPRE\\_AMSConstructDiscreteGradient](#) (HYPRE\_ParCSRMatrix A, HYPRE\_ParVector x\_coord, HYPRE\_BigInt \*edge\_vertex, HYPRE\_Int edge\_orientation, HYPRE\_ParCSRMatrix \*G)

## ParCSR ADS Solver and Preconditioner

Parallel auxiliary space divergence solver and preconditioner

- HYPRE\_Int [HYPRE\\_ADSCreate](#) (HYPRE\_Solver \*solver)
- HYPRE\_Int [HYPRE\\_ADSDestroy](#) (HYPRE\_Solver solver)
- HYPRE\_Int [HYPRE\\_ADSSetup](#) (HYPRE\_Solver solver, HYPRE\_ParCSRMatrix A, HYPRE\_ParVector b, HYPRE\_ParVector x)
- HYPRE\_Int [HYPRE\\_ADSSolve](#) (HYPRE\_Solver solver, HYPRE\_ParCSRMatrix A, HYPRE\_ParVector b, HYPRE\_ParVector x)
- HYPRE\_Int [HYPRE\\_ADSSetDiscreteCurl](#) (HYPRE\_Solver solver, HYPRE\_ParCSRMatrix C)
- HYPRE\_Int [HYPRE\\_ADSSetDiscreteGradient](#) (HYPRE\_Solver solver, HYPRE\_ParCSRMatrix G)
- HYPRE\_Int [HYPRE\\_ADSSetCoordinateVectors](#) (HYPRE\_Solver solver, HYPRE\_ParVector x, HYPRE\_ParVector y, HYPRE\_ParVector z)
- HYPRE\_Int [HYPRE\\_ADSSetInterpolations](#) (HYPRE\_Solver solver, HYPRE\_ParCSRMatrix RT\_Pi, HYPRE\_ParCSRMatrix RT\_Pix, HYPRE\_ParCSRMatrix RT\_Piy, HYPRE\_ParCSRMatrix RT\_Piz, HYPRE\_ParCSRMatrix ND\_Pi, HYPRE\_ParCSRMatrix ND\_Pix, HYPRE\_ParCSRMatrix ND\_Piy, HYPRE\_ParCSRMatrix ND\_Piz)
- HYPRE\_Int [HYPRE\\_ADSSetMaxIter](#) (HYPRE\_Solver solver, HYPRE\_Int maxit)
- HYPRE\_Int [HYPRE\\_ADSSetTol](#) (HYPRE\_Solver solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_ADSSetCycleType](#) (HYPRE\_Solver solver, HYPRE\_Int cycle\_type)
- HYPRE\_Int [HYPRE\\_ADSSetPrintLevel](#) (HYPRE\_Solver solver, HYPRE\_Int print\_level)
- HYPRE\_Int [HYPRE\\_ADSSetSmoothingOptions](#) (HYPRE\_Solver solver, HYPRE\_Int relax\_type, HYPRE\_Int relax\_times, HYPRE\_Real relax\_weight, HYPRE\_Real omega)



- HYPRE\_Int [HYPRE\\_ADSSetChebySmoothingOptions](#) (HYPRE\_Solver solver, HYPRE\_Int cheby\_order, HYPRE\_Int cheby\_fraction)
- HYPRE\_Int [HYPRE\\_ADSSetAMSOOptions](#) (HYPRE\_Solver solver, HYPRE\_Int cycle\_type, HYPRE\_Int coarsen\_type, HYPRE\_Int agg\_levels, HYPRE\_Int relax\_type, HYPRE\_Real strength\_threshold, HYPRE\_Int interp\_type, HYPRE\_Int Pmax)
- HYPRE\_Int [HYPRE\\_ADSSetAMGOOptions](#) (HYPRE\_Solver solver, HYPRE\_Int coarsen\_type, HYPRE\_Int agg\_levels, HYPRE\_Int relax\_type, HYPRE\_Real strength\_threshold, HYPRE\_Int interp\_type, HYPRE\_Int Pmax)
- HYPRE\_Int [HYPRE\\_ADGetNumIterations](#) (HYPRE\_Solver solver, HYPRE\_Int \*num\_iterations)
- HYPRE\_Int [HYPRE\\_ADGetFinalRelativeResidualNorm](#) (HYPRE\_Solver solver, HYPRE\_Real \*rel\_resid\_norm)

### ParCSR PCG Solver

These routines should be used in conjunction with the generic interface in [Krylov Solvers](#).

- HYPRE\_Int [HYPRE\\_ParCSRPCGCreate](#) (MPI\_Comm comm, HYPRE\_Solver \*solver)
- HYPRE\_Int [HYPRE\\_ParCSRPCGDestroy](#) (HYPRE\_Solver solver)
- HYPRE\_Int [HYPRE\\_ParCSRPCGSetup](#) (HYPRE\_Solver solver, HYPRE\_ParCSRMatrix A, HYPRE\_ParVector b, HYPRE\_ParVector x)
- HYPRE\_Int [HYPRE\\_ParCSRPCGSolve](#) (HYPRE\_Solver solver, HYPRE\_ParCSRMatrix A, HYPRE\_ParVector b, HYPRE\_ParVector x)
- HYPRE\_Int [HYPRE\\_ParCSRPCGSetTol](#) (HYPRE\_Solver solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_ParCSRPCGSetAbsoluteTol](#) (HYPRE\_Solver solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_ParCSRPCGSetMaxIter](#) (HYPRE\_Solver solver, HYPRE\_Int max\_iter)
- HYPRE\_Int [HYPRE\\_ParCSRPCGSetStopCrit](#) (HYPRE\_Solver solver, HYPRE\_Int stop\_crit)
- HYPRE\_Int [HYPRE\\_ParCSRPCGSetTwoNorm](#) (HYPRE\_Solver solver, HYPRE\_Int two\_norm)
- HYPRE\_Int [HYPRE\\_ParCSRPCGSetRelChange](#) (HYPRE\_Solver solver, HYPRE\_Int rel\_change)
- HYPRE\_Int [HYPRE\\_ParCSRPCGSetPrecond](#) (HYPRE\_Solver solver, HYPRE\_PtrToParSolverFcn preconditioner, HYPRE\_PtrToParSolverFcn preconditioner\_setup, HYPRE\_Solver preconditioner\_solver)
- HYPRE\_Int [HYPRE\\_ParCSRPCGGetPrecond](#) (HYPRE\_Solver solver, HYPRE\_Solver \*precond\_data)
- HYPRE\_Int [HYPRE\\_ParCSRPCGSetLogging](#) (HYPRE\_Solver solver, HYPRE\_Int logging)
- HYPRE\_Int [HYPRE\\_ParCSRPCGSetPrintLevel](#) (HYPRE\_Solver solver, HYPRE\_Int print\_level)
- HYPRE\_Int [HYPRE\\_ParCSRPCGGetNumIterations](#) (HYPRE\_Solver solver, HYPRE\_Int \*num\_iterations)
- HYPRE\_Int [HYPRE\\_ParCSRPCGGetFinalRelativeResidualNorm](#) (HYPRE\_Solver solver, HYPRE\_Real \*norm)
- HYPRE\_Int [HYPRE\\_ParCSRPCGGetResidual](#) (HYPRE\_Solver solver, HYPRE\_ParVector \*residual)
- HYPRE\_Int [HYPRE\\_ParCSRDiagScaleSetup](#) (HYPRE\_Solver solver, HYPRE\_ParCSRMatrix A, HYPRE\_ParVector y, HYPRE\_ParVector x)
- HYPRE\_Int [HYPRE\\_ParCSRDiagScale](#) (HYPRE\_Solver solver, HYPRE\_ParCSRMatrix HA, HYPRE\_ParVector Hy, HYPRE\_ParVector Hx)
- HYPRE\_Int [HYPRE\\_ParCSROnProcTriSetup](#) (HYPRE\_Solver solver, HYPRE\_ParCSRMatrix HA, HYPRE\_ParVector Hy, HYPRE\_ParVector Hx)
- HYPRE\_Int [HYPRE\\_ParCSROnProcTriSolve](#) (HYPRE\_Solver solver, HYPRE\_ParCSRMatrix HA, HYPRE\_ParVector Hy, HYPRE\_ParVector Hx)

## ParCSR GMRES Solver

These routines should be used in conjunction with the generic interface in [Krylov Solvers](#).

- HYPRE\_Int [HYPRE\\_ParCSRGMRESCreate](#) (MPI\_Comm comm, [HYPRE\\_Solver](#) \*solver)
- HYPRE\_Int [HYPRE\\_ParCSRGMRESDestroy](#) ([HYPRE\\_Solver](#) solver)
- HYPRE\_Int [HYPRE\\_ParCSRGMRESSetup](#) ([HYPRE\\_Solver](#) solver, HYPRE\_ParCSRMatrix A, HYPRE\_↵  
ParVector b, HYPRE\_ParVector x)
- HYPRE\_Int [HYPRE\\_ParCSRGMRESSolve](#) ([HYPRE\\_Solver](#) solver, HYPRE\_ParCSRMatrix A, HYPRE\_↵  
ParVector b, HYPRE\_ParVector x)
- HYPRE\_Int [HYPRE\\_ParCSRGMRESSetKDim](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int k\_dim)
- HYPRE\_Int [HYPRE\\_ParCSRGMRESSetTol](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_ParCSRGMRESSetAbsoluteTol](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Real a\_tol)
- HYPRE\_Int [HYPRE\\_ParCSRGMRESSetMinIter](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int min\_iter)
- HYPRE\_Int [HYPRE\\_ParCSRGMRESSetMaxIter](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int max\_iter)
- HYPRE\_Int [HYPRE\\_ParCSRGMRESSetStopCrit](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int stop\_crit)
- HYPRE\_Int [HYPRE\\_ParCSRGMRESSetPrecond](#) ([HYPRE\\_Solver](#) solver, [HYPRE\\_PtrToParSolverFcn](#) pre-  
cond, [HYPRE\\_PtrToParSolverFcn](#) precondition\_setup, [HYPRE\\_Solver](#) precondition\_solver)
- HYPRE\_Int [HYPRE\\_ParCSRGMRESGetPrecond](#) ([HYPRE\\_Solver](#) solver, [HYPRE\\_Solver](#) \*precond\_data)
- HYPRE\_Int [HYPRE\\_ParCSRGMRESSetLogging](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int logging)
- HYPRE\_Int [HYPRE\\_ParCSRGMRESSetPrintLevel](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int print\_level)
- HYPRE\_Int [HYPRE\\_ParCSRGMRESGetNumIterations](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int \*num\_↵  
iterations)
- HYPRE\_Int [HYPRE\\_ParCSRGMRESGetFinalRelativeResidualNorm](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Real  
\*norm)
- HYPRE\_Int [HYPRE\\_ParCSRGMRESGetResidual](#) ([HYPRE\\_Solver](#) solver, HYPRE\_ParVector \*residual)
- HYPRE\_Int [HYPRE\\_ParCSRCOGMRESCreate](#) (MPI\_Comm comm, [HYPRE\\_Solver](#) \*solver)
- HYPRE\_Int [HYPRE\\_ParCSRCOGMRESDestroy](#) ([HYPRE\\_Solver](#) solver)
- HYPRE\_Int [HYPRE\\_ParCSRCOGMRESSetup](#) ([HYPRE\\_Solver](#) solver, HYPRE\_ParCSRMatrix A, HYPRE\_↵  
\_ParVector b, HYPRE\_ParVector x)
- HYPRE\_Int [HYPRE\\_ParCSRCOGMRESSolve](#) ([HYPRE\\_Solver](#) solver, HYPRE\_ParCSRMatrix A, HYPRE\_↵  
\_ParVector b, HYPRE\_ParVector x)
- HYPRE\_Int [HYPRE\\_ParCSRCOGMRESSetKDim](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int k\_dim)
- HYPRE\_Int [HYPRE\\_ParCSRCOGMRESSetUnroll](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int unroll)
- HYPRE\_Int [HYPRE\\_ParCSRCOGMRESSetCGS](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int cgs)
- HYPRE\_Int [HYPRE\\_ParCSRCOGMRESSetTol](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_ParCSRCOGMRESSetAbsoluteTol](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Real a\_tol)
- HYPRE\_Int [HYPRE\\_ParCSRCOGMRESSetMinIter](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int min\_iter)
- HYPRE\_Int [HYPRE\\_ParCSRCOGMRESSetMaxIter](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int max\_iter)
- HYPRE\_Int [HYPRE\\_ParCSRCOGMRESSetPrecond](#) ([HYPRE\\_Solver](#) solver, [HYPRE\\_PtrToParSolverFcn](#)  
precond, [HYPRE\\_PtrToParSolverFcn](#) precondition\_setup, [HYPRE\\_Solver](#) precondition\_solver)
- HYPRE\_Int [HYPRE\\_ParCSRCOGMRESGetPrecond](#) ([HYPRE\\_Solver](#) solver, [HYPRE\\_Solver](#) \*precond\_↵  
data)
- HYPRE\_Int [HYPRE\\_ParCSRCOGMRESSetLogging](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int logging)
- HYPRE\_Int [HYPRE\\_ParCSRCOGMRESSetPrintLevel](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int print\_level)
- HYPRE\_Int [HYPRE\\_ParCSRCOGMRESGetNumIterations](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int \*num\_↵  
iterations)
- HYPRE\_Int [HYPRE\\_ParCSRCOGMRESGetFinalRelativeResidualNorm](#) ([HYPRE\\_Solver](#) solver, HYPRE\_↵  
Real \*norm)
- HYPRE\_Int [HYPRE\\_ParCSRCOGMRESGetResidual](#) ([HYPRE\\_Solver](#) solver, HYPRE\_ParVector \*residual)

### ParCSR FlexGMRES Solver

These routines should be used in conjunction with the generic interface in [Krylov Solvers](#).

- HYPRE\_Int [HYPRE\\_ParCSRFlexGMRESCreate](#) (MPI\_Comm comm, [HYPRE\\_Solver](#) \*solver)
- HYPRE\_Int [HYPRE\\_ParCSRFlexGMRESDestroy](#) ([HYPRE\\_Solver](#) solver)
- HYPRE\_Int [HYPRE\\_ParCSRFlexGMRESSetup](#) ([HYPRE\\_Solver](#) solver, HYPRE\_ParCSRMatrix A, HYPRE\_ParVector b, HYPRE\_ParVector x)
- HYPRE\_Int [HYPRE\\_ParCSRFlexGMRESSolve](#) ([HYPRE\\_Solver](#) solver, HYPRE\_ParCSRMatrix A, HYPRE\_ParVector b, HYPRE\_ParVector x)
- HYPRE\_Int [HYPRE\\_ParCSRFlexGMRESSetKDim](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int k\_dim)
- HYPRE\_Int [HYPRE\\_ParCSRFlexGMRESSetTol](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_ParCSRFlexGMRESSetAbsoluteTol](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Real a\_tol)
- HYPRE\_Int [HYPRE\\_ParCSRFlexGMRESSetMinIter](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int min\_iter)
- HYPRE\_Int [HYPRE\\_ParCSRFlexGMRESSetMaxIter](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int max\_iter)
- HYPRE\_Int [HYPRE\\_ParCSRFlexGMRESSetPrecond](#) ([HYPRE\\_Solver](#) solver, [HYPRE\\_PtrToParSolverFcn](#) precondition, [HYPRE\\_PtrToParSolverFcn](#) precondition\_setup, [HYPRE\\_Solver](#) precondition\_solver)
- HYPRE\_Int [HYPRE\\_ParCSRFlexGMRESGetPrecond](#) ([HYPRE\\_Solver](#) solver, [HYPRE\\_Solver](#) \*precond\_data)
- HYPRE\_Int [HYPRE\\_ParCSRFlexGMRESSetLogging](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int logging)
- HYPRE\_Int [HYPRE\\_ParCSRFlexGMRESSetPrintLevel](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int print\_level)
- HYPRE\_Int [HYPRE\\_ParCSRFlexGMRESGetNumIterations](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int \*num\_iterations)
- HYPRE\_Int [HYPRE\\_ParCSRFlexGMRESGetFinalRelativeResidualNorm](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Real \*norm)
- HYPRE\_Int [HYPRE\\_ParCSRFlexGMRESGetResidual](#) ([HYPRE\\_Solver](#) solver, HYPRE\_ParVector \*residual)
- HYPRE\_Int [HYPRE\\_ParCSRFlexGMRESSetModifyPC](#) ([HYPRE\\_Solver](#) solver, [HYPRE\\_PtrToModifyPCFcn](#) modify\_pc)

### ParCSR LGMRES Solver

These routines should be used in conjunction with the generic interface in [Krylov Solvers](#).

- HYPRE\_Int [HYPRE\\_ParCSRLGMRESCreate](#) (MPI\_Comm comm, [HYPRE\\_Solver](#) \*solver)
- HYPRE\_Int [HYPRE\\_ParCSRLGMRESDestroy](#) ([HYPRE\\_Solver](#) solver)
- HYPRE\_Int [HYPRE\\_ParCSRLGMRESSetup](#) ([HYPRE\\_Solver](#) solver, HYPRE\_ParCSRMatrix A, HYPRE\_ParVector b, HYPRE\_ParVector x)
- HYPRE\_Int [HYPRE\\_ParCSRLGMRESSolve](#) ([HYPRE\\_Solver](#) solver, HYPRE\_ParCSRMatrix A, HYPRE\_ParVector b, HYPRE\_ParVector x)
- HYPRE\_Int [HYPRE\\_ParCSRLGMRESSetKDim](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int k\_dim)
- HYPRE\_Int [HYPRE\\_ParCSRLGMRESSetAugDim](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int aug\_dim)
- HYPRE\_Int [HYPRE\\_ParCSRLGMRESSetTol](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_ParCSRLGMRESSetAbsoluteTol](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Real a\_tol)
- HYPRE\_Int [HYPRE\\_ParCSRLGMRESSetMinIter](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int min\_iter)
- HYPRE\_Int [HYPRE\\_ParCSRLGMRESSetMaxIter](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int max\_iter)
- HYPRE\_Int [HYPRE\\_ParCSRLGMRESSetPrecond](#) ([HYPRE\\_Solver](#) solver, [HYPRE\\_PtrToParSolverFcn](#) precondition, [HYPRE\\_PtrToParSolverFcn](#) precondition\_setup, [HYPRE\\_Solver](#) precondition\_solver)
- HYPRE\_Int [HYPRE\\_ParCSRLGMRESGetPrecond](#) ([HYPRE\\_Solver](#) solver, [HYPRE\\_Solver](#) \*precond\_data)
- HYPRE\_Int [HYPRE\\_ParCSRLGMRESSetLogging](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int logging)
- HYPRE\_Int [HYPRE\\_ParCSRLGMRESSetPrintLevel](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int print\_level)
- HYPRE\_Int [HYPRE\\_ParCSRLGMRESGetNumIterations](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int \*num\_iterations)
- HYPRE\_Int [HYPRE\\_ParCSRLGMRESGetFinalRelativeResidualNorm](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Real \*norm)
- HYPRE\_Int [HYPRE\\_ParCSRLGMRESGetResidual](#) ([HYPRE\\_Solver](#) solver, HYPRE\_ParVector \*residual)

## ParCSR BiCGSTAB Solver

These routines should be used in conjunction with the generic interface in [Krylov Solvers](#).

- HYPRE\_Int [HYPRE\\_ParCSRBICGSTABCreate](#) (MPI\_Comm comm, [HYPRE\\_Solver](#) \*solver)
- HYPRE\_Int [HYPRE\\_ParCSRBICGSTABDestroy](#) ([HYPRE\\_Solver](#) solver)
- HYPRE\_Int [HYPRE\\_ParCSRBICGSTABSetup](#) ([HYPRE\\_Solver](#) solver, HYPRE\_ParCSRMatrix A, HYPRE\_ParVector b, HYPRE\_ParVector x)
- HYPRE\_Int [HYPRE\\_ParCSRBICGSTABSolve](#) ([HYPRE\\_Solver](#) solver, HYPRE\_ParCSRMatrix A, HYPRE\_ParVector b, HYPRE\_ParVector x)
- HYPRE\_Int [HYPRE\\_ParCSRBICGSTABSetTol](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_ParCSRBICGSTABSetAbsoluteTol](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Real a\_tol)
- HYPRE\_Int [HYPRE\\_ParCSRBICGSTABSetMinIter](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int min\_iter)
- HYPRE\_Int [HYPRE\\_ParCSRBICGSTABSetMaxIter](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int max\_iter)
- HYPRE\_Int [HYPRE\\_ParCSRBICGSTABSetStopCrit](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int stop\_crit)
- HYPRE\_Int [HYPRE\\_ParCSRBICGSTABSetPrecond](#) ([HYPRE\\_Solver](#) solver, [HYPRE\\_PtrToParSolverFcn](#) precondition, [HYPRE\\_PtrToParSolverFcn](#) precondition\_setup, [HYPRE\\_Solver](#) precondition\_solver)
- HYPRE\_Int [HYPRE\\_ParCSRBICGSTABGetPrecond](#) ([HYPRE\\_Solver](#) solver, [HYPRE\\_Solver](#) \*precondition\_data)
- HYPRE\_Int [HYPRE\\_ParCSRBICGSTABSetLogging](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int logging)
- HYPRE\_Int [HYPRE\\_ParCSRBICGSTABSetPrintLevel](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int print\_level)
- HYPRE\_Int [HYPRE\\_ParCSRBICGSTABGetNumIterations](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int \*num\_iterations)
- HYPRE\_Int [HYPRE\\_ParCSRBICGSTABGetFinalRelativeResidualNorm](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Real \*norm)
- HYPRE\_Int [HYPRE\\_ParCSRBICGSTABGetResidual](#) ([HYPRE\\_Solver](#) solver, HYPRE\_ParVector \*residual)

## ParCSR Hybrid Solver

- HYPRE\_Int [HYPRE\\_ParCSRHybridCreate](#) ([HYPRE\\_Solver](#) \*solver)
- HYPRE\_Int [HYPRE\\_ParCSRHybridDestroy](#) ([HYPRE\\_Solver](#) solver)
- HYPRE\_Int [HYPRE\\_ParCSRHybridSetup](#) ([HYPRE\\_Solver](#) solver, HYPRE\_ParCSRMatrix A, HYPRE\_ParVector b, HYPRE\_ParVector x)
- HYPRE\_Int [HYPRE\\_ParCSRHybridSolve](#) ([HYPRE\\_Solver](#) solver, HYPRE\_ParCSRMatrix A, HYPRE\_ParVector b, HYPRE\_ParVector x)
- HYPRE\_Int [HYPRE\\_ParCSRHybridSetTol](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_ParCSRHybridSetAbsoluteTol](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_ParCSRHybridSetConvergenceTol](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Real cf\_tol)
- HYPRE\_Int [HYPRE\\_ParCSRHybridSetDSCGMaxIter](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int dscg\_max\_its)
- HYPRE\_Int [HYPRE\\_ParCSRHybridSetPCGMaxIter](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int pcg\_max\_its)
- HYPRE\_Int [HYPRE\\_ParCSRHybridSetSetupType](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int setup\_type)
- HYPRE\_Int [HYPRE\\_ParCSRHybridSetSolverType](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int solver\_type)
- HYPRE\_Int [HYPRE\\_ParCSRHybridSetRecomputeResidual](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int recompute\_residual)
- HYPRE\_Int [HYPRE\\_ParCSRHybridGetRecomputeResidual](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int \*recompute\_residual)
- HYPRE\_Int [HYPRE\\_ParCSRHybridSetRecomputeResidualP](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int recompute\_residual\_p)
- HYPRE\_Int [HYPRE\\_ParCSRHybridGetRecomputeResidualP](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int \*recompute\_residual\_p)
- HYPRE\_Int [HYPRE\\_ParCSRHybridSetKDim](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int k\_dim)
- HYPRE\_Int [HYPRE\\_ParCSRHybridSetTwoNorm](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int two\_norm)
- HYPRE\_Int [HYPRE\\_ParCSRHybridSetStopCrit](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int stop\_crit)
- HYPRE\_Int [HYPRE\\_ParCSRHybridSetRelChange](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int rel\_change)

- HYPRE\_Int HYPRE\_ParCSRHybridSetPrecond (HYPRE\_Solver solver, HYPRE\_PtrToParSolverFcn precondition, HYPRE\_PtrToParSolverFcn precondition\_setup, HYPRE\_Solver precondition\_solver)
- HYPRE\_Int HYPRE\_ParCSRHybridSetLogging (HYPRE\_Solver solver, HYPRE\_Int logging)
- HYPRE\_Int HYPRE\_ParCSRHybridSetPrintLevel (HYPRE\_Solver solver, HYPRE\_Int print\_level)
- HYPRE\_Int HYPRE\_ParCSRHybridSetStrongThreshold (HYPRE\_Solver solver, HYPRE\_Real strong\_threshold ↵)
- HYPRE\_Int HYPRE\_ParCSRHybridSetMaxRowSum (HYPRE\_Solver solver, HYPRE\_Real max\_row\_sum)
- HYPRE\_Int HYPRE\_ParCSRHybridSetTruncFactor (HYPRE\_Solver solver, HYPRE\_Real trunc\_factor)
- HYPRE\_Int HYPRE\_ParCSRHybridSetPMaxElmts (HYPRE\_Solver solver, HYPRE\_Int P\_max\_elmts)
- HYPRE\_Int HYPRE\_ParCSRHybridSetMaxLevels (HYPRE\_Solver solver, HYPRE\_Int max\_levels)
- HYPRE\_Int HYPRE\_ParCSRHybridSetMeasureType (HYPRE\_Solver solver, HYPRE\_Int measure\_type)
- HYPRE\_Int HYPRE\_ParCSRHybridSetCoarsenType (HYPRE\_Solver solver, HYPRE\_Int coarsen\_type)
- HYPRE\_Int HYPRE\_ParCSRHybridSetInterpType (HYPRE\_Solver solver, HYPRE\_Int interp\_type)
- HYPRE\_Int HYPRE\_ParCSRHybridSetCycleType (HYPRE\_Solver solver, HYPRE\_Int cycle\_type)
- HYPRE\_Int HYPRE\_ParCSRHybridSetGridRelaxType (HYPRE\_Solver solver, HYPRE\_Int \*grid\_relax\_type)
- HYPRE\_Int HYPRE\_ParCSRHybridSetGridRelaxPoints (HYPRE\_Solver solver, HYPRE\_Int \*\*grid\_relax\_points ↵)
- HYPRE\_Int HYPRE\_ParCSRHybridSetNumSweeps (HYPRE\_Solver solver, HYPRE\_Int num\_sweeps)
- HYPRE\_Int HYPRE\_ParCSRHybridSetCycleNumSweeps (HYPRE\_Solver solver, HYPRE\_Int num\_sweeps, HYPRE\_Int k)
- HYPRE\_Int HYPRE\_ParCSRHybridSetRelaxType (HYPRE\_Solver solver, HYPRE\_Int relax\_type)
- HYPRE\_Int HYPRE\_ParCSRHybridSetCycleRelaxType (HYPRE\_Solver solver, HYPRE\_Int relax\_type, HYPRE\_Int k)
- HYPRE\_Int HYPRE\_ParCSRHybridSetRelaxOrder (HYPRE\_Solver solver, HYPRE\_Int relax\_order)
- HYPRE\_Int HYPRE\_ParCSRHybridSetRelaxWt (HYPRE\_Solver solver, HYPRE\_Real relax\_wt)
- HYPRE\_Int HYPRE\_ParCSRHybridSetLevelRelaxWt (HYPRE\_Solver solver, HYPRE\_Real relax\_wt, HYPRE\_Int level)
- HYPRE\_Int HYPRE\_ParCSRHybridSetOuterWt (HYPRE\_Solver solver, HYPRE\_Real outer\_wt)
- HYPRE\_Int HYPRE\_ParCSRHybridSetLevelOuterWt (HYPRE\_Solver solver, HYPRE\_Real outer\_wt, HYPRE\_Int level)
- HYPRE\_Int HYPRE\_ParCSRHybridSetMaxCoarseSize (HYPRE\_Solver solver, HYPRE\_Int max\_coarse\_size ↵)
- HYPRE\_Int HYPRE\_ParCSRHybridSetMinCoarseSize (HYPRE\_Solver solver, HYPRE\_Int min\_coarse\_size ↵)
- HYPRE\_Int HYPRE\_ParCSRHybridSetSeqThreshold (HYPRE\_Solver solver, HYPRE\_Int seq\_threshold)
- HYPRE\_Int HYPRE\_ParCSRHybridSetRelaxWeight (HYPRE\_Solver solver, HYPRE\_Real \*relax\_weight)
- HYPRE\_Int HYPRE\_ParCSRHybridSetOmega (HYPRE\_Solver solver, HYPRE\_Real \*omega)
- HYPRE\_Int HYPRE\_ParCSRHybridSetAggNumLevels (HYPRE\_Solver solver, HYPRE\_Int agg\_num\_levels)
- HYPRE\_Int HYPRE\_ParCSRHybridSetAggInterpType (HYPRE\_Solver solver, HYPRE\_Int agg\_interp\_type)
- HYPRE\_Int HYPRE\_ParCSRHybridSetNumPaths (HYPRE\_Solver solver, HYPRE\_Int num\_paths)
- HYPRE\_Int HYPRE\_ParCSRHybridSetNumFunctions (HYPRE\_Solver solver, HYPRE\_Int num\_functions)
- HYPRE\_Int HYPRE\_ParCSRHybridSetDofFunc (HYPRE\_Solver solver, HYPRE\_Int \*dof\_func)
- HYPRE\_Int HYPRE\_ParCSRHybridSetNodal (HYPRE\_Solver solver, HYPRE\_Int nodal)
- HYPRE\_Int HYPRE\_ParCSRHybridSetKeepTranspose (HYPRE\_Solver solver, HYPRE\_Int keepT)
- HYPRE\_Int HYPRE\_ParCSRHybridSetNonGalerkinTol (HYPRE\_Solver solver, HYPRE\_Int num\_levels, HYPRE\_Real \*nongalerkin\_tol)
- HYPRE\_Int HYPRE\_ParCSRHybridGetNumIterations (HYPRE\_Solver solver, HYPRE\_Int \*num\_its)
- HYPRE\_Int HYPRE\_ParCSRHybridGetDSCGNumIterations (HYPRE\_Solver solver, HYPRE\_Int \*dscg\_num\_its ↵)
- HYPRE\_Int HYPRE\_ParCSRHybridGetPCGNumIterations (HYPRE\_Solver solver, HYPRE\_Int \*pcg\_num\_its ↵)
- HYPRE\_Int HYPRE\_ParCSRHybridGetFinalRelativeResidualNorm (HYPRE\_Solver solver, HYPRE\_Real \*norm)
- HYPRE\_Int HYPRE\_ParCSRHybridSetNumGridSweeps (HYPRE\_Solver solver, HYPRE\_Int \*num\_grid\_sweeps ↵)
- HYPRE\_Int HYPRE\_ParCSRHybridGetSetupSolveTime (HYPRE\_Solver solver, HYPRE\_Real \*time)

## ParCSR MGR Solver

Parallel multigrid reduction solver and preconditioner. This solver or preconditioner is designed with systems of PDEs in mind. However, it can also be used for scalar linear systems, particularly for problems where the user can exploit information from the physics of the problem. In this way, the MGR solver could potentially be used as a foundation for a physics-based preconditioner.

- HYPRE\_Int [HYPRE\\_MGRCreate](#) (HYPRE\_Solver \*solver)
- HYPRE\_Int [HYPRE\\_MGRDestroy](#) (HYPRE\_Solver solver)
- HYPRE\_Int [HYPRE\\_MGRSetup](#) (HYPRE\_Solver solver, HYPRE\_ParCSRMatrix A, HYPRE\_ParVector b, HYPRE\_ParVector x)
- HYPRE\_Int [HYPRE\\_MGRSolve](#) (HYPRE\_Solver solver, HYPRE\_ParCSRMatrix A, HYPRE\_ParVector b, HYPRE\_ParVector x)
- HYPRE\_Int [HYPRE\\_MGRSetCpointsByContiguousBlock](#) (HYPRE\_Solver solver, HYPRE\_Int block\_size, HYPRE\_Int max\_num\_levels, HYPRE\_BigInt \*idx\_array, HYPRE\_Int \*num\_block\_coarse\_points, HYPRE\_Int \*\*block\_coarse\_indexes)
- HYPRE\_Int [HYPRE\\_MGRSetCpointsByBlock](#) (HYPRE\_Solver solver, HYPRE\_Int block\_size, HYPRE\_Int max\_num\_levels, HYPRE\_Int \*num\_block\_coarse\_points, HYPRE\_Int \*\*block\_coarse\_indexes)
- HYPRE\_Int [HYPRE\\_MGRSetCpointsByPointMarkerArray](#) (HYPRE\_Solver solver, HYPRE\_Int block\_size, HYPRE\_Int max\_num\_levels, HYPRE\_Int \*num\_block\_coarse\_points, HYPRE\_Int \*\*lvl\_block\_coarse\_indexes, HYPRE\_Int \*point\_marker\_array)
- HYPRE\_Int [HYPRE\\_MGRSetNonCpointsToFpoints](#) (HYPRE\_Solver solver, HYPRE\_Int nonCptToFptFlag)
- HYPRE\_Int [HYPRE\\_MGRSetMaxCoarseLevels](#) (HYPRE\_Solver solver, HYPRE\_Int maxlev)
- HYPRE\_Int [HYPRE\\_MGRSetBlockSize](#) (HYPRE\_Solver solver, HYPRE\_Int bsize)
- HYPRE\_Int [HYPRE\\_MGRSetReservedCoarseNodes](#) (HYPRE\_Solver solver, HYPRE\_Int reserved\_coarse\_size, HYPRE\_BigInt \*reserved\_coarse\_nodes)
- HYPRE\_Int [HYPRE\\_MGRSetReservedCpointsLevelToKeep](#) (HYPRE\_Solver solver, HYPRE\_Int level)
- HYPRE\_Int [HYPRE\\_MGRSetRelaxType](#) (HYPRE\_Solver solver, HYPRE\_Int relax\_type)
- HYPRE\_Int [HYPRE\\_MGRSetFRelaxMethod](#) (HYPRE\_Solver solver, HYPRE\_Int relax\_method)
- HYPRE\_Int [HYPRE\\_MGRSetLevelFRelaxMethod](#) (HYPRE\_Solver solver, HYPRE\_Int \*relax\_method)
- HYPRE\_Int [HYPRE\\_MGRSetCoarseGridMethod](#) (HYPRE\_Solver solver, HYPRE\_Int \*cg\_method)
- HYPRE\_Int [HYPRE\\_MGRSetLevelFRelaxNumFunctions](#) (HYPRE\_Solver solver, HYPRE\_Int \*num\_functions)
- HYPRE\_Int [HYPRE\\_MGRSetRestrictType](#) (HYPRE\_Solver solver, HYPRE\_Int restrict\_type)
- HYPRE\_Int [HYPRE\\_MGRSetLevelRestrictType](#) (HYPRE\_Solver solver, HYPRE\_Int \*restrict\_type)
- HYPRE\_Int [HYPRE\\_MGRSetNumRestrictSweeps](#) (HYPRE\_Solver solver, HYPRE\_Int nsweeps)
- HYPRE\_Int [HYPRE\\_MGRSetInterpType](#) (HYPRE\_Solver solver, HYPRE\_Int interp\_type)
- HYPRE\_Int [HYPRE\\_MGRSetLevelInterpType](#) (HYPRE\_Solver solver, HYPRE\_Int \*interp\_type)
- HYPRE\_Int [HYPRE\\_MGRSetNumRelaxSweeps](#) (HYPRE\_Solver solver, HYPRE\_Int nsweeps)
- HYPRE\_Int [HYPRE\\_MGRSetNumInterpSweeps](#) (HYPRE\_Solver solver, HYPRE\_Int nsweeps)
- HYPRE\_Int [HYPRE\\_MGRSetFSolver](#) (HYPRE\_Solver solver, HYPRE\_PtrToParSolverFcn fine\_grid\_solver\_solve, HYPRE\_PtrToParSolverFcn fine\_grid\_solver\_setup, HYPRE\_Solver fsolver)
- HYPRE\_Int [HYPRE\\_MGRBuildAff](#) (HYPRE\_ParCSRMatrix A, HYPRE\_Int \*CF\_marker, HYPRE\_Int debug\_flag, HYPRE\_ParCSRMatrix \*A\_ff)
- HYPRE\_Int [HYPRE\\_MGRSetCoarseSolver](#) (HYPRE\_Solver solver, HYPRE\_PtrToParSolverFcn coarse\_grid\_solver\_solve, HYPRE\_PtrToParSolverFcn coarse\_grid\_solver\_setup, HYPRE\_Solver coarse\_grid\_solver)
- HYPRE\_Int [HYPRE\\_MGRSetPrintLevel](#) (HYPRE\_Solver solver, HYPRE\_Int print\_level)
- HYPRE\_Int [HYPRE\\_MGRSetFrelaxPrintLevel](#) (HYPRE\_Solver solver, HYPRE\_Int print\_level)
- HYPRE\_Int [HYPRE\\_MGRSetCoarseGridPrintLevel](#) (HYPRE\_Solver solver, HYPRE\_Int print\_level)
- HYPRE\_Int [HYPRE\\_MGRSetTruncateCoarseGridThreshold](#) (HYPRE\_Solver solver, HYPRE\_Real threshold)
- HYPRE\_Int [HYPRE\\_MGRSetLogging](#) (HYPRE\_Solver solver, HYPRE\_Int logging)
- HYPRE\_Int [HYPRE\\_MGRSetMaxIter](#) (HYPRE\_Solver solver, HYPRE\_Int max\_iter)
- HYPRE\_Int [HYPRE\\_MGRSetTol](#) (HYPRE\_Solver solver, HYPRE\_Real tol)



- HYPRE\_Int [HYPRE\\_MGRSetMaxGlobalSmoothIters](#) (HYPRE\_Solver solver, HYPRE\_Int smooth\_iter)
- HYPRE\_Int [HYPRE\\_MGRSetGlobalSmoothType](#) (HYPRE\_Solver solver, HYPRE\_Int smooth\_type)
- HYPRE\_Int [HYPRE\\_MGRGetNumIterations](#) (HYPRE\_Solver solver, HYPRE\_Int \*num\_iterations)
- HYPRE\_Int [HYPRE\\_MGRGetCoarseGridConvergenceFactor](#) (HYPRE\_Solver solver, HYPRE\_Real \*conv\_factor)
- HYPRE\_Int [HYPRE\\_MGRSetPMaxElmts](#) (HYPRE\_Solver solver, HYPRE\_Int P\_max\_elmts)
- HYPRE\_Int [HYPRE\\_MGRGetFinalRelativeResidualNorm](#) (HYPRE\_Solver solver, HYPRE\_Real \*res\_norm)

## ParCSR ILU Solver

(Parallel) ILU smoother

- HYPRE\_Int [HYPRE\\_ILUCreate](#) (HYPRE\_Solver \*solver)
- HYPRE\_Int [HYPRE\\_ILUDestroy](#) (HYPRE\_Solver solver)
- HYPRE\_Int [HYPRE\\_ILUSetup](#) (HYPRE\_Solver solver, HYPRE\_ParCSRMatrix A, HYPRE\_ParVector b, HYPRE\_ParVector x)
- HYPRE\_Int [HYPRE\\_ILUSolve](#) (HYPRE\_Solver solver, HYPRE\_ParCSRMatrix A, HYPRE\_ParVector b, HYPRE\_ParVector x)
- HYPRE\_Int [HYPRE\\_ILUSetMaxIter](#) (HYPRE\_Solver solver, HYPRE\_Int max\_iter)
- HYPRE\_Int [HYPRE\\_ILUSetTol](#) (HYPRE\_Solver solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_ILUSetLevelOfFill](#) (HYPRE\_Solver solver, HYPRE\_Int lfil)
- HYPRE\_Int [HYPRE\\_ILUSetMaxNnzPerRow](#) (HYPRE\_Solver solver, HYPRE\_Int nzmax)
- HYPRE\_Int [HYPRE\\_ILUSetDropThreshold](#) (HYPRE\_Solver solver, HYPRE\_Real threshold)
- HYPRE\_Int [HYPRE\\_ILUSetDropThresholdArray](#) (HYPRE\_Solver solver, HYPRE\_Real \*threshold)
- HYPRE\_Int [HYPRE\\_ILUSetNSHDropThreshold](#) (HYPRE\_Solver solver, HYPRE\_Real threshold)
- HYPRE\_Int [HYPRE\\_ILUSetNSHDropThresholdArray](#) (HYPRE\_Solver solver, HYPRE\_Real \*threshold)
- HYPRE\_Int [HYPRE\\_ILUSetSchurMaxIter](#) (HYPRE\_Solver solver, HYPRE\_Int ss\_max\_iter)
- HYPRE\_Int [HYPRE\\_ILUSetType](#) (HYPRE\_Solver solver, HYPRE\_Int ilu\_type)
- HYPRE\_Int [HYPRE\\_ILUSetLocalReordering](#) (HYPRE\_Solver solver, HYPRE\_Int reordering\_type)
- HYPRE\_Int [HYPRE\\_ILUSetPrintLevel](#) (HYPRE\_Solver solver, HYPRE\_Int print\_level)
- HYPRE\_Int [HYPRE\\_ILUSetLogging](#) (HYPRE\_Solver solver, HYPRE\_Int logging)
- HYPRE\_Int [HYPRE\\_ILUGetNumIterations](#) (HYPRE\_Solver solver, HYPRE\_Int \*num\_iterations)
- HYPRE\_Int [HYPRE\\_ILUGetFinalRelativeResidualNorm](#) (HYPRE\_Solver solver, HYPRE\_Real \*res\_norm)
- HYPRE\_ParCSRMatrix [GenerateLaplacian](#) (MPI\_Comm comm, HYPRE\_BigInt nx, HYPRE\_BigInt ny, HYPRE\_BigInt nz, HYPRE\_Int P, HYPRE\_Int Q, HYPRE\_Int R, HYPRE\_Int p, HYPRE\_Int q, HYPRE\_Int r, HYPRE\_Real \*value)
- HYPRE\_ParCSRMatrix [GenerateLaplacian27pt](#) (MPI\_Comm comm, HYPRE\_BigInt nx, HYPRE\_BigInt ny, HYPRE\_BigInt nz, HYPRE\_Int P, HYPRE\_Int Q, HYPRE\_Int R, HYPRE\_Int p, HYPRE\_Int q, HYPRE\_Int r, HYPRE\_Real \*value)
- HYPRE\_ParCSRMatrix [GenerateLaplacian9pt](#) (MPI\_Comm comm, HYPRE\_BigInt nx, HYPRE\_BigInt ny, HYPRE\_Int P, HYPRE\_Int Q, HYPRE\_Int p, HYPRE\_Int q, HYPRE\_Real \*value)
- HYPRE\_ParCSRMatrix [GenerateDifConv](#) (MPI\_Comm comm, HYPRE\_BigInt nx, HYPRE\_BigInt ny, HYPRE\_BigInt nz, HYPRE\_Int P, HYPRE\_Int Q, HYPRE\_Int R, HYPRE\_Int p, HYPRE\_Int q, HYPRE\_Int r, HYPRE\_Real \*value)
- HYPRE\_ParCSRMatrix [GenerateRotate7pt](#) (MPI\_Comm comm, HYPRE\_BigInt nx, HYPRE\_BigInt ny, HYPRE\_Int P, HYPRE\_Int Q, HYPRE\_Int p, HYPRE\_Int q, HYPRE\_Real alpha, HYPRE\_Real eps)
- HYPRE\_ParCSRMatrix [GenerateVarDifConv](#) (MPI\_Comm comm, HYPRE\_BigInt nx, HYPRE\_BigInt ny, HYPRE\_BigInt nz, HYPRE\_Int P, HYPRE\_Int Q, HYPRE\_Int R, HYPRE\_Int p, HYPRE\_Int q, HYPRE\_Int r, HYPRE\_Real eps, HYPRE\_ParVector \*rhs\_ptr)
- HYPRE\_ParCSRMatrix [GenerateRSVarDifConv](#) (MPI\_Comm comm, HYPRE\_BigInt nx, HYPRE\_BigInt ny, HYPRE\_BigInt nz, HYPRE\_Int P, HYPRE\_Int Q, HYPRE\_Int R, HYPRE\_Int p, HYPRE\_Int q, HYPRE\_Int r, HYPRE\_Real eps, HYPRE\_ParVector \*rhs\_ptr, HYPRE\_Int type)

- float \* [GenerateCoordinates](#) (MPI\_Comm comm, HYPRE\_BigInt nx, HYPRE\_BigInt ny, HYPRE\_BigInt nz, HYPRE\_Int P, HYPRE\_Int Q, HYPRE\_Int R, HYPRE\_Int p, HYPRE\_Int q, HYPRE\_Int r, HYPRE\_Int coord-dim)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetPostInterpType](#) (HYPRE\_Solver solver, HYPRE\_Int post\_interp\_type)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetJacobiTruncThreshold](#) (HYPRE\_Solver solver, HYPRE\_Real jacobi\_trunc\_threshold)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetNumCRRelaxSteps](#) (HYPRE\_Solver solver, HYPRE\_Int num\_CR\_relax\_steps)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetCRRate](#) (HYPRE\_Solver solver, HYPRE\_Real CR\_rate)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetCRStrongTh](#) (HYPRE\_Solver solver, HYPRE\_Real CR\_strong\_th)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetCRUseCG](#) (HYPRE\_Solver solver, HYPRE\_Int CR\_use\_CG)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetISType](#) (HYPRE\_Solver solver, HYPRE\_Int IS\_type)

### ParCSR LOBPCG Eigensolver

These routines should be used in conjunction with the generic interface in [Eigensolvers](#).

- HYPRE\_Int [HYPRE\\_ParCSRSetupInterpreter](#) (mv\_InterfaceInterpreter \*i)
- HYPRE\_Int [HYPRE\\_ParCSRSetupMatvec](#) (HYPRE\_MatvecFunctions \*mv)
- HYPRE\_Int [HYPRE\\_ParCSRMultiVectorPrint](#) (void \*x\_, const char \*fileName)
- void \* [HYPRE\\_ParCSRMultiVectorRead](#) (MPI\_Comm comm, void \*ii\_, const char \*fileName)

## 3.6.1 Detailed Description

These solvers use matrix/vector storage schemes that are tailored for general sparse matrix systems.

@memo Linear solvers for sparse matrix systems

## 3.6.2 Macro Definition Documentation

### 3.6.2.1 HYPRE\_MODIFYPC

```
#define HYPRE_MODIFYPC
```

### 3.6.2.2 HYPRE\_SOLVER\_STRUCT

```
#define HYPRE_SOLVER_STRUCT
```

The solver object.

## 3.6.3 Typedef Documentation

### 3.6.3.1 HYPRE\_PtrToModifyPCFcn

```
typedef HYPRE_Int(* HYPRE_PtrToModifyPCFcn) (HYPRE_Solver, HYPRE_Int, HYPRE_Real)
```



### 3.6.3.2 HYPRE\_PtrToParSolverFcn

```
typedef HYPRE_Int (* HYPRE_PtrToParSolverFcn) (HYPRE_Solver, HYPRE_ParCSRMatrix, HYPRE_ParVector, HYPRE_ParVector)
```

### 3.6.3.3 HYPRE\_Solver

```
typedef struct hypre_Solver_struct* HYPRE_Solver
```

## 3.6.4 Function Documentation

### 3.6.4.1 GenerateCoordinates()

```
float * GenerateCoordinates (
    MPI_Comm comm,
    HYPRE_BigInt nx,
    HYPRE_BigInt ny,
    HYPRE_BigInt nz,
    HYPRE_Int P,
    HYPRE_Int Q,
    HYPRE_Int R,
    HYPRE_Int p,
    HYPRE_Int q,
    HYPRE_Int r,
    HYPRE_Int coorddim )
```

### 3.6.4.2 GenerateDifConv()

```
HYPRE_ParCSRMatrix GenerateDifConv (
    MPI_Comm comm,
    HYPRE_BigInt nx,
    HYPRE_BigInt ny,
    HYPRE_BigInt nz,
    HYPRE_Int P,
    HYPRE_Int Q,
    HYPRE_Int R,
    HYPRE_Int p,
    HYPRE_Int q,
    HYPRE_Int r,
    HYPRE_Real * value )
```

### 3.6.4.3 GenerateLaplacian()

```
HYPRE_ParCSRMatrix GenerateLaplacian (
    MPI_Comm comm,
    HYPRE_BigInt nx,
    HYPRE_BigInt ny,
    HYPRE_BigInt nz,
    HYPRE_Int P,
    HYPRE_Int Q,
    HYPRE_Int R,
    HYPRE_Int p,
    HYPRE_Int q,
    HYPRE_Int r,
    HYPRE_Real * value )
```

#### 3.6.4.4 GenerateLaplacian27pt()

```
HYPRE_ParCSRMatrix GenerateLaplacian27pt (
    MPI_Comm comm,
    HYPRE_BigInt nx,
    HYPRE_BigInt ny,
    HYPRE_BigInt nz,
    HYPRE_Int P,
    HYPRE_Int Q,
    HYPRE_Int R,
    HYPRE_Int p,
    HYPRE_Int q,
    HYPRE_Int r,
    HYPRE_Real * value )
```

#### 3.6.4.5 GenerateLaplacian9pt()

```
HYPRE_ParCSRMatrix GenerateLaplacian9pt (
    MPI_Comm comm,
    HYPRE_BigInt nx,
    HYPRE_BigInt ny,
    HYPRE_Int P,
    HYPRE_Int Q,
    HYPRE_Int p,
    HYPRE_Int q,
    HYPRE_Real * value )
```

#### 3.6.4.6 GenerateRotate7pt()

```
HYPRE_ParCSRMatrix GenerateRotate7pt (
    MPI_Comm comm,
    HYPRE_BigInt nx,
    HYPRE_BigInt ny,
    HYPRE_Int P,
    HYPRE_Int Q,
    HYPRE_Int p,
    HYPRE_Int q,
    HYPRE_Real alpha,
    HYPRE_Real eps )
```

#### 3.6.4.7 GenerateRSVarDifConv()

```
HYPRE_ParCSRMatrix GenerateRSVarDifConv (
    MPI_Comm comm,
    HYPRE_BigInt nx,
    HYPRE_BigInt ny,
    HYPRE_BigInt nz,
    HYPRE_Int P,
    HYPRE_Int Q,
    HYPRE_Int R,
    HYPRE_Int p,
    HYPRE_Int q,
    HYPRE_Int r,
    HYPRE_Real eps,
    HYPRE_ParVector * rhs_ptr,
    HYPRE_Int type )
```

**3.6.4.8 GenerateVarDifConv()**

```

HYPRE_ParCSRMatrix GenerateVarDifConv (
    MPI_Comm comm,
    HYPRE_BigInt nx,
    HYPRE_BigInt ny,
    HYPRE_BigInt nz,
    HYPRE_Int P,
    HYPRE_Int Q,
    HYPRE_Int R,
    HYPRE_Int p,
    HYPRE_Int q,
    HYPRE_Int r,
    HYPRE_Real eps,
    HYPRE_ParVector * rhs_ptr )

```

**3.6.4.9 HYPRE\_ADSCreate()**

```

HYPRE_Int HYPRE_ADSCreate (
    HYPRE_Solver * solver )

```

Create an ADS solver object.

**3.6.4.10 HYPRE\_ADSDestroy()**

```

HYPRE_Int HYPRE_ADSDestroy (
    HYPRE_Solver solver )

```

Destroy an ADS solver object.

**3.6.4.11 HYPRE\_ADSSetFinalRelativeResidualNorm()**

```

HYPRE_Int HYPRE_ADSSetFinalRelativeResidualNorm (
    HYPRE_Solver solver,
    HYPRE_Real * rel_resid_norm )

```

Returns the norm of the final relative residual.

**3.6.4.12 HYPRE\_ADSSetNumIterations()**

```

HYPRE_Int HYPRE_ADSSetNumIterations (
    HYPRE_Solver solver,
    HYPRE_Int * num_iterations )

```

Returns the number of iterations taken.

### 3.6.4.13 HYPRE\_ADSSetAMGOptions()

```
HYPRE_Int HYPRE_ADSSetAMGOptions (
    HYPRE_Solver solver,
    HYPRE_Int coarsen_type,
    HYPRE_Int agg_levels,
    HYPRE_Int relax_type,
    HYPRE_Real strength_threshold,
    HYPRE_Int interp_type,
    HYPRE_Int Pmax )
```

(Optional) Sets AMG parameters for  $B_{II}$ . The defaults are 10, 1, 3, 0.25, 0, 0. See the user's manual for more details.

### 3.6.4.14 HYPRE\_ADSSetAMSOptions()

```
HYPRE_Int HYPRE_ADSSetAMSOptions (
    HYPRE_Solver solver,
    HYPRE_Int cycle_type,
    HYPRE_Int coarsen_type,
    HYPRE_Int agg_levels,
    HYPRE_Int relax_type,
    HYPRE_Real strength_threshold,
    HYPRE_Int interp_type,
    HYPRE_Int Pmax )
```

(Optional) Sets AMS parameters for  $B_C$ . The defaults are 11, 10, 1, 3, 0.25, 0, 0. Note that *cycle\_type* should be greater than 10, unless the high-order interface of HYPRE\_ADSSetInterpolations is being used! See the user's manual for more details.

### 3.6.4.15 HYPRE\_ADSSetChebySmoothingOptions()

```
HYPRE_Int HYPRE_ADSSetChebySmoothingOptions (
    HYPRE_Solver solver,
    HYPRE_Int cheby_order,
    HYPRE_Int cheby_fraction )
```

(Optional) Sets parameters for Chebyshev relaxation. The defaults are 2, 0.3.

### 3.6.4.16 HYPRE\_ADSSetCoordinateVectors()

```
HYPRE_Int HYPRE_ADSSetCoordinateVectors (
    HYPRE_Solver solver,
    HYPRE_ParVector x,
    HYPRE_ParVector y,
    HYPRE_ParVector z )
```

Sets the  $x$ ,  $y$  and  $z$  coordinates of the vertices in the mesh. This function should be called before [HYPRE\\_ADSSetup\(\)](#)!

**3.6.4.17 HYPRE\_ADSSetCycleType()**

```
HYPRE_Int HYPRE_ADSSetCycleType (
    HYPRE_Solver solver,
    HYPRE_Int cycle_type )
```

(Optional) Choose which auxiliary-space solver to use. Possible values are:

- 1 : 3-level multiplicative solver (01210)
- 2 : 3-level additive solver (0+1+2)
- 3 : 3-level multiplicative solver (02120)
- 4 : 3-level additive solver (010+2)
- 5 : 3-level multiplicative solver (0102010)
- 6 : 3-level additive solver (1+020)
- 7 : 3-level multiplicative solver (0201020)
- 8 : 3-level additive solver (0(1+2)0)
- 11 : 5-level multiplicative solver (013454310)
- 12 : 5-level additive solver (0+1+3+4+5)
- 13 : 5-level multiplicative solver (034515430)
- 14 : 5-level additive solver (01(3+4+5)10)

The default is 1. See the user's manual for more details.

**3.6.4.18 HYPRE\_ADSSetDiscreteCurl()**

```
HYPRE_Int HYPRE_ADSSetDiscreteCurl (
    HYPRE_Solver solver,
    HYPRE_ParCSRMatrix C )
```

Sets the discrete curl matrix *C*. This function should be called before [HYPRE\\_ADSSetup\(\)](#)!

**3.6.4.19 HYPRE\_ADSSetDiscreteGradient()**

```
HYPRE_Int HYPRE_ADSSetDiscreteGradient (
    HYPRE_Solver solver,
    HYPRE_ParCSRMatrix G )
```

Sets the discrete gradient matrix *G*. This function should be called before [HYPRE\\_ADSSetup\(\)](#)!

### 3.6.4.20 HYPRE\_ADSSetInterpolations()

```
HYPRE_Int HYPRE_ADSSetInterpolations (
    HYPRE_Solver solver,
    HYPRE_ParCSRMatrix RT_Pi,
    HYPRE_ParCSRMatrix RT_Pix,
    HYPRE_ParCSRMatrix RT_Piy,
    HYPRE_ParCSRMatrix RT_Piz,
    HYPRE_ParCSRMatrix ND_Pi,
    HYPRE_ParCSRMatrix ND_Pix,
    HYPRE_ParCSRMatrix ND_Piy,
    HYPRE_ParCSRMatrix ND_Piz )
```

(Optional) Set the (components of) the Raviart-Thomas ( $\Pi_{RT}$ ) and the Nedelec ( $\Pi_{ND}$ ) interpolation matrices.

This function is generally intended to be used only for high-order  $H(div)$  discretizations (in the lowest order case, these matrices are constructed internally in ADS from the discrete gradient and curl matrices and the coordinates of the vertices), though it can also be used in the lowest-order case or for other types of discretizations.

By definition,  $RT\_Pi$  and  $ND\_Pi$  are the matrix representations of the linear operators  $\Pi_{RT}$  and  $\Pi_{ND}$  that interpolate (high-order) vector nodal finite elements into the (high-order) Raviart-Thomas and Nedelec spaces. The component matrices are defined in both cases as  $\Pi^x \varphi = \Pi(\varphi, 0, 0)$  and similarly for  $\Pi^y$  and  $\Pi^z$ . Note that all these operators depend on the choice of the basis and degrees of freedom in the high-order spaces.

The column numbering of  $RT\_Pi$  and  $ND\_Pi$  should be node-based, i.e. the  $x/y/z$  components of the first node (vertex or high-order dof) should be listed first, followed by the  $x/y/z$  components of the second node and so on (see the documentation of `HYPRE_BoomerAMGSetDofFunc`).

If used, this function should be called before `hypre_ADSSetup()` and there is no need to provide the vertex coordinates. Furthermore, only one of the sets  $\{\Pi_{RT}\}$  and  $\{\Pi_{RT}^x, \Pi_{RT}^y, \Pi_{RT}^z\}$  needs to be specified (though it is OK to provide both). If  $RT\_Pix$  is NULL, then scalar  $\Pi$ -based ADS cycles, i.e. those with `cycle_type` > 10, will be unavailable. Similarly, ADS cycles based on monolithic  $\Pi$  (`cycle_type` < 10) require that  $RT\_Pi$  is not NULL. The same restrictions hold for the sets  $\{\Pi_{ND}\}$  and  $\{\Pi_{ND}^x, \Pi_{ND}^y, \Pi_{ND}^z\}$  – only one of them needs to be specified, and the availability of each enables different AMS cycle type options.

### 3.6.4.21 HYPRE\_ADSSetMaxIter()

```
HYPRE_Int HYPRE_ADSSetMaxIter (
    HYPRE_Solver solver,
    HYPRE_Int maxit )
```

(Optional) Sets maximum number of iterations, if ADS is used as a solver. To use ADS as a preconditioner, set the maximum number of iterations to 1. The default is 20.

### 3.6.4.22 HYPRE\_ADSSetPrintLevel()

```
HYPRE_Int HYPRE_ADSSetPrintLevel (
    HYPRE_Solver solver,
    HYPRE_Int print_level )
```

(Optional) Control how much information is printed during the solution iterations. The default is 1 (print residual norm at each step).

### 3.6.4.23 HYPRE\_ADSSetSmoothingOptions()

```
HYPRE_Int HYPRE_ADSSetSmoothingOptions (
    HYPRE_Solver solver,
    HYPRE_Int relax_type,
    HYPRE_Int relax_times,
    HYPRE_Real relax_weight,
    HYPRE_Real omega )
```

(Optional) Sets relaxation parameters for  $A$ . The defaults are 2, 1, 1.0, 1.0.

The available options for *relax\_type* are:

- 1 :  $\ell_1$ -scaled Jacobi
- 2 :  $\ell_1$ -scaled block symmetric Gauss-Seidel/SSOR
- 3 : Kaczmarz
- 4 : truncated version of  $\ell_1$ -scaled block symmetric Gauss-Seidel/SSOR
- 16 : Chebyshev

### 3.6.4.24 HYPRE\_ADSSetTol()

```
HYPRE_Int HYPRE_ADSSetTol (
    HYPRE_Solver solver,
    HYPRE_Real tol )
```

(Optional) Set the convergence tolerance, if ADS is used as a solver. When using ADS as a preconditioner, set the tolerance to 0.0. The default is  $10^{-6}$ .

### 3.6.4.25 HYPRE\_ADSSetup()

```
HYPRE_Int HYPRE_ADSSetup (
    HYPRE_Solver solver,
    HYPRE_ParCSRMatrix A,
    HYPRE_ParVector b,
    HYPRE_ParVector x )
```

Set up the ADS solver or preconditioner. If used as a preconditioner, this function should be passed to the iterative solver *SetPrecond* function.

#### Parameters

<i>solver</i>	[IN] object to be set up.
<i>A</i>	[IN] ParCSR matrix used to construct the solver/preconditioner.
<i>b</i>	Ignored by this function.
<i>x</i>	Ignored by this function.

### 3.6.4.26 HYPRE\_ADSSolve()

```
HYPRE_Int HYPRE_ADSSolve (
    HYPRE_Solver solver,
    HYPRE_ParCSRMatrix A,
    HYPRE_ParVector b,
    HYPRE_ParVector x )
```

Solve the system or apply ADS as a preconditioner. If used as a preconditioner, this function should be passed to the iterative solver *SetPrecond* function.

#### Parameters

<i>solver</i>	[IN] solver or preconditioner object to be applied.
<i>A</i>	[IN] ParCSR matrix, matrix of the linear system to be solved
<i>b</i>	[IN] right hand side of the linear system to be solved
<i>x</i>	[OUT] approximated solution of the linear system to be solved

### 3.6.4.27 HYPRE\_AMSConstructDiscreteGradient()

```
HYPRE_Int HYPRE_AMSConstructDiscreteGradient (
    HYPRE_ParCSRMatrix A,
    HYPRE_ParVector x_coord,
    HYPRE_BigInt * edge_vertex,
    HYPRE_Int edge_orientation,
    HYPRE_ParCSRMatrix * G )
```

Construct and return the lowest-order discrete gradient matrix *G* using some edge and vertex information. We assume that *edge\_vertex* lists the edge vertices consecutively, and that the orientation of all edges is consistent.

If *edge\_orientation* = 1, the edges are already oriented.

If *edge\_orientation* = 2, the orientation of edge *i* depends only on the sign of *edge\_vertex*[2\*i+1] - *edge\_vertex*[2\*i].

### 3.6.4.28 HYPRE\_AMSCreate()

```
HYPRE_Int HYPRE_AMSCreate (
    HYPRE_Solver * solver )
```

Create an AMS solver object.

### 3.6.4.29 HYPRE\_AMSDestroy()

```
HYPRE_Int HYPRE_AMSDestroy (
    HYPRE_Solver solver )
```

Destroy an AMS solver object.



**3.6.4.30 HYPRE\_AMSGetFinalRelativeResidualNorm()**

```
HYPRE_Int HYPRE_AMSGetFinalRelativeResidualNorm (
    HYPRE_Solver solver,
    HYPRE_Real * rel_resid_norm )
```

Returns the norm of the final relative residual.

**3.6.4.31 HYPRE\_AMSGetNumIterations()**

```
HYPRE_Int HYPRE_AMSGetNumIterations (
    HYPRE_Solver solver,
    HYPRE_Int * num_iterations )
```

Returns the number of iterations taken.

**3.6.4.32 HYPRE\_AMSProjectOutGradients()**

```
HYPRE_Int HYPRE_AMSProjectOutGradients (
    HYPRE_Solver solver,
    HYPRE_ParVector x )
```

For problems with zero-conductivity regions, project the vector onto the compatible subspace:  $x = (I - G_0(G_0^t G_0)^{-1} G_0^t)x$ , where  $G_0$  is the discrete gradient restricted to the interior nodes of the regions with zero conductivity. This ensures that  $x$  is orthogonal to the gradients in the range of  $G_0$ .

This function is typically called after the solution iteration is complete, in order to facilitate the visualization of the computed field. Without it the values in the zero-conductivity regions contain kernel components.

**3.6.4.33 HYPRE\_AMSSetAlphaAMGCoarseRelaxType()**

```
HYPRE_Int HYPRE_AMSSetAlphaAMGCoarseRelaxType (
    HYPRE_Solver solver,
    HYPRE_Int alpha_coarse_relax_type )
```

(Optional) Sets the coarsest level relaxation in the AMG solver for  $B_{II}$ . The default is 8 (I1-GS). Use 9, 19, 29 or 99 for a direct solver.

**3.6.4.34 HYPRE\_AMSSetAlphaAMGOptions()**

```
HYPRE_Int HYPRE_AMSSetAlphaAMGOptions (
    HYPRE_Solver solver,
    HYPRE_Int alpha_coarsen_type,
    HYPRE_Int alpha_agg_levels,
    HYPRE_Int alpha_relax_type,
    HYPRE_Real alpha_strength_threshold,
    HYPRE_Int alpha_interp_type,
    HYPRE_Int alpha_Pmax )
```

(Optional) Sets AMG parameters for  $B_{II}$ . The defaults are 10, 1, 3, 0.25, 0, 0. See the user's manual for more details.

### 3.6.4.35 HYPRE\_AMSSetAlphaPoissonMatrix()

```
HYPRE_Int HYPRE_AMSSetAlphaPoissonMatrix (
    HYPRE_Solver solver,
    HYPRE_ParCSRMatrix A_alpha )
```

(Optional) Sets the matrix  $A_\alpha$  corresponding to the Poisson problem with coefficient  $\alpha$  (the curl-curl term coefficient in the Maxwell problem).

If this function is called, the coarse space solver on the range of  $\Pi^T$  is a block-diagonal version of  $A_\Pi$ . If this function is not called, the coarse space solver on the range of  $\Pi^T$  is constructed as  $\Pi^T A \Pi$  in [HYPRE\\_AMSSetup\(\)](#). See the user's manual for more details.

### 3.6.4.36 HYPRE\_AMSSetBetaAMGCoarseRelaxType()

```
HYPRE_Int HYPRE_AMSSetBetaAMGCoarseRelaxType (
    HYPRE_Solver solver,
    HYPRE_Int beta_coarse_relax_type )
```

(Optional) Sets the coarsest level relaxation in the AMG solver for  $B_G$ . The default is 8 (I1-GS). Use 9, 19, 29 or 99 for a direct solver.

### 3.6.4.37 HYPRE\_AMSSetBetaAMGOptions()

```
HYPRE_Int HYPRE_AMSSetBetaAMGOptions (
    HYPRE_Solver solver,
    HYPRE_Int beta_coarsen_type,
    HYPRE_Int beta_agg_levels,
    HYPRE_Int beta_relax_type,
    HYPRE_Real beta_strength_threshold,
    HYPRE_Int beta_interp_type,
    HYPRE_Int beta_Pmax )
```

(Optional) Sets AMG parameters for  $B_G$ . The defaults are 10, 1, 3, 0.25, 0, 0. See the user's manual for more details.

### 3.6.4.38 HYPRE\_AMSSetBetaPoissonMatrix()

```
HYPRE_Int HYPRE_AMSSetBetaPoissonMatrix (
    HYPRE_Solver solver,
    HYPRE_ParCSRMatrix A_beta )
```

(Optional) Sets the matrix  $A_\beta$  corresponding to the Poisson problem with coefficient  $\beta$  (the mass term coefficient in the Maxwell problem).

If not given, the Poisson matrix will be computed in [HYPRE\\_AMSSetup\(\)](#). If the given matrix is NULL, we assume that  $\beta$  is identically 0 and use two-level (instead of three-level) methods. See the user's manual for more details.

**3.6.4.39 HYPRE\_AMSSetCoordinateVectors()**

```
HYPRE_Int HYPRE_AMSSetCoordinateVectors (
    HYPRE_Solver solver,
    HYPRE_ParVector x,
    HYPRE_ParVector y,
    HYPRE_ParVector z )
```

Sets the x, y and z coordinates of the vertices in the mesh.

Either [HYPRE\\_AMSSetCoordinateVectors\(\)](#) or [HYPRE\\_AMSSetEdgeConstantVectors\(\)](#) should be called before [HYPRE\\_AMSSetup\(\)](#)!

**3.6.4.40 HYPRE\_AMSSetCycleType()**

```
HYPRE_Int HYPRE_AMSSetCycleType (
    HYPRE_Solver solver,
    HYPRE_Int cycle_type )
```

(Optional) Choose which three-level solver to use. Possible values are:

- 1 : 3-level multiplicative solver (01210)
- 2 : 3-level additive solver (0+1+2)
- 3 : 3-level multiplicative solver (02120)
- 4 : 3-level additive solver (010+2)
- 5 : 3-level multiplicative solver (0102010)
- 6 : 3-level additive solver (1+020)
- 7 : 3-level multiplicative solver (0201020)
- 8 : 3-level additive solver (0(1+2)0)
- 11 : 5-level multiplicative solver (013454310)
- 12 : 5-level additive solver (0+1+3+4+5)
- 13 : 5-level multiplicative solver (034515430)
- 14 : 5-level additive solver (01(3+4+5)10)

The default is 1. See the user's manual for more details.

**3.6.4.41 HYPRE\_AMSSetDimension()**

```
HYPRE_Int HYPRE_AMSSetDimension (
    HYPRE_Solver solver,
    HYPRE_Int dim )
```

(Optional) Sets the problem dimension (2 or 3). The default is 3.

### 3.6.4.42 HYPRE\_AMSSetDiscreteGradient()

```
HYPRE_Int HYPRE_AMSSetDiscreteGradient (
    HYPRE_Solver solver,
    HYPRE_ParCSRMatrix G )
```

Sets the discrete gradient matrix  $G$ . This function should be called before [HYPRE\\_AMSSetup\(\)](#)!

### 3.6.4.43 HYPRE\_AMSSetEdgeConstantVectors()

```
HYPRE_Int HYPRE_AMSSetEdgeConstantVectors (
    HYPRE_Solver solver,
    HYPRE_ParVector Gx,
    HYPRE_ParVector Gy,
    HYPRE_ParVector Gz )
```

Sets the vectors  $Gx$ ,  $Gy$  and  $Gz$  which give the representations of the constant vector fields  $(1,0,0)$ ,  $(0,1,0)$  and  $(0,0,1)$  in the edge element basis.

Either [HYPRE\\_AMSSetCoordinateVectors\(\)](#) or [HYPRE\\_AMSSetEdgeConstantVectors\(\)](#) should be called before [HYPRE\\_AMSSetup\(\)](#)!

### 3.6.4.44 HYPRE\_AMSSetInteriorNodes()

```
HYPRE_Int HYPRE_AMSSetInteriorNodes (
    HYPRE_Solver solver,
    HYPRE_ParVector interior_nodes )
```

(Optional) Set the list of nodes which are interior to a zero-conductivity region. This way, a more robust solver is constructed, that can be iterated to lower tolerance levels. A node is interior if its entry in the array is 1.0. This function should be called before [HYPRE\\_AMSSetup\(\)](#)!

### 3.6.4.45 HYPRE\_AMSSetInterpolations()

```
HYPRE_Int HYPRE_AMSSetInterpolations (
    HYPRE_Solver solver,
    HYPRE_ParCSRMatrix Pi,
    HYPRE_ParCSRMatrix Pix,
    HYPRE_ParCSRMatrix Piy,
    HYPRE_ParCSRMatrix Piz )
```

(Optional) Set the (components of) the Nedelec interpolation matrix  $\Pi = [\Pi^x, \Pi^y, \Pi^z]$ .

This function is generally intended to be used only for high-order Nedelec discretizations (in the lowest order case,  $\Pi$  is constructed internally in AMS from the discrete gradient matrix and the coordinates of the vertices), though it can also be used in the lowest-order case or for other types of discretizations (e.g. ones based on the second family of Nedelec elements).

By definition,  $\Pi$  is the matrix representation of the linear operator that interpolates (high-order) vector nodal finite elements into the (high-order) Nedelec space. The component matrices are defined as  $\Pi^x \varphi = \Pi(\varphi, 0, 0)$  and similarly for  $\Pi^y$  and  $\Pi^z$ . Note that all these operators depend on the choice of the basis and degrees of freedom in the high-order spaces.

The column numbering of  $Pi$  should be node-based, i.e. the  $x/y/z$  components of the first node (vertex or high-order dof) should be listed first, followed by the  $x/y/z$  components of the second node and so on (see the documentation of [HYPRE\\_BoomerAMGSetDofFunc\(\)](#)).

If used, this function should be called before [HYPRE\\_AMSSetup\(\)](#) and there is no need to provide the vertex coordinates. Furthermore, only one of the sets  $\{\Pi\}$  and  $\{\Pi^x, \Pi^y, \Pi^z\}$  needs to be specified (though it is OK to provide both). If  $Pix$  is NULL, then scalar  $\Pi$ -based AMS cycles, i.e. those with *cycle\_type* > 10, will be unavailable. Similarly, AMS cycles based on monolithic  $\Pi$  (*cycle\_type* < 10) require that  $Pi$  is not NULL.

**3.6.4.46 HYPRE\_AMSsetMaxIter()**

```
HYPRE_Int HYPRE_AMSsetMaxIter (
    HYPRE_Solver solver,
    HYPRE_Int maxit )
```

(Optional) Sets maximum number of iterations, if AMS is used as a solver. To use AMS as a preconditioner, set the maximum number of iterations to 1. The default is 20.

**3.6.4.47 HYPRE\_AMSsetPrintLevel()**

```
HYPRE_Int HYPRE_AMSsetPrintLevel (
    HYPRE_Solver solver,
    HYPRE_Int print_level )
```

(Optional) Control how much information is printed during the solution iterations. The default is 1 (print residual norm at each step).

**3.6.4.48 HYPRE\_AMSsetProjectionFrequency()**

```
HYPRE_Int HYPRE_AMSsetProjectionFrequency (
    HYPRE_Solver solver,
    HYPRE_Int projection_frequency )
```

(Optional) Set the frequency at which a projection onto the compatible subspace for problems with zero-conductivity regions is performed. The default value is 5.

**3.6.4.49 HYPRE\_AMSsetSmoothingOptions()**

```
HYPRE_Int HYPRE_AMSsetSmoothingOptions (
    HYPRE_Solver solver,
    HYPRE_Int relax_type,
    HYPRE_Int relax_times,
    HYPRE_Real relax_weight,
    HYPRE_Real omega )
```

(Optional) Sets relaxation parameters for  $A$ . The defaults are 2, 1, 1.0, 1.0.

The available options for *relax\_type* are:

- 1 :  $\ell_1$ -scaled Jacobi
- 2 :  $\ell_1$ -scaled block symmetric Gauss-Seidel/SSOR
- 3 : Kaczmarz
- 4 : truncated version of  $\ell_1$ -scaled block symmetric Gauss-Seidel/SSOR
- 16 : Chebyshev

### 3.6.4.50 HYPRE\_AMSSetTol()

```
HYPRE_Int HYPRE_AMSSetTol (
    HYPRE_Solver solver,
    HYPRE_Real tol )
```

(Optional) Set the convergence tolerance, if AMS is used as a solver. When using AMS as a preconditioner, set the tolerance to 0.0. The default is  $10^{-6}$ .

### 3.6.4.51 HYPRE\_AMSSetup()

```
HYPRE_Int HYPRE_AMSSetup (
    HYPRE_Solver solver,
    HYPRE_ParCSRMatrix A,
    HYPRE_ParVector b,
    HYPRE_ParVector x )
```

Set up the AMS solver or preconditioner. If used as a preconditioner, this function should be passed to the iterative solver *SetPrecond* function.

#### Parameters

<i>solver</i>	[IN] object to be set up.
<i>A</i>	[IN] ParCSR matrix used to construct the solver/preconditioner.
<i>b</i>	Ignored by this function.
<i>x</i>	Ignored by this function.

### 3.6.4.52 HYPRE\_AMSSolve()

```
HYPRE_Int HYPRE_AMSSolve (
    HYPRE_Solver solver,
    HYPRE_ParCSRMatrix A,
    HYPRE_ParVector b,
    HYPRE_ParVector x )
```

Solve the system or apply AMS as a preconditioner. If used as a preconditioner, this function should be passed to the iterative solver *SetPrecond* function.

#### Parameters

<i>solver</i>	[IN] solver or preconditioner object to be applied.
<i>A</i>	[IN] ParCSR matrix, matrix of the linear system to be solved
<i>b</i>	[IN] right hand side of the linear system to be solved
<i>x</i>	[OUT] approximated solution of the linear system to be solved

### 3.6.4.53 HYPRE\_BoomerAMGCreate()

```
HYPRE_Int HYPRE_BoomerAMGCreate (
    HYPRE_Solver * solver )
```

Create a solver object.

#### 3.6.4.54 HYPRE\_BoomerAMGDDCreate()

```
HYPRE_Int HYPRE_BoomerAMGDDCreate (  
    HYPRE_Solver * solver )
```

Create a solver object.

#### 3.6.4.55 HYPRE\_BoomerAMGDDDestroy()

```
HYPRE_Int HYPRE_BoomerAMGDDDestroy (  
    HYPRE_Solver solver )
```

Destroy a solver object.

#### 3.6.4.56 HYPRE\_BoomerAMGDDGetAMG()

```
HYPRE_Int HYPRE_BoomerAMGDDGetAMG (  
    HYPRE_Solver solver,  
    HYPRE_Solver * amg_solver )
```

(Optional) Get the underlying AMG hierarchy as a HYPRE\_Solver object.

#### 3.6.4.57 HYPRE\_BoomerAMGDDGetFinalRelativeResidualNorm()

```
HYPRE_Int HYPRE_BoomerAMGDDGetFinalRelativeResidualNorm (  
    HYPRE_Solver solver,  
    HYPRE_Real * rel_resid_norm )
```

Returns the norm of the final relative residual.

#### 3.6.4.58 HYPRE\_BoomerAMGDDGetNumIterations()

```
HYPRE_Int HYPRE_BoomerAMGDDGetNumIterations (  
    HYPRE_Solver solver,  
    HYPRE_Int * num_iterations )
```

Returns the number of iterations taken.

#### 3.6.4.59 HYPRE\_BoomerAMGDDSetFACCycleType()

```
HYPRE_Int HYPRE_BoomerAMGDDSetFACCycleType (  
    HYPRE_Solver solver,  
    HYPRE_Int amgdd_fac_cycle_type )
```

(Optional) Set the cycle type for the AMG-DD inner FAC cycles. 1 (default) = V-cycle, 2 = W-cycle, 3 = F-cycle

**3.6.4.60 HYPRE\_BoomerAMGDDSetFACNumCycles()**

```
HYPRE_Int HYPRE_BoomerAMGDDSetFACNumCycles (
    HYPRE_Solver solver,
    HYPRE_Int amgdd_fac_num_cycles )
```

(Optional) Set the number of inner FAC cycles per AMG-DD iteration. Default is 2.

**3.6.4.61 HYPRE\_BoomerAMGDDSetFACNumRelax()**

```
HYPRE_Int HYPRE_BoomerAMGDDSetFACNumRelax (
    HYPRE_Solver solver,
    HYPRE_Int amgdd_fac_num_relax )
```

(Optional) Set the number of pre- and post-relaxations per level for AMG-DD inner FAC cycles. Default is 1.

**3.6.4.62 HYPRE\_BoomerAMGDDSetFACRelaxType()**

```
HYPRE_Int HYPRE_BoomerAMGDDSetFACRelaxType (
    HYPRE_Solver solver,
    HYPRE_Int amgdd_fac_relax_type )
```

(Optional) Set the relaxation type for the AMG-DD inner FAC cycles. 0 = Jacobi, 1 = Gauss-Seidel, 2 = ordered Gauss-Seidel, 3 (default) = C/F L1-scaled Jacobi

**3.6.4.63 HYPRE\_BoomerAMGDDSetFACRelaxWeight()**

```
HYPRE_Int HYPRE_BoomerAMGDDSetFACRelaxWeight (
    HYPRE_Solver solver,
    HYPRE_Real amgdd_fac_relax_weight )
```

(Optional) Set the relaxation weight for the AMG-DD inner FAC cycles. Default is 1.0.

**3.6.4.64 HYPRE\_BoomerAMGDDSetNumGhostLayers()**

```
HYPRE_Int HYPRE_BoomerAMGDDSetNumGhostLayers (
    HYPRE_Solver solver,
    HYPRE_Int num_ghost_layers )
```

(Optional) Set the AMG-DD number of ghost layers. Default is 1.

**3.6.4.65 HYPRE\_BoomerAMGDDSetPadding()**

```
HYPRE_Int HYPRE_BoomerAMGDDSetPadding (
    HYPRE_Solver solver,
    HYPRE_Int padding )
```

(Optional) Set the AMG-DD padding. Default is 1.



**3.6.4.66 HYPRE\_BoomerAMGDDSetStartLevel()**

```
HYPRE_Int HYPRE_BoomerAMGDDSetStartLevel (
    HYPRE_Solver solver,
    HYPRE_Int start_level )
```

(Optional) Set the AMG-DD start level. Default is 0.

**3.6.4.67 HYPRE\_BoomerAMGDDSetup()**

```
HYPRE_Int HYPRE_BoomerAMGDDSetup (
    HYPRE_Solver solver,
    HYPRE_ParCSRMatrix A,
    HYPRE_ParVector b,
    HYPRE_ParVector x )
```

Set up the BoomerAMGDD solver or preconditioner. If used as a preconditioner, this function should be passed to the iterative solver *SetPrecond* function.

**Parameters**

<i>solver</i>	[IN] object to be set up.
<i>A</i>	[IN] ParCSR matrix used to construct the solver/preconditioner.
<i>b</i>	Ignored by this function.
<i>x</i>	Ignored by this function.

**3.6.4.68 HYPRE\_BoomerAMGDDSetUserFACRelaxation()**

```
HYPRE_Int HYPRE_BoomerAMGDDSetUserFACRelaxation (
    HYPRE_Solver solver,
    HYPRE_Int(*) (void *amgdd_vdata, HYPRE_Int level, HYPRE_Int cycle_param) user↔
    FACRelaxation )
```

(Optional) Pass a custom user-defined function as a relaxation method for the AMG-DD FAC cycles. Function should have the following form, where *amgdd\_solver* is of type *hypre\_ParAMGDDData\** and *level* is the level on which to relax: *HYPRE\_Int userFACRelaxation( HYPRE\_Solver amgdd\_solver, HYPRE\_Int level )*

**3.6.4.69 HYPRE\_BoomerAMGDDSolve()**

```
HYPRE_Int HYPRE_BoomerAMGDDSolve (
    HYPRE_Solver solver,
    HYPRE_ParCSRMatrix A,
    HYPRE_ParVector b,
    HYPRE_ParVector x )
```

Solve the system or apply AMG-DD as a preconditioner. If used as a preconditioner, this function should be passed to the iterative solver *SetPrecond* function.

## Parameters

<i>solver</i>	[IN] solver or preconditioner object to be applied.
<i>A</i>	[IN] ParCSR matrix, matrix of the linear system to be solved
<i>b</i>	[IN] right hand side of the linear system to be solved
<i>x</i>	[OUT] approximated solution of the linear system to be solved

**3.6.4.70 HYPRE\_BoomerAMGDestroy()**

```
HYPRE_Int HYPRE_BoomerAMGDestroy (
    HYPRE_Solver solver )
```

Destroy a solver object.

**3.6.4.71 HYPRE\_BoomerAMGGetFinalRelativeResidualNorm()**

```
HYPRE_Int HYPRE_BoomerAMGGetFinalRelativeResidualNorm (
    HYPRE_Solver solver,
    HYPRE_Real * rel_resid_norm )
```

Returns the norm of the final relative residual.

**3.6.4.72 HYPRE\_BoomerAMGGetGridHierarchy()**

```
HYPRE_Int HYPRE_BoomerAMGGetGridHierarchy (
    HYPRE_Solver solver,
    HYPRE_Int * cgrid )
```

(Optional) Get the coarse grid hierarchy. Assumes input/ output array is preallocated to the size of the local matrix. On return, *cgrid[i]* returns the last grid level containing node *i*.

## Parameters

<i>solver</i>	[IN] solver or preconditioner
<i>cgrid</i>	[IN/ OUT] preallocated array. On return, contains grid hierarchy info.

**3.6.4.73 HYPRE\_BoomerAMGGetNumIterations()**

```
HYPRE_Int HYPRE_BoomerAMGGetNumIterations (
    HYPRE_Solver solver,
    HYPRE_Int * num_iterations )
```

Returns the number of iterations taken.

**3.6.4.74 HYPRE\_BoomerAMGGetResidual()**

```
HYPRE_Int HYPRE_BoomerAMGGetResidual (
    HYPRE_Solver solver,
    HYPRE_ParVector * residual )
```

Returns the residual.

**3.6.4.75 HYPRE\_BoomerAMGInitGridRelaxation()**

```
HYPRE_Int HYPRE_BoomerAMGInitGridRelaxation (
    HYPRE_Int ** num_grid_sweeps_ptr,
    HYPRE_Int ** grid_relax_type_ptr,
    HYPRE_Int *** grid_relax_points_ptr,
    HYPRE_Int coarsen_type,
    HYPRE_Real ** relax_weights_ptr,
    HYPRE_Int max_levels )
```

(Optional) This routine will be eliminated in the future.

**3.6.4.76 HYPRE\_BoomerAMGSetAdditive()**

```
HYPRE_Int HYPRE_BoomerAMGSetAdditive (
    HYPRE_Solver solver,
    HYPRE_Int addlvl )
```

(Optional) Defines use of an additive V(1,1)-cycle using the classical additive method starting at level 'addlvl'. The multiplicative approach is used on levels 0, ...'addlvl+1'. 'addlvl' needs to be  $> -1$  for this to have an effect. Can only be used with weighted Jacobi and l1-Jacobi(default).

Can only be used when AMG is used as a preconditioner !!!

**3.6.4.77 HYPRE\_BoomerAMGSetAddLastLvl()**

```
HYPRE_Int HYPRE_BoomerAMGSetAddLastLvl (
    HYPRE_Solver solver,
    HYPRE_Int add_last_lvl )
```

(Optional) Defines last level where additive, mult-additive or simple cycle is used. The multiplicative approach is used on levels  $> \text{add\_last\_lvl}$ .

Can only be used when AMG is used as a preconditioner !!!

**3.6.4.78 HYPRE\_BoomerAMGSetAddRelaxType()**

```
HYPRE_Int HYPRE_BoomerAMGSetAddRelaxType (
    HYPRE_Solver solver,
    HYPRE_Int add_rlx_type )
```

(Optional) Defines the relaxation type used in the (mult)additive cycle portion (also affects simple method.) The default is 18 (L1-Jacobi). Currently the only other option allowed is 0 (Jacobi) which should be used in combination with HYPRE\_BoomerAMGSetAddRelaxWt.

**3.6.4.79 HYPRE\_BoomerAMGSetAddRelaxWt()**

```
HYPRE_Int HYPRE_BoomerAMGSetAddRelaxWt (
    HYPRE_Solver solver,
    HYPRE_Real add_rlx_wt )
```

(Optional) Defines the relaxation weight used for Jacobi within the (mult)additive or simple cycle portion. The default is 1. The weight only affects the Jacobi method, and has no effect on L1-Jacobi

**3.6.4.80 HYPRE\_BoomerAMGSetADropTol()**

```
HYPRE_Int HYPRE_BoomerAMGSetADropTol (
    HYPRE_Solver solver,
    HYPRE_Real A_drop_tol )
```

(Optional) Defines the drop tolerance for the A-matrices from the 2nd level of AMG. The default is 0.

**3.6.4.81 HYPRE\_BoomerAMGSetADropType()**

```
HYPRE_Int HYPRE_BoomerAMGSetADropType (
    HYPRE_Solver solver,
    HYPRE_Int A_drop_type )
```

(Optional) Drop the entries that are not on the diagonal and smaller than its row norm: type 1: 1-norm, 2: 2-norm, -1: infinity norm

**3.6.4.82 HYPRE\_BoomerAMGSetAggInterpType()**

```
HYPRE_Int HYPRE_BoomerAMGSetAggInterpType (
    HYPRE_Solver solver,
    HYPRE_Int agg_interp_type )
```

(Optional) Defines the interpolation used on levels of aggressive coarsening The default is 4, i.e. multipass interpolation. The following options exist:

- 1 : 2-stage extended+i interpolation
- 2 : 2-stage standard interpolation
- 3 : 2-stage extended interpolation
- 4 : multipass interpolation
- 5 : 2-stage extended interpolation in matrix-matrix form
- 6 : 2-stage extended+i interpolation in matrix-matrix form
- 7 : 2-stage extended+e interpolation in matrix-matrix form

**3.6.4.83 HYPRE\_BoomerAMGSetAggNumLevels()**

```
HYPRE_Int HYPRE_BoomerAMGSetAggNumLevels (
    HYPRE_Solver solver,
    HYPRE_Int agg_num_levels )
```

(Optional) Defines the number of levels of aggressive coarsening. The default is 0, i.e. no aggressive coarsening.

**3.6.4.84 HYPRE\_BoomerAMGSetAggP12MaxElmts()**

```
HYPRE_Int HYPRE_BoomerAMGSetAggP12MaxElmts (
    HYPRE_Solver solver,
    HYPRE_Int agg_p12_max_elmts )
```

(Optional) Defines the maximal number of elements per row for the matrices P1 and P2 which are used to build 2-stage interpolation. The default is 0.

**3.6.4.85 HYPRE\_BoomerAMGSetAggP12TruncFactor()**

```
HYPRE_Int HYPRE_BoomerAMGSetAggP12TruncFactor (
    HYPRE_Solver solver,
    HYPRE_Real agg_p12_trunc_factor )
```

(Optional) Defines the truncation factor for the matrices P1 and P2 which are used to build 2-stage interpolation. The default is 0.

**3.6.4.86 HYPRE\_BoomerAMGSetAggPMaxElmts()**

```
HYPRE_Int HYPRE_BoomerAMGSetAggPMaxElmts (
    HYPRE_Solver solver,
    HYPRE_Int agg_p_max_elmts )
```

(Optional) Defines the maximal number of elements per row for the interpolation used for aggressive coarsening. The default is 0.

**3.6.4.87 HYPRE\_BoomerAMGSetAggTruncFactor()**

```
HYPRE_Int HYPRE_BoomerAMGSetAggTruncFactor (
    HYPRE_Solver solver,
    HYPRE_Real agg_trunc_factor )
```

(Optional) Defines the truncation factor for the interpolation used for aggressive coarsening. The default is 0.

**3.6.4.88 HYPRE\_BoomerAMGSetCGCIts()**

```
HYPRE_Int HYPRE_BoomerAMGSetCGCIts (
    HYPRE_Solver solver,
    HYPRE_Int its )
```

(optional) Defines the number of pathes for CGC-coarsening.

**3.6.4.89 HYPRE\_BoomerAMGSetChebyEigEst()**

```
HYPRE_Int HYPRE_BoomerAMGSetChebyEigEst (
    HYPRE_Solver solver,
    HYPRE_Int eig_est )
```

(Optional) Defines how to estimate eigenvalues. The default is 10 (i.e., 10 CG iterations are used to find extreme eigenvalues.) If eig\_est=0, the largest eigenvalue is estimated using Gershgorin, the smallest is set to 0. If eig\_est is a positive number n, n iterations of CG are used to determine the smallest and largest eigenvalue.

**3.6.4.90 HYPRE\_BoomerAMGSetChebyFraction()**

```
HYPRE_Int HYPRE_BoomerAMGSetChebyFraction (
    HYPRE_Solver solver,
    HYPRE_Real ratio )
```

(Optional) Fraction of the spectrum to use for the Chebyshev smoother. The default is .3 (i.e., damp on upper 30% of the spectrum).

**3.6.4.91 HYPRE\_BoomerAMGSetChebyOrder()**

```
HYPRE_Int HYPRE_BoomerAMGSetChebyOrder (
    HYPRE_Solver solver,
    HYPRE_Int order )
```

(Optional) Defines the Order for Chebyshev smoother. The default is 2 (valid options are 1-4).

**3.6.4.92 HYPRE\_BoomerAMGSetChebyScale()**

```
HYPRE_Int HYPRE_BoomerAMGSetChebyScale (
    HYPRE_Solver solver,
    HYPRE_Int scale )
```

(Optional) Defines whether matrix should be scaled. The default is 1 (i.e., scaled).

**3.6.4.93 HYPRE\_BoomerAMGSetChebyVariant()**

```
HYPRE_Int HYPRE_BoomerAMGSetChebyVariant (
    HYPRE_Solver solver,
    HYPRE_Int variant )
```

(Optional) Defines which polynomial variant should be used. The default is 0 (i.e., scaled).

**3.6.4.94 HYPRE\_BoomerAMGSetCoarsenCutFactor()**

```
HYPRE_Int HYPRE_BoomerAMGSetCoarsenCutFactor (
    HYPRE_Solver solver,
    HYPRE_Int coarsen_cut_factor )
```

(Optional) Sets cut factor for choosing isolated points during coarsening according to the rows' density. The default is 0. If nnzrow > coarsen\_cut\_factor\*avg\_nnzrow, where avg\_nnzrow is the average number of nonzeros per row of the global matrix, holds for a given row, it is set as fine, and interpolation weights are not computed.

**3.6.4.95 HYPRE\_BoomerAMGSetCoarsenType()**

```
HYPRE_Int HYPRE_BoomerAMGSetCoarsenType (
    HYPRE_Solver solver,
    HYPRE_Int coarsen_type )
```

(Optional) Defines which parallel coarsening algorithm is used. There are the following options for *coarsen\_type*:

- 0 : CLJP-coarsening (a parallel coarsening algorithm using independent sets.
- 1 : classical Ruge-Stueben coarsening on each processor, no boundary treatment (not recommended!)
- 3 : classical Ruge-Stueben coarsening on each processor, followed by a third pass, which adds coarse points on the boundaries
- 6 : Falgout coarsening (uses 1 first, followed by CLJP using the interior coarse points generated by 1 as its first independent set)
- 7 : CLJP-coarsening (using a fixed random vector, for debugging purposes only)
- 8 : PMIS-coarsening (a parallel coarsening algorithm using independent sets, generating lower complexities than CLJP, might also lead to slower convergence)
- 9 : PMIS-coarsening (using a fixed random vector, for debugging purposes only)
- 10 : HMIS-coarsening (uses one pass Ruge-Stueben on each processor independently, followed by PMIS using the interior C-points generated as its first independent set)
- 11 : one-pass Ruge-Stueben coarsening on each processor, no boundary treatment (not recommended!)
- 21 : CGC coarsening by M. Griebel, B. Metsch and A. Schweitzer
- 22 : CGC-E coarsening by M. Griebel, B. Metsch and A. Schweitzer

The default is 10.

**3.6.4.96 HYPRE\_BoomerAMGSetConvergeType()**

```
HYPRE_Int HYPRE_BoomerAMGSetConvergeType (
    HYPRE_Solver solver,
    HYPRE_Int type )
```

(Optional) Set the type convergence checking 0: (default)  $\text{norm}(r)/\text{norm}(b)$ , or  $\text{norm}(r)$  when  $b == 0$  1:  $\text{nomr}(r) / \text{norm}(r_0)$

**3.6.4.97 HYPRE\_BoomerAMGSetCoordDim()**

```
HYPRE_Int HYPRE_BoomerAMGSetCoordDim (
    HYPRE_Solver solver,
    HYPRE_Int coorddim )
```

HYPRE\_BoomerAMGSetCoordDim

**3.6.4.98 HYPRE\_BoomerAMGSetCoordinates()**

```
HYPRE_Int HYPRE_BoomerAMGSetCoordinates (
    HYPRE_Solver solver,
    float * coordinates )
```

HYPRE\_BoomerAMGSetCoordinates

**3.6.4.99 HYPRE\_BoomerAMGSetCPoints()**

```
HYPRE_Int HYPRE_BoomerAMGSetCPoints (
    HYPRE_Solver solver,
    HYPRE_Int cpt_coarse_level,
    HYPRE_Int num_cpt_coarse,
    HYPRE_BigInt * cpt_coarse_index )
```

(Optional) Fix C points to be kept till a specified coarse level.

**Parameters**

<i>solver</i>	[IN] solver or preconditioner
<i>cpt_coarse_level</i>	[IN] coarse level up to which to keep C points
<i>num_cpt_coarse</i>	[IN] number of C points to be kept
<i>cpt_coarse_index</i>	[IN] indexes of C points to be kept

**3.6.4.100 HYPRE\_BoomerAMGSetCpointsToKeep()**

```
HYPRE_Int HYPRE_BoomerAMGSetCpointsToKeep (
    HYPRE_Solver solver,
    HYPRE_Int cpt_coarse_level,
    HYPRE_Int num_cpt_coarse,
    HYPRE_BigInt * cpt_coarse_index )
```

(Optional) Deprecated function. Use HYPRE\_BoomerAMGSetCPoints instead.

**3.6.4.101 HYPRE\_BoomerAMGSetCRRate()**

```
HYPRE_Int HYPRE_BoomerAMGSetCRRate (
    HYPRE_Solver solver,
    HYPRE_Real CR_rate )
```

**3.6.4.102 HYPRE\_BoomerAMGSetCRStrongTh()**

```
HYPRE_Int HYPRE_BoomerAMGSetCRStrongTh (
    HYPRE_Solver solver,
    HYPRE_Real CR_strong_th )
```



**3.6.4.103 HYPRE\_BoomerAMGSetCRUseCG()**

```
HYPRE_Int HYPRE_BoomerAMGSetCRUseCG (
    HYPRE_Solver solver,
    HYPRE_Int CR_use_CG )
```

**3.6.4.104 HYPRE\_BoomerAMGSetCycleNumSweeps()**

```
HYPRE_Int HYPRE_BoomerAMGSetCycleNumSweeps (
    HYPRE_Solver solver,
    HYPRE_Int num_sweeps,
    HYPRE_Int k )
```

(Optional) Sets the number of sweeps at a specified cycle. There are the following options for *k*:

- 1 : the down cycle
- 2 : the up cycle
- 3 : the coarsest level

**3.6.4.105 HYPRE\_BoomerAMGSetCycleRelaxType()**

```
HYPRE_Int HYPRE_BoomerAMGSetCycleRelaxType (
    HYPRE_Solver solver,
    HYPRE_Int relax_type,
    HYPRE_Int k )
```

(Optional) Defines the smoother at a given cycle. For options of *relax\_type* see description of HYPRE\_BoomerAMGSetRelaxType). Options for *k* are

- 1 : the down cycle
- 2 : the up cycle
- 3 : the coarsest level

**3.6.4.106 HYPRE\_BoomerAMGSetCycleType()**

```
HYPRE_Int HYPRE_BoomerAMGSetCycleType (
    HYPRE_Solver solver,
    HYPRE_Int cycle_type )
```

(Optional) Defines the type of cycle. For a V-cycle, set *cycle\_type* to 1, for a W-cycle set *cycle\_type* to 2. The default is 1.

**3.6.4.107 HYPRE\_BoomerAMGSetDebugFlag()**

```
HYPRE_Int HYPRE_BoomerAMGSetDebugFlag (
    HYPRE_Solver solver,
    HYPRE_Int debug_flag )
```

(Optional)

**3.6.4.108 HYPRE\_BoomerAMGSetDofFunc()**

```
HYPRE_Int HYPRE_BoomerAMGSetDofFunc (
    HYPRE_Solver solver,
    HYPRE_Int * dof_func )
```

(Optional) Sets the mapping that assigns the function to each variable, if using the systems version. If no assignment is made and the number of functions is  $k > 1$ , the mapping generated is  $(0, 1, \dots, k-1, 0, 1, \dots, k-1, \dots)$ .

**3.6.4.109 HYPRE\_BoomerAMGSetDomainType()**

```
HYPRE_Int HYPRE_BoomerAMGSetDomainType (
    HYPRE_Solver solver,
    HYPRE_Int domain_type )
```

(Optional) Defines the type of domain used for the Schwarz method. The following options exist for *domain\_type*:

- 0 : each point is a domain
- 1 : each node is a domain (only of interest in "systems" AMG)
- 2 : each domain is generated by agglomeration (default)

**3.6.4.110 HYPRE\_BoomerAMGSetDropTol()**

```
HYPRE_Int HYPRE_BoomerAMGSetDropTol (
    HYPRE_Solver solver,
    HYPRE_Real drop_tol )
```

(Optional) Defines drop tolerance for PILUT. For further explanation see description of PILUT.

**3.6.4.111 HYPRE\_BoomerAMGSetEuBJ()**

```
HYPRE_Int HYPRE_BoomerAMGSetEuBJ (
    HYPRE_Solver solver,
    HYPRE_Int eu_bj )
```

(Optional) Defines use of block jacobi ILUT for Euclid. For further explanation see description of Euclid.

**3.6.4.112 HYPRE\_BoomerAMGSetEuclidFile()**

```
HYPRE_Int HYPRE_BoomerAMGSetEuclidFile (
    HYPRE_Solver solver,
    char * euclidfile )
```

(Optional) Defines name of an input file for Euclid parameters. For further explanation see description of Euclid.

**3.6.4.113 HYPRE\_BoomerAMGSetEuLevel()**

```
HYPRE_Int HYPRE_BoomerAMGSetEuLevel (
    HYPRE_Solver solver,
    HYPRE_Int eu_level )
```

(Optional) Defines number of levels for ILU(k) in Euclid. For further explanation see description of Euclid.

**3.6.4.114 HYPRE\_BoomerAMGSetEuSparseA()**

```
HYPRE_Int HYPRE_BoomerAMGSetEuSparseA (
    HYPRE_Solver solver,
    HYPRE_Real eu_sparse_A )
```

(Optional) Defines filter for ILU(k) for Euclid. For further explanation see description of Euclid.

**3.6.4.115 HYPRE\_BoomerAMGSetFCycle()**

```
HYPRE_Int HYPRE_BoomerAMGSetFCycle (
    HYPRE_Solver solver,
    HYPRE_Int fcycle )
```

(Optional) Specifies the use of Full multigrid cycle. The default is 0.

**3.6.4.116 HYPRE\_BoomerAMGSetFilter()**

```
HYPRE_Int HYPRE_BoomerAMGSetFilter (
    HYPRE_Solver solver,
    HYPRE_Real filter )
```

(Optional) Defines filter for ParaSAILS. For further explanation see description of ParaSAILS.

**3.6.4.117 HYPRE\_BoomerAMGSetFilterThresholdR()**

```
HYPRE_Int HYPRE_BoomerAMGSetFilterThresholdR (
    HYPRE_Solver solver,
    HYPRE_Real filter_threshold )
```

(Optional) The filter threshold for R is used to eliminate small entries of the approximate ideal restriction after building it. Default value is 0.0, which disables filtering.

**3.6.4.118 HYPRE\_BoomerAMGSetFPoints()**

```
HYPRE_Int HYPRE_BoomerAMGSetFPoints (
    HYPRE_Solver solver,
    HYPRE_Int num_fpt,
    HYPRE_BigInt * fpt_index )
```

(Optional) Set fine points in the first level.

## Parameters

<i>solver</i>	[IN] solver or preconditioner
<i>num_fpt</i>	[IN] number of fine points
<i>fpt_index</i>	[IN] global indices of fine points

**3.6.4.119 HYPRE\_BoomerAMGSetGMRESSwitchR()**

```
HYPRE_Int HYPRE_BoomerAMGSetGMRESSwitchR (
    HYPRE_Solver solver,
    HYPRE_Int gmres_switch )
```

(Optional) Set local problem size at which GMRES is used over a direct solve in approximating ideal restriction. The default is 0.

**3.6.4.120 HYPRE\_BoomerAMGSetGridRelaxPoints()**

```
HYPRE_Int HYPRE_BoomerAMGSetGridRelaxPoints (
    HYPRE_Solver solver,
    HYPRE_Int ** grid_relax_points )
```

(Optional) Defines in which order the points are relaxed.

Note: This routine will be phased out!!!! Use HYPRE\_BoomerAMGSetRelaxOrder instead.

**3.6.4.121 HYPRE\_BoomerAMGSetGridRelaxType()**

```
HYPRE_Int HYPRE_BoomerAMGSetGridRelaxType (
    HYPRE_Solver solver,
    HYPRE_Int * grid_relax_type )
```

(Optional) Defines which smoother is used on the fine and coarse grid, the up and down cycle.

Note: This routine will be phased out!!!! Use HYPRE\_BoomerAMGSetRelaxType or HYPRE\_BoomerAMGSet↔CycleRelaxType instead.

**3.6.4.122 HYPRE\_BoomerAMGSetGSMG()**

```
HYPRE_Int HYPRE_BoomerAMGSetGSMG (
    HYPRE_Solver solver,
    HYPRE_Int gsmg )
```

(Optional) Specifies the use of GSMG - geometrically smooth coarsening and interpolation. Currently any nonzero value for gsmg will lead to the use of GSMG. The default is 0, i.e. (GSMG is not used)

**3.6.4.123 HYPRE\_BoomerAMGSetILUDroptol()**

```
HYPRE_Int HYPRE_BoomerAMGSetILUDroptol (
    HYPRE_Solver solver,
    HYPRE_Real ilu_droptol )
```

Defines drop tolerance for iLUT smoother For further explanation see description of ILU.

**3.6.4.124 HYPRE\_BoomerAMGSetILULevel()**

```
HYPRE_Int HYPRE_BoomerAMGSetILULevel (
    HYPRE_Solver solver,
    HYPRE_Int ilu_lfil )
```

Defines level k for ILU(k) smoother For further explanation see description of ILU.

**3.6.4.125 HYPRE\_BoomerAMGSetILUMaxIter()**

```
HYPRE_Int HYPRE_BoomerAMGSetILUMaxIter (
    HYPRE_Solver solver,
    HYPRE_Int ilu_max_iter )
```

Defines number of iterations for ILU smoother on each level For further explanation see description of ILU.

**3.6.4.126 HYPRE\_BoomerAMGSetILUMaxRowNnz()**

```
HYPRE_Int HYPRE_BoomerAMGSetILUMaxRowNnz (
    HYPRE_Solver solver,
    HYPRE_Int ilu_max_row_nnz )
```

Defines max row nonzeros for ILUT smoother For further explanation see description of ILU.

**3.6.4.127 HYPRE\_BoomerAMGSetILUType()**

```
HYPRE_Int HYPRE_BoomerAMGSetILUType (
    HYPRE_Solver solver,
    HYPRE_Int ilu_type )
```

Defines type of ILU smoother to use For further explanation see description of ILU.

### 3.6.4.128 HYPRE\_BoomerAMGSetInterpType()

```
HYPRE_Int HYPRE_BoomerAMGSetInterpType (
    HYPRE_Solver solver,
    HYPRE_Int interp_type )
```

(Optional) Defines which parallel interpolation operator is used. There are the following options for *interp\_type*:

- 0 : classical modified interpolation
- 1 : LS interpolation (for use with GSMG)
- 2 : classical modified interpolation for hyperbolic PDEs
- 3 : direct interpolation (with separation of weights) (also for GPU use)
- 4 : multipass interpolation
- 5 : multipass interpolation (with separation of weights)
- 6 : extended+i interpolation (also for GPU use)
- 7 : extended+i (if no common C neighbor) interpolation
- 8 : standard interpolation
- 9 : standard interpolation (with separation of weights)
- 10 : classical block interpolation (for use with nodal systems version only)
- 11 : classical block interpolation (for use with nodal systems version only) with diagonalized diagonal blocks
- 12 : FF interpolation
- 13 : FF1 interpolation
- 14 : extended interpolation (also for GPU use)
- 15 : interpolation with adaptive weights (GPU use only)
- 16 : extended interpolation in matrix-matrix form
- 17 : extended+i interpolation in matrix-matrix form
- 18 : extended+e interpolation in matrix-matrix form

The default is ext+i interpolation (interp\_type 6) truncated to at most 4 elements per row. (see HYPRE\_BoomerAMGSetPMaxElmts).

### 3.6.4.129 HYPRE\_BoomerAMGSetInterpVecAbsQTrunc()

```
HYPRE_Int HYPRE_BoomerAMGSetInterpVecAbsQTrunc (
    HYPRE_Solver solver,
    HYPRE_Real q_trunc )
```

(Optional) Defines a truncation factor for Q, the additional columns added to the original interpolation matrix P, to reduce complexity. The default is no truncation.

**3.6.4.130 HYPRE\_BoomerAMGSetInterpVecQMax()**

```
HYPRE_Int HYPRE_BoomerAMGSetInterpVecQMax (
    HYPRE_Solver solver,
    HYPRE_Int q_max )
```

(Optional) Defines the maximal elements per row for Q, the additional columns added to the original interpolation matrix P, to reduce complexity. The default is no truncation.

**3.6.4.131 HYPRE\_BoomerAMGSetInterpVectors()**

```
HYPRE_Int HYPRE_BoomerAMGSetInterpVectors (
    HYPRE_Solver solver,
    HYPRE_Int num_vectors,
    HYPRE_ParVector * interp_vectors )
```

(Optional) Allows the user to incorporate additional vectors into the interpolation for systems AMG, e.g. rigid body modes for linear elasticity problems. This can only be used in context with nodal coarsening and still requires the user to choose an interpolation.

**3.6.4.132 HYPRE\_BoomerAMGSetInterpVecVariant()**

```
HYPRE_Int HYPRE_BoomerAMGSetInterpVecVariant (
    HYPRE_Solver solver,
    HYPRE_Int var )
```

(Optional) Defines the interpolation variant used for HYPRE\_BoomerAMGSetInterpVectors:

- 1 : GM approach 1
- 2 : GM approach 2 (to be preferred over 1)
- 3 : LN approach

**3.6.4.133 HYPRE\_BoomerAMGSetIsolatedFPoints()**

```
HYPRE_Int HYPRE_BoomerAMGSetIsolatedFPoints (
    HYPRE_Solver solver,
    HYPRE_Int num_isolated_fpt,
    HYPRE_BigInt * isolated_fpt_index )
```

(Optional) Set isolated fine points in the first level. Interpolation weights are not computed for these points.

**Parameters**

<i>solver</i>	[IN] solver or preconditioner
<i>num_isolated_fpt</i>	[IN] number of isolated fine points
<i>isolated_fpt_index</i>	[IN] global indices of isolated fine points

**3.6.4.134 HYPRE\_BoomerAMGSetIsTriangular()**

```
HYPRE_Int HYPRE_BoomerAMGSetIsTriangular (
    HYPRE_Solver solver,
    HYPRE_Int is_triangular )
```

(Optional) Assumes the matrix is triangular in some ordering to speed up the setup time of approximate ideal restriction.

The default is 0.

**3.6.4.135 HYPRE\_BoomerAMGSetISType()**

```
HYPRE_Int HYPRE_BoomerAMGSetISType (
    HYPRE_Solver solver,
    HYPRE_Int IS_type )
```

**3.6.4.136 HYPRE\_BoomerAMGSetJacobiTruncThreshold()**

```
HYPRE_Int HYPRE_BoomerAMGSetJacobiTruncThreshold (
    HYPRE_Solver solver,
    HYPRE_Real jacobi_trunc_threshold )
```

**3.6.4.137 HYPRE\_BoomerAMGSetKeepSameSign()**

```
HYPRE_Int HYPRE_BoomerAMGSetKeepSameSign (
    HYPRE_Solver solver,
    HYPRE_Int keep_same_sign )
```

**3.6.4.138 HYPRE\_BoomerAMGSetKeepTranspose()**

```
HYPRE_Int HYPRE_BoomerAMGSetKeepTranspose (
    HYPRE_Solver solver,
    HYPRE_Int keepTranspose )
```

(Optional) If set to 1, the local interpolation transposes will be saved to use more efficient matvecs instead of matvecTs (Recommended for efficient use on GPUs)

**3.6.4.139 HYPRE\_BoomerAMGSetLevel()**

```
HYPRE_Int HYPRE_BoomerAMGSetLevel (
    HYPRE_Solver solver,
    HYPRE_Int level )
```

(Optional) Defines number of levels for ParaSAILS. For further explanation see description of ParaSAILS.



**3.6.4.140 HYPRE\_BoomerAMGSetLevelNonGalerkinTol()**

```

HYPRE_Int HYPRE_BoomerAMGSetLevelNonGalerkinTol (
    HYPRE_Solver solver,
    HYPRE_Real nongalerkin_tol,
    HYPRE_Int level )

```

(Optional) Defines the level specific non-Galerkin drop-tolerances for sparsifying coarse grid operators and thus reducing communication. A drop-tolerance of 0.0 means to skip doing non-Galerkin on that level. The maximum drop tolerance for a level is 1.0, although much smaller values such as 0.03 or 0.01 are recommended.

Note that if the user wants to set a specific tolerance on all levels, HYPRE\_BoomerAMGSetNonGalerkinTol should be used. Individual levels can then be changed using this routine.

In general, it is safer to drop more aggressively on coarser levels. For instance, one could use 0.0 on the finest level, 0.01 on the second level and then using 0.05 on all remaining levels. The best way to achieve this is to set 0.05 on all levels with HYPRE\_BoomerAMGSetNonGalerkinTol and then change the tolerance on level 0 to 0.0 and the tolerance on level 1 to 0.01 with HYPRE\_BoomerAMGSetLevelNonGalerkinTol. Like many AMG parameters, these drop tolerances can be tuned. It is also common to delay the start of the non-Galerkin process further to a later level than level 1.

**Parameters**

<i>solver</i>	[IN] solver or preconditioner object to be applied.
<i>nongalerkin_tol</i>	[IN] level specific drop tolerance
<i>level</i>	[IN] level on which drop tolerance is used

**3.6.4.141 HYPRE\_BoomerAMGSetLevelOuterWt()**

```

HYPRE_Int HYPRE_BoomerAMGSetLevelOuterWt (
    HYPRE_Solver solver,
    HYPRE_Real omega,
    HYPRE_Int level )

```

(Optional) Defines the outer relaxation weight for hybrid SOR or SSOR on the user defined level. Note that the finest level is denoted 0, the next coarser level 1, etc. For nonpositive omega, the parameter is determined on the given level as described for HYPRE\_BoomerAMGSetOuterWt. The default is 1.

**3.6.4.142 HYPRE\_BoomerAMGSetLevelRelaxWt()**

```

HYPRE_Int HYPRE_BoomerAMGSetLevelRelaxWt (
    HYPRE_Solver solver,
    HYPRE_Real relax_weight,
    HYPRE_Int level )

```

(Optional) Defines the relaxation weight for smoothed Jacobi and hybrid SOR on the user defined level. Note that the finest level is denoted 0, the next coarser level 1, etc. For nonpositive *relax\_weight*, the parameter is determined on the given level as described for HYPRE\_BoomerAMGSetRelaxWt. The default is 1.

**3.6.4.143 HYPRE\_BoomerAMGSetLogging()**

```
HYPRE_Int HYPRE_BoomerAMGSetLogging (
    HYPRE_Solver solver,
    HYPRE_Int logging )
```

(Optional) Requests additional computations for diagnostic and similar data to be logged by the user. Default to 0 for do nothing. The latest residual will be available if logging > 1.

**3.6.4.144 HYPRE\_BoomerAMGSetMaxCoarseSize()**

```
HYPRE_Int HYPRE_BoomerAMGSetMaxCoarseSize (
    HYPRE_Solver solver,
    HYPRE_Int max_coarse_size )
```

(Optional) Sets maximum size of coarsest grid. The default is 9.

**3.6.4.145 HYPRE\_BoomerAMGSetMaxIter()**

```
HYPRE_Int HYPRE_BoomerAMGSetMaxIter (
    HYPRE_Solver solver,
    HYPRE_Int max_iter )
```

(Optional) Sets maximum number of iterations, if BoomerAMG is used as a solver. If it is used as a preconditioner, it should be set to 1. The default is 20.

**3.6.4.146 HYPRE\_BoomerAMGSetMaxLevels()**

```
HYPRE_Int HYPRE_BoomerAMGSetMaxLevels (
    HYPRE_Solver solver,
    HYPRE_Int max_levels )
```

(Optional) Sets maximum number of multigrid levels. The default is 25.

**3.6.4.147 HYPRE\_BoomerAMGSetMaxNzPerRow()**

```
HYPRE_Int HYPRE_BoomerAMGSetMaxNzPerRow (
    HYPRE_Solver solver,
    HYPRE_Int max_nz_per_row )
```

(Optional) Defines maximal number of nonzeros for PILUT. For further explanation see description of PILUT.

**3.6.4.148 HYPRE\_BoomerAMGSetMaxRowSum()**

```
HYPRE_Int HYPRE_BoomerAMGSetMaxRowSum (
    HYPRE_Solver solver,
    HYPRE_Real max_row_sum )
```

(Optional) Sets a parameter to modify the definition of strength for diagonal dominant portions of the matrix. The default is 0.9. If *max\_row\_sum* is 1, no checking for diagonally dominant rows is performed.

**3.6.4.149 HYPRE\_BoomerAMGSetMeasureType()**

```
HYPRE_Int HYPRE_BoomerAMGSetMeasureType (
    HYPRE_Solver solver,
    HYPRE_Int measure_type )
```

(Optional) Defines whether local or global measures are used.

**3.6.4.150 HYPRE\_BoomerAMGSetMinCoarseSize()**

```
HYPRE_Int HYPRE_BoomerAMGSetMinCoarseSize (
    HYPRE_Solver solver,
    HYPRE_Int min_coarse_size )
```

(Optional) Sets minimum size of coarsest grid. The default is 1.

**3.6.4.151 HYPRE\_BoomerAMGSetMinIter()**

```
HYPRE_Int HYPRE_BoomerAMGSetMinIter (
    HYPRE_Solver solver,
    HYPRE_Int min_iter )
```

(Optional)

**3.6.4.152 HYPRE\_BoomerAMGSetModuleRAP2()**

```
HYPRE_Int HYPRE_BoomerAMGSetModuleRAP2 (
    HYPRE_Solver solver,
    HYPRE_Int mod_rap2 )
```

(Optional) If mod\_rap2 not equal 0, the triple matrix product RAP is replaced by two matrix products with modularized kernels (Required for triple matrix product generation on GPUs)

**3.6.4.153 HYPRE\_BoomerAMGSetMultAdditive()**

```
HYPRE_Int HYPRE_BoomerAMGSetMultAdditive (
    HYPRE_Solver solver,
    HYPRE_Int addlvl )
```

(Optional) Defines use of an additive V(1,1)-cycle using the mult-additive method starting at level 'addlvl'. The multiplicative approach is used on levels 0, ...'addlvl+1'. 'addlvl' needs to be  $> -1$  for this to have an effect. Can only be used with weighted Jacobi and I1-Jacobi(default).

Can only be used when AMG is used as a preconditioner !!!

**3.6.4.154 HYPRE\_BoomerAMGSetMultAddPMaxElmts()**

```
HYPRE_Int HYPRE_BoomerAMGSetMultAddPMaxElmts (
    HYPRE_Solver solver,
    HYPRE_Int add_P_max_elmts )
```

(Optional) Defines the maximal number of elements per row for the smoothed interpolation used for mult-additive or simple method. The default is 0.

**3.6.4.155 HYPRE\_BoomerAMGSetMultAddTruncFactor()**

```
HYPRE_Int HYPRE_BoomerAMGSetMultAddTruncFactor (
    HYPRE_Solver solver,
    HYPRE_Real add_trunc_factor )
```

(Optional) Defines the truncation factor for the smoothed interpolation used for mult-additive or simple method. The default is 0.

**3.6.4.156 HYPRE\_BoomerAMGSetNodal()**

```
HYPRE_Int HYPRE_BoomerAMGSetNodal (
    HYPRE_Solver solver,
    HYPRE_Int nodal )
```

(Optional) Sets whether to use the nodal systems coarsening. Should be used for linear systems generated from systems of PDEs. The default is 0 (unknown-based coarsening, only coarsens within same function). For the remaining options a nodal matrix is generated by applying a norm to the nodal blocks and applying the coarsening algorithm to this matrix.

- 1 : Frobenius norm
- 2 : sum of absolute values of elements in each block
- 3 : largest element in each block (not absolute value)
- 4 : row-sum norm
- 6 : sum of all values in each block

**3.6.4.157 HYPRE\_BoomerAMGSetNodalDiag()**

```
HYPRE_Int HYPRE_BoomerAMGSetNodalDiag (
    HYPRE_Solver solver,
    HYPRE_Int nodal_diag )
```

(Optional) Sets whether to give special treatment to diagonal elements in the nodal systems version. The default is 0. If set to 1, the diagonal entry is set to the negative sum of all off diagonal entries. If set to 2, the signs of all diagonal entries are inverted.

**3.6.4.158 HYPRE\_BoomerAMGSetNonGalerkinTol()**

```
HYPRE_Int HYPRE_BoomerAMGSetNonGalerkinTol (
    HYPRE_Solver solver,
    HYPRE_Real nongalerkin_tol )
```

(Optional) Defines the non-Galerkin drop-tolerance for sparsifying coarse grid operators and thus reducing communication. Value specified here is set on all levels. This routine should be used before HYPRE\_BoomerAMGSetLevelNonGalerkinTol, which then can be used to change individual levels if desired

**3.6.4.159 HYPRE\_BoomerAMGSetNonGalerkTol()**

```
HYPRE_Int HYPRE_BoomerAMGSetNonGalerkTol (
    HYPRE_Solver solver,
    HYPRE_Int nongalerk_num_tol,
    HYPRE_Real * nongalerk_tol )
```

(Optional) Defines the non-Galerkin drop-tolerance (old version)

**3.6.4.160 HYPRE\_BoomerAMGSetNumCRRelaxSteps()**

```
HYPRE_Int HYPRE_BoomerAMGSetNumCRRelaxSteps (
    HYPRE_Solver solver,
    HYPRE_Int num_CR_relax_steps )
```

**3.6.4.161 HYPRE\_BoomerAMGSetNumFunctions()**

```
HYPRE_Int HYPRE_BoomerAMGSetNumFunctions (
    HYPRE_Solver solver,
    HYPRE_Int num_functions )
```

(Optional) Sets the size of the system of PDEs, if using the systems version. The default is 1, i.e. a scalar system.

**3.6.4.162 HYPRE\_BoomerAMGSetNumGridSweeps()**

```
HYPRE_Int HYPRE_BoomerAMGSetNumGridSweeps (
    HYPRE_Solver solver,
    HYPRE_Int * num_grid_sweeps )
```

(Optional) Defines the number of sweeps for the fine and coarse grid, the up and down cycle.

Note: This routine will be phased out!!!! Use HYPRE\_BoomerAMGSetNumSweeps or HYPRE\_BoomerAMGSet↔CycleNumSweeps instead.

**3.6.4.163 HYPRE\_BoomerAMGSetNumPaths()**

```
HYPRE_Int HYPRE_BoomerAMGSetNumPaths (
    HYPRE_Solver solver,
    HYPRE_Int num_paths )
```

(Optional) Defines the degree of aggressive coarsening. The default is 1. Larger numbers lead to less aggressive coarsening.

**3.6.4.164 HYPRE\_BoomerAMGSetNumSamples()**

```
HYPRE_Int HYPRE_BoomerAMGSetNumSamples (
    HYPRE_Solver solver,
    HYPRE_Int num_samples )
```

(Optional) Defines the number of sample vectors used in GSMG or LS interpolation.

**3.6.4.165 HYPRE\_BoomerAMGSetNumSweeps()**

```
HYPRE_Int HYPRE_BoomerAMGSetNumSweeps (
    HYPRE_Solver solver,
    HYPRE_Int num_sweeps )
```

(Optional) Sets the number of sweeps. On the finest level, the up and the down cycle the number of sweeps are set to *num\_sweeps* and on the coarsest level to 1. The default is 1.

**3.6.4.166 HYPRE\_BoomerAMGSetOldDefault()**

```
HYPRE_Int HYPRE_BoomerAMGSetOldDefault (
    HYPRE_Solver solver )
```

Recovers old default for coarsening and interpolation, i.e. Falgout coarsening and untruncated modified classical interpolation. This option might be preferred for 2 dimensional problems.

**3.6.4.167 HYPRE\_BoomerAMGSetOmega()**

```
HYPRE_Int HYPRE_BoomerAMGSetOmega (
    HYPRE_Solver solver,
    HYPRE_Real * omega )
```

(Optional) Defines the outer relaxation weight for hybrid SOR. Note: This routine will be phased out!!!! Use HYPRE\_BoomerAMGSetOuterWt or HYPRE\_BoomerAMGSetLevelOuterWt instead.

**3.6.4.168 HYPRE\_BoomerAMGSetOuterWt()**

```
HYPRE_Int HYPRE_BoomerAMGSetOuterWt (
    HYPRE_Solver solver,
    HYPRE_Real omega )
```

(Optional) Defines the outer relaxation weight for hybrid SOR and SSOR on all levels.

Values for *omega* are

- $> 0$  : this assigns the same outer relaxation weight *omega* on each level
- $= -k$  : an outer relaxation weight is determined with at most *k* CG steps on each level (this only makes sense for symmetric positive definite problems and smoothers such as SSOR)

The default is 1.

**3.6.4.169 HYPRE\_BoomerAMGSetOverlap()**

```
HYPRE_Int HYPRE_BoomerAMGSetOverlap (
    HYPRE_Solver solver,
    HYPRE_Int overlap )
```

(Optional) Defines the overlap for the Schwarz method. The following options exist for overlap:

- 0 : no overlap
- 1 : minimal overlap (default)
- 2 : overlap generated by including all neighbors of domain boundaries

**3.6.4.170 HYPRE\_BoomerAMGSetPlotFileName()**

```
HYPRE_Int HYPRE_BoomerAMGSetPlotFileName (
    HYPRE_Solver solver,
    const char * plotfilename )
```

HYPRE\_BoomerAMGSetPlotFilename

**3.6.4.171 HYPRE\_BoomerAMGSetPlotGrids()**

```
HYPRE_Int HYPRE_BoomerAMGSetPlotGrids (
    HYPRE_Solver solver,
    HYPRE_Int plotgrids )
```

HYPRE\_BoomerAMGSetPlotGrids

**3.6.4.172 HYPRE\_BoomerAMGSetPMaxElmts()**

```
HYPRE_Int HYPRE_BoomerAMGSetPMaxElmts (
    HYPRE_Solver solver,
    HYPRE_Int P_max_elmts )
```

(Optional) Defines the maximal number of elements per row for the interpolation. The default is 4. To turn off truncation, it needs to be set to 0.

**3.6.4.173 HYPRE\_BoomerAMGSetPostInterpType()**

```
HYPRE_Int HYPRE_BoomerAMGSetPostInterpType (
    HYPRE_Solver solver,
    HYPRE_Int post_interp_type )
```

**3.6.4.174 HYPRE\_BoomerAMGSetPrintFileName()**

```
HYPRE_Int HYPRE_BoomerAMGSetPrintFileName (
    HYPRE_Solver solver,
    const char * print_file_name )
```

(Optional) Name of file to which BoomerAMG will print; cf HYPRE\_BoomerAMGSetPrintLevel. (Presently this is ignored).

**3.6.4.175 HYPRE\_BoomerAMGSetPrintLevel()**

```
HYPRE_Int HYPRE_BoomerAMGSetPrintLevel (
    HYPRE_Solver solver,
    HYPRE_Int print_level )
```

(Optional) Requests automatic printing of setup and solve information.

- 0 : no printout (default)
- 1 : print setup information
- 2 : print solve information
- 3 : print both setup and solve information

Note, that if one desires to print information and uses BoomerAMG as a preconditioner, suggested *print\_level* is 1 to avoid excessive output, and use *print\_level* of solver for solve phase information.

### 3.6.4.176 HYPRE\_BoomerAMGSetRAP2()

```
HYPRE_Int HYPRE_BoomerAMGSetRAP2 (
    HYPRE_Solver solver,
    HYPRE_Int rap2 )
```

(Optional) If rap2 not equal 0, the triple matrix product RAP is replaced by two matrix products. (Required for triple matrix product generation on GPUs)

### 3.6.4.177 HYPRE\_BoomerAMGSetRedundant()

```
HYPRE_Int HYPRE_BoomerAMGSetRedundant (
    HYPRE_Solver solver,
    HYPRE_Int redundant )
```

(Optional) operates switch for redundancy. Needs to be used with HYPRE\_BoomerAMGSetSeqThreshold. Default is 0, i.e. no redundancy.

### 3.6.4.178 HYPRE\_BoomerAMGSetRelaxOrder()

```
HYPRE_Int HYPRE_BoomerAMGSetRelaxOrder (
    HYPRE_Solver solver,
    HYPRE_Int relax_order )
```

(Optional) Defines in which order the points are relaxed. There are the following options for *relax\_order*:

- 0 : the points are relaxed in natural or lexicographic order on each processor
- 1 : CF-relaxation is used, i.e on the fine grid and the down cycle the coarse points are relaxed first, followed by the fine points; on the up cycle the F-points are relaxed first, followed by the C-points. On the coarsest level, if an iterative scheme is used, the points are relaxed in lexicographic order.

The default is 0.

### 3.6.4.179 HYPRE\_BoomerAMGSetRelaxType()

```
HYPRE_Int HYPRE_BoomerAMGSetRelaxType (
    HYPRE_Solver solver,
    HYPRE_Int relax_type )
```

(Optional) Defines the smoother to be used. It uses the given smoother on the fine grid, the up and the down cycle and sets the solver on the coarsest level to Gaussian elimination (9). The default is  $\ell_1$ -Gauss-Seidel, forward solve (13) on the down cycle and backward solve (14) on the up cycle.

There are the following options for *relax\_type*:

- 0 : Jacobi
- 1 : Gauss-Seidel, sequential (very slow!)
- 2 : Gauss-Seidel, interior points in parallel, boundary sequential (slow!)



- 3 : hybrid Gauss-Seidel or SOR, forward solve
- 4 : hybrid Gauss-Seidel or SOR, backward solve
- 5 : hybrid chaotic Gauss-Seidel (works only with OpenMP)
- 6 : hybrid symmetric Gauss-Seidel or SSOR
- 8 :  $\ell_1$ -scaled hybrid symmetric Gauss-Seidel
- 9 : Gaussian elimination (only on coarsest level)
- 13 :  $\ell_1$  Gauss-Seidel, forward solve
- 14 :  $\ell_1$  Gauss-Seidel, backward solve
- 15 : CG (warning - not a fixed smoother - may require FGMRES)
- 16 : Chebyshev
- 17 : FCF-Jacobi
- 18 :  $\ell_1$ -scaled jacobi

#### 3.6.4.180 HYPRE\_BoomerAMGSetRelaxWeight()

```
HYPRE_Int HYPRE_BoomerAMGSetRelaxWeight (
    HYPRE_Solver solver,
    HYPRE_Real * relax_weight )
```

(Optional) Defines the relaxation weight for smoothed Jacobi and hybrid SOR.

Note: This routine will be phased out!!!! Use HYPRE\_BoomerAMGSetRelaxWt or HYPRE\_BoomerAMGSetLevel↔RelaxWt instead.

#### 3.6.4.181 HYPRE\_BoomerAMGSetRelaxWt()

```
HYPRE_Int HYPRE_BoomerAMGSetRelaxWt (
    HYPRE_Solver solver,
    HYPRE_Real relax_weight )
```

(Optional) Defines the relaxation weight for smoothed Jacobi and hybrid SOR on all levels.

Values for *relax\_weight* are

- $> 0$  : this assigns the given relaxation weight on all levels
- $= 0$  : the weight is determined on each level with the estimate  $\frac{3}{4\|D^{-1/2}AD^{-1/2}\|}$ , where  $D$  is the diagonal of  $A$  (this should only be used with Jacobi)
- $= -k$  : the relaxation weight is determined with at most  $k$  CG steps on each level (this should only be used for symmetric positive definite problems)

The default is 1.

**3.6.4.182 HYPRE\_BoomerAMGSetRestriction()**

```
HYPRE_Int HYPRE_BoomerAMGSetRestriction (
    HYPRE_Solver solver,
    HYPRE_Int restr_par )
```

(Optional) Defines which parallel restriction operator is used. There are the following options for `restr_type`:

- 0 :  $P^T$  - Transpose of the interpolation operator
- 1 : AIR-1 - Approximate Ideal Restriction (distance 1)
- 2 : AIR-2 - Approximate Ideal Restriction (distance 2)

The default is 0.

**3.6.4.183 HYPRE\_BoomerAMGSetSabs()**

```
HYPRE_Int HYPRE_BoomerAMGSetSabs (
    HYPRE_Solver solver,
    HYPRE_Int Sabs )
```

(Optional) if `Sabs` equals 1, the strength of connection test is based on the absolute value of the matrix coefficients

**3.6.4.184 HYPRE\_BoomerAMGSetSchwarzRlxWeight()**

```
HYPRE_Int HYPRE_BoomerAMGSetSchwarzRlxWeight (
    HYPRE_Solver solver,
    HYPRE_Real schwarz_rlx_weight )
```

(Optional) Defines a smoothing parameter for the additive Schwarz method.

**3.6.4.185 HYPRE\_BoomerAMGSetSchwarzUseNonSymm()**

```
HYPRE_Int HYPRE_BoomerAMGSetSchwarzUseNonSymm (
    HYPRE_Solver solver,
    HYPRE_Int use_nonsymm )
```

(Optional) Indicates that the aggregates may not be SPD for the Schwarz method. The following options exist for `use_nonsymm`:

- 0 : assume SPD (default)
- 1 : assume non-symmetric

**3.6.4.186 HYPRE\_BoomerAMGSetSCommPkgSwitch()**

```
HYPRE_Int HYPRE_BoomerAMGSetSCommPkgSwitch (
    HYPRE_Solver solver,
    HYPRE_Real S_commpkg_switch )
```

(Optional) Deprecated. This routine now has no effect.

**3.6.4.187 HYPRE\_BoomerAMGSetSepWeight()**

```
HYPRE_Int HYPRE_BoomerAMGSetSepWeight (
    HYPRE_Solver solver,
    HYPRE_Int sep_weight )
```

(Optional) Defines whether separation of weights is used when defining strength for standard interpolation or multi-pass interpolation. Default: 0, i.e. no separation of weights used.

**3.6.4.188 HYPRE\_BoomerAMGSetSeqThreshold()**

```
HYPRE_Int HYPRE_BoomerAMGSetSeqThreshold (
    HYPRE_Solver solver,
    HYPRE_Int seq_threshold )
```

(Optional) Sets maximal size for agglomeration or redundant coarse grid solve. When the system is smaller than this threshold, sequential AMG is used on process 0 or on all remaining active processes (if redundant = 1 ).

**3.6.4.189 HYPRE\_BoomerAMGSetSimple()**

```
HYPRE_Int HYPRE_BoomerAMGSetSimple (
    HYPRE_Solver solver,
    HYPRE_Int addlvl )
```

(Optional) Defines use of an additive V(1,1)-cycle using the simplified mult-additive method starting at level 'addlvl'. The multiplicative approach is used on levels 0, ...'addlvl'+1'. 'addlvl' needs to be > -1 for this to have an effect. Can only be used with weighted Jacobi and I1-Jacobi(default).

Can only be used when AMG is used as a preconditioner !!!

**3.6.4.190 HYPRE\_BoomerAMGSetSmoothNumLevels()**

```
HYPRE_Int HYPRE_BoomerAMGSetSmoothNumLevels (
    HYPRE_Solver solver,
    HYPRE_Int smooth_num_levels )
```

(Optional) Sets the number of levels for more complex smoothers. The smoothers, as defined by HYPRE\_BoomerAMGSetSmoothType, will be used on level 0 (the finest level) through level *smooth\_num\_levels-1*. The default is 0, i.e. no complex smoothers are used.

**3.6.4.191 HYPRE\_BoomerAMGSetSmoothNumSweeps()**

```
HYPRE_Int HYPRE_BoomerAMGSetSmoothNumSweeps (
    HYPRE_Solver solver,
    HYPRE_Int smooth_num_sweeps )
```

(Optional) Sets the number of sweeps for more complex smoothers. The default is 1.

**3.6.4.192 HYPRE\_BoomerAMGSetSmoothType()**

```
HYPRE_Int HYPRE_BoomerAMGSetSmoothType (
    HYPRE_Solver solver,
    HYPRE_Int smooth_type )
```

(Optional) Enables the use of more complex smoothers. The following options exist for *smooth\_type*:

- 6 : Schwarz (routines needed to set: HYPRE\_BoomerAMGSetDomainType, HYPRE\_BoomerAMGSetOverlap, HYPRE\_BoomerAMGSetVariant, HYPRE\_BoomerAMGSetSchwarzRlxWeight)
- 7 : Pilut (routines needed to set: HYPRE\_BoomerAMGSetDropTol, HYPRE\_BoomerAMGSetMaxNzPerRow)
- 8 : ParaSails (routines needed to set: HYPRE\_BoomerAMGSetSym, HYPRE\_BoomerAMGSetLevel, HYPRE\_BoomerAMGSetFilter, HYPRE\_BoomerAMGSetThreshold)
- 9 : Euclid (routines needed to set: HYPRE\_BoomerAMGSetEuclidFile)
- 5 : ParILUK (routines needed to set: HYPRE\_ILUSetLevelOfFill, HYPRE\_ILUSetType)

The default is 6. Also, if no smoother parameters are set via the routines mentioned in the table above, default values are used.

**3.6.4.193 HYPRE\_BoomerAMGSetStrongThreshold()**

```
HYPRE_Int HYPRE_BoomerAMGSetStrongThreshold (
    HYPRE_Solver solver,
    HYPRE_Real strong_threshold )
```

(Optional) Sets AMG strength threshold. The default is 0.25. For 2D Laplace operators, 0.25 is a good value, for 3D Laplace operators, 0.5 or 0.6 is a better value. For elasticity problems, a large strength threshold, such as 0.9, is often better.

**3.6.4.194 HYPRE\_BoomerAMGSetStrongThresholdR()**

```
HYPRE_Int HYPRE_BoomerAMGSetStrongThresholdR (
    HYPRE_Solver solver,
    HYPRE_Real strong_threshold )
```

(Optional) The strong threshold for R is strong connections used in building an approximate ideal restriction. Default value is 0.25.

**3.6.4.195 HYPRE\_BoomerAMGSetSym()**

```
HYPRE_Int HYPRE_BoomerAMGSetSym (
    HYPRE_Solver solver,
    HYPRE_Int sym )
```

(Optional) Defines symmetry for ParaSAILS. For further explanation see description of ParaSAILS.

**3.6.4.196 HYPRE\_BoomerAMGSetThreshold()**

```
HYPRE_Int HYPRE_BoomerAMGSetThreshold (
    HYPRE_Solver solver,
    HYPRE_Real threshold )
```

(Optional) Defines threshold for ParaSAILS. For further explanation see description of ParaSAILS.

**3.6.4.197 HYPRE\_BoomerAMGSetTol()**

```
HYPRE_Int HYPRE_BoomerAMGSetTol (
    HYPRE_Solver solver,
    HYPRE_Real tol )
```

(Optional) Set the convergence tolerance, if BoomerAMG is used as a solver. If it is used as a preconditioner, it should be set to 0. The default is 1.e-6.

**3.6.4.198 HYPRE\_BoomerAMGSetTruncFactor()**

```
HYPRE_Int HYPRE_BoomerAMGSetTruncFactor (
    HYPRE_Solver solver,
    HYPRE_Real trunc_factor )
```

(Optional) Defines a truncation factor for the interpolation. The default is 0.

**3.6.4.199 HYPRE\_BoomerAMGSetup()**

```
HYPRE_Int HYPRE_BoomerAMGSetup (
    HYPRE_Solver solver,
    HYPRE_ParCSRMatrix A,
    HYPRE_ParVector b,
    HYPRE_ParVector x )
```

Set up the BoomerAMG solver or preconditioner. If used as a preconditioner, this function should be passed to the iterative solver *SetPrecond* function.

**Parameters**

<i>solver</i>	[IN] object to be set up.
<i>A</i>	[IN] ParCSR matrix used to construct the solver/preconditioner.
<i>b</i>	Ignored by this function.
<i>x</i>	Ignored by this function.

### 3.6.4.200 HYPRE\_BoomerAMGSetVariant()

```
HYPRE_Int HYPRE_BoomerAMGSetVariant (
    HYPRE_Solver solver,
    HYPRE_Int variant )
```

(Optional) Defines which variant of the Schwarz method is used. The following options exist for *variant*:

- 0 : hybrid multiplicative Schwarz method (no overlap across processor boundaries)
- 1 : hybrid additive Schwarz method (no overlap across processor boundaries)
- 2 : additive Schwarz method
- 3 : hybrid multiplicative Schwarz method (with overlap across processor boundaries)

The default is 0.

### 3.6.4.201 HYPRE\_BoomerAMGSolve()

```
HYPRE_Int HYPRE_BoomerAMGSolve (
    HYPRE_Solver solver,
    HYPRE_ParCSRMatrix A,
    HYPRE_ParVector b,
    HYPRE_ParVector x )
```

Solve the system or apply AMG as a preconditioner. If used as a preconditioner, this function should be passed to the iterative solver *SetPrecond* function.

#### Parameters

<i>solver</i>	[IN] solver or preconditioner object to be applied.
<i>A</i>	[IN] ParCSR matrix, matrix of the linear system to be solved
<i>b</i>	[IN] right hand side of the linear system to be solved
<i>x</i>	[OUT] approximated solution of the linear system to be solved

### 3.6.4.202 HYPRE\_BoomerAMGSolveT()

```
HYPRE_Int HYPRE_BoomerAMGSolveT (
    HYPRE_Solver solver,
    HYPRE_ParCSRMatrix A,
    HYPRE_ParVector b,
    HYPRE_ParVector x )
```

Solve the transpose system  $A^T x = b$  or apply AMG as a preconditioner to the transpose system . Note that this function should only be used when preconditioning CGNR with BoomerAMG. It can only be used with Jacobi smoothing (relax\_type 0 or 7) and without CF smoothing, i.e relax\_order needs to be set to 0. If used as a preconditioner, this function should be passed to the iterative solver *SetPrecond* function.

#### Parameters

<i>solver</i>	[IN] solver or preconditioner object to be applied.
---------------	---

## Parameters

$A$	[IN] ParCSR matrix
$b$	[IN] right hand side of the linear system to be solved
$x$	[OUT] approximated solution of the linear system to be solved

**3.6.4.203 HYPRE\_EuclidCreate()**

```
HYPRE_Int HYPRE_EuclidCreate (
    MPI_Comm comm,
    HYPRE_Solver * solver )
```

Create a Euclid object.

**3.6.4.204 HYPRE\_EuclidDestroy()**

```
HYPRE_Int HYPRE_EuclidDestroy (
    HYPRE_Solver solver )
```

Destroy a Euclid object.

**3.6.4.205 HYPRE\_EuclidSetBJ()**

```
HYPRE_Int HYPRE_EuclidSetBJ (
    HYPRE_Solver solver,
    HYPRE_Int bj )
```

Use block Jacobi ILU preconditioning instead of PILU

**3.6.4.206 HYPRE\_EuclidSetILUT()**

```
HYPRE_Int HYPRE_EuclidSetILUT (
    HYPRE_Solver solver,
    HYPRE_Real drop_tol )
```

uses ILUT and defines a drop tolerance relative to the largest absolute value of any entry in the row being factored.

**3.6.4.207 HYPRE\_EuclidSetLevel()**

```
HYPRE_Int HYPRE_EuclidSetLevel (
    HYPRE_Solver solver,
    HYPRE_Int level )
```

Set level k for ILU(k) factorization, default: 1

**3.6.4.208 HYPRE\_EuclidSetMem()**

```
HYPRE_Int HYPRE_EuclidSetMem (
    HYPRE_Solver solver,
    HYPRE_Int eu_mem )
```

If *eu\_mem* not equal 0, a summary of Euclid's memory usage is printed to stdout.

**3.6.4.209 HYPRE\_EuclidSetParams()**

```
HYPRE_Int HYPRE_EuclidSetParams (
    HYPRE_Solver solver,
    HYPRE_Int argc,
    char * argv[] )
```

Insert (name, value) pairs in Euclid's options database by passing Euclid the command line (or an array of strings). All Euclid options (e.g, level, drop-tolerance) are stored in this database. If a (name, value) pair already exists, this call updates the value. See also: HYPRE\_EuclidSetParamsFromFile.

**Parameters**

<i>argc</i>	[IN] Length of argv array
<i>argv</i>	[IN] Array of strings

**3.6.4.210 HYPRE\_EuclidSetParamsFromFile()**

```
HYPRE_Int HYPRE_EuclidSetParamsFromFile (
    HYPRE_Solver solver,
    char * filename )
```

Insert (name, value) pairs in Euclid's options database. Each line of the file should either begin with a "#", indicating a comment line, or contain a (name value) pair, e.g:

```
>cat optionsFile
\#sample runtime parameter file
-blockJacobi 3
-matFile      /home/hysom/myfile.euclid
-doSomething true
-xx_coeff -1.0
```

See also: HYPRE\_EuclidSetParams.

**Parameters**

<i>filename</i> [IN]	Pathname/filename to read
----------------------	---------------------------

**3.6.4.211 HYPRE\_EuclidSetRowScale()**

```
HYPRE_Int HYPRE_EuclidSetRowScale (
```



```
HYPRE_Solver solver,
HYPRE_Int row_scale )
```

If *row\_scale* not equal 0, values are scaled prior to factorization so that largest value in any row is +1 or -1. Note that this can destroy symmetry in a matrix.

#### 3.6.4.212 HYPRE\_EuclidSetSparseA()

```
HYPRE_Int HYPRE_EuclidSetSparseA (
    HYPRE_Solver solver,
    HYPRE_Real sparse_A )
```

Defines a drop tolerance for ILU(k). Default: 0 Use with HYPRE\_EuclidSetRowScale. Note that this can destroy symmetry in a matrix.

#### 3.6.4.213 HYPRE\_EuclidSetStats()

```
HYPRE_Int HYPRE_EuclidSetStats (
    HYPRE_Solver solver,
    HYPRE_Int eu_stats )
```

If *eu\_stats* not equal 0, a summary of runtime settings and timing information is printed to stdout.

#### 3.6.4.214 HYPRE\_EuclidSetup()

```
HYPRE_Int HYPRE_EuclidSetup (
    HYPRE_Solver solver,
    HYPRE_ParCSRMatrix A,
    HYPRE_ParVector b,
    HYPRE_ParVector x )
```

Set up the Euclid preconditioner. This function should be passed to the iterative solver *SetPrecond* function.

##### Parameters

<i>solver</i>	[IN] Preconditioner object to set up.
<i>A</i>	[IN] ParCSR matrix used to construct the preconditioner.
<i>b</i>	Ignored by this function.
<i>x</i>	Ignored by this function.

#### 3.6.4.215 HYPRE\_EuclidSolve()

```
HYPRE_Int HYPRE_EuclidSolve (
    HYPRE_Solver solver,
    HYPRE_ParCSRMatrix A,
    HYPRE_ParVector b,
    HYPRE_ParVector x )
```

Apply the Euclid preconditioner. This function should be passed to the iterative solver *SetPrecond* function.

## Parameters

<i>solver</i>	[IN] Preconditioner object to apply.
<i>A</i>	Ignored by this function.
<i>b</i>	[IN] Vector to precondition.
<i>x</i>	[OUT] Preconditioned vector.

**3.6.4.216 HYPRE\_ILUCreate()**

```
HYPRE_Int HYPRE_ILUCreate (
    HYPRE_Solver * solver )
```

Create a solver object

**3.6.4.217 HYPRE\_ILUDestroy()**

```
HYPRE_Int HYPRE_ILUDestroy (
    HYPRE_Solver solver )
```

Destroy a solver object

**3.6.4.218 HYPRE\_ILUGetFinalRelativeResidualNorm()**

```
HYPRE_Int HYPRE_ILUGetFinalRelativeResidualNorm (
    HYPRE_Solver solver,
    HYPRE_Real * res_norm )
```

(Optional) Return the norm of the final relative residual.

**3.6.4.219 HYPRE\_ILUGetNumIterations()**

```
HYPRE_Int HYPRE_ILUGetNumIterations (
    HYPRE_Solver solver,
    HYPRE_Int * num_iterations )
```

(Optional) Return the number of ILU iterations.

**3.6.4.220 HYPRE\_ILUSetDropThreshold()**

```
HYPRE_Int HYPRE_ILUSetDropThreshold (
    HYPRE_Solver solver,
    HYPRE_Real threshold )
```

(Optional) Set the threshold for dropping in L and U factors (for ILUT). Any fill-in less than this threshold is dropped in the factorization. The default is 1.0e-2.

**3.6.4.221 HYPRE\_ILUSetDropThresholdArray()**

```
HYPRE_Int HYPRE_ILUSetDropThresholdArray (
    HYPRE_Solver solver,
    HYPRE_Real * threshold )
```

(Optional) Set the array of thresholds for dropping in ILUT. B, E, and F correspond to upper left, lower left and upper right of 2 x 2 block decomposition respectively. Any fill-in less than threshold is dropped in the factorization.

- threshold[0] : threshold for matrix B.
- threshold[1] : threshold for matrix E and F.
- threshold[2] : threshold for matrix S (Schur Complement). The default is 1.0e-2.

**3.6.4.222 HYPRE\_ILUSetLevelOfFill()**

```
HYPRE_Int HYPRE_ILUSetLevelOfFill (
    HYPRE_Solver solver,
    HYPRE_Int lfil )
```

(Optional) Set the level of fill k, for level-based ILU(k) The default is 0 (for ILU(0)).

**3.6.4.223 HYPRE\_ILUSetLocalReordering()**

```
HYPRE_Int HYPRE_ILUSetLocalReordering (
    HYPRE_Solver solver,
    HYPRE_Int reordering_type )
```

Set the type of reordering for the local matrix.

Options for *reordering\_type* are:

- 0 : No reordering
- 1 : RCM (default)

**3.6.4.224 HYPRE\_ILUSetLogging()**

```
HYPRE_Int HYPRE_ILUSetLogging (
    HYPRE_Solver solver,
    HYPRE_Int logging )
```

(Optional) Requests logging of solver diagnostics. Requests additional computations for diagnostic and similar data to be logged by the user. Default is 0, do nothing. The latest residual will be available if logging > 1.

**3.6.4.225 HYPRE\_ILUSetMaxIter()**

```
HYPRE_Int HYPRE_ILUSetMaxIter (
    HYPRE_Solver solver,
    HYPRE_Int max_iter )
```

(Optional) Set maximum number of iterations if used as a solver. Set this to 1 if ILU is used as a preconditioner. The default is 20.

**3.6.4.226 HYPRE\_ILUSetMaxNnzPerRow()**

```
HYPRE_Int HYPRE_ILUSetMaxNnzPerRow (
    HYPRE_Solver solver,
    HYPRE_Int nnzmax )
```

(Optional) Set the max non-zeros per row in L and U factors (for ILUT) The default is 1000.

**3.6.4.227 HYPRE\_ILUSetNSHDropThreshold()**

```
HYPRE_Int HYPRE_ILUSetNSHDropThreshold (
    HYPRE_Solver solver,
    HYPRE_Real threshold )
```

(Optional) Set the threshold for dropping in Newton–Schulz–Hotelling iteration (NHS-ILU). Any entries less than this threshold are dropped when forming the approximate inverse matrix. The default is 1.0e-2.

**3.6.4.228 HYPRE\_ILUSetNSHDropThresholdArray()**

```
HYPRE_Int HYPRE_ILUSetNSHDropThresholdArray (
    HYPRE_Solver solver,
    HYPRE_Real * threshold )
```

(Optional) Set the array of thresholds for dropping in Newton–Schulz–Hotelling iteration (for NHS-ILU). Any fill-in less than thresholds is dropped when forming the approximate inverse matrix.

- threshold[0] : threshold for Minimal Residual iteration (initial guess for NSH).
- threshold[1] : threshold for Newton–Schulz–Hotelling iteration.

The default is 1.0e-2.

**3.6.4.229 HYPRE\_ILUSetPrintLevel()**

```
HYPRE_Int HYPRE_ILUSetPrintLevel (
    HYPRE_Solver solver,
    HYPRE_Int print_level )
```

(Optional) Set the print level to print setup and solve information.

- 0 : no printout (default)
- 1 : print setup information
- 2 : print solve information
- 3 : print both setup and solve information

**3.6.4.230 HYPRE\_ILUSetSchurMaxIter()**

```
HYPRE_Int HYPRE_ILUSetSchurMaxIter (
    HYPRE_Solver solver,
    HYPRE_Int ss_max_iter )
```

(Optional) Set maximum number of iterations for Schur System Solve. For GMRES-ILU, this is the maximum number of iterations for GMRES. The Krylov dimension for GMRES is set equal to this value to avoid restart. For NSH-ILU, this is the maximum number of iterations for NSH solve. The default is 5.

**3.6.4.231 HYPRE\_ILUSetTol()**

```
HYPRE_Int HYPRE_ILUSetTol (
    HYPRE_Solver solver,
    HYPRE_Real tol )
```

(Optional) Set the convergence tolerance for the ILU smoother. Use tol = 0.0 if ILU is used as a preconditioner. The default is 1.e-7.

**3.6.4.232 HYPRE\_ILUSetType()**

```
HYPRE_Int HYPRE_ILUSetType (
    HYPRE_Solver solver,
    HYPRE_Int ilu_type )
```

Set the type of ILU factorization.

Options for *ilu\_type* are:

- 0 : BJ with ILU(k) (default, with k = 0)
- 1 : BJ with ILUT
- 10 : GMRES with ILU(k)
- 11 : GMRES with ILUT
- 20 : NSH with ILU(k)
- 21 : NSH with ILUT
- 30 : RAS with ILU(k)
- 31 : RAS with ILUT
- 40 : (nonsymmetric permutation) DDPQ-GMRES with ILU(k)
- 41 : (nonsymmetric permutation) DDPQ-GMRES with ILUT
- 50 : GMRES with RAP-ILU(0) using MILU(0) for P

**3.6.4.233 HYPRE\_ILUSetup()**

```
HYPRE_Int HYPRE_ILUSetup (
    HYPRE_Solver solver,
    HYPRE_ParCSRMatrix A,
    HYPRE_ParVector b,
    HYPRE_ParVector x )
```

Setup the ILU solver or preconditioner. If used as a preconditioner, this function should be passed to the iterative solver *SetPrecond* function.

## Parameters

<i>solver</i>	[IN] object to be set up.
<i>A</i>	[IN] ParCSR matrix used to construct the solver/preconditioner.
<i>b</i>	right-hand-side of the linear system to be solved (Ignored by this function).
<i>x</i>	approximate solution of the linear system to be solved (Ignored by this function).

**3.6.4.234 HYPRE\_ILUSolve()**

```

HYPRE_Int HYPRE_ILUSolve (
    HYPRE_Solver solver,
    HYPRE_ParCSRMatrix A,
    HYPRE_ParVector b,
    HYPRE_ParVector x )

```

Solve the system or apply ILU as a preconditioner. If used as a preconditioner, this function should be passed to the iterative solver *SetPrecond* function.

## Parameters

<i>solver</i>	[IN] solver or preconditioner object to be applied.
<i>A</i>	[IN] ParCSR matrix, matrix of the linear system to be solved
<i>b</i>	[IN] right hand side of the linear system to be solved
<i>x</i>	[OUT] approximated solution of the linear system to be solved

**3.6.4.235 HYPRE\_MGRBuildAff()**

```

HYPRE_Int HYPRE_MGRBuildAff (
    HYPRE_ParCSRMatrix A,
    HYPRE_Int * CF_marker,
    HYPRE_Int debug_flag,
    HYPRE_ParCSRMatrix * A_ff )

```

**3.6.4.236 HYPRE\_MGRCreate()**

```

HYPRE_Int HYPRE_MGRCreate (
    HYPRE_Solver * solver )

```

Create a solver object

**3.6.4.237 HYPRE\_MGRDestroy()**

```

HYPRE_Int HYPRE_MGRDestroy (
    HYPRE_Solver solver )

```

Destroy a solver object

**3.6.4.238 HYPRE\_MGRGetCoarseGridConvergenceFactor()**

```
HYPRE_Int HYPRE_MGRGetCoarseGridConvergenceFactor (
    HYPRE_Solver solver,
    HYPRE_Real * conv_factor )
```

**3.6.4.239 HYPRE\_MGRGetFinalRelativeResidualNorm()**

```
HYPRE_Int HYPRE_MGRGetFinalRelativeResidualNorm (
    HYPRE_Solver solver,
    HYPRE_Real * res_norm )
```

(Optional) Return the norm of the final relative residual.

**3.6.4.240 HYPRE\_MGRGetNumIterations()**

```
HYPRE_Int HYPRE_MGRGetNumIterations (
    HYPRE_Solver solver,
    HYPRE_Int * num_iterations )
```

(Optional) Return the number of MGR iterations.

**3.6.4.241 HYPRE\_MGRSetBlockSize()**

```
HYPRE_Int HYPRE_MGRSetBlockSize (
    HYPRE_Solver solver,
    HYPRE_Int bsize )
```

(Optional) Set the system block size. This should match the block size set in the MGRSetCpointsByBlock function. The default is 1.

**3.6.4.242 HYPRE\_MGRSetCoarseGridMethod()**

```
HYPRE_Int HYPRE_MGRSetCoarseGridMethod (
    HYPRE_Solver solver,
    HYPRE_Int * cg_method )
```

(Optional) Set the strategy for coarse grid computation. Options for *cg\_method* are:

- 0 : Galerkin coarse grid computation using RAP.
- 1 : Non-Galerkin coarse grid computation with dropping strategy.

**3.6.4.243 HYPRE\_MGRSetCoarseGridPrintLevel()**

```
HYPRE_Int HYPRE_MGRSetCoarseGridPrintLevel (
    HYPRE_Solver solver,
    HYPRE_Int print_level )
```

#### 3.6.4.244 HYPRE\_MGRSetCoarseSolver()

```
HYPRE_Int HYPRE_MGRSetCoarseSolver (
    HYPRE_Solver solver,
    HYPRE_PtrToParSolverFcn coarse_grid_solver_solve,
    HYPRE_PtrToParSolverFcn coarse_grid_solver_setup,
    HYPRE_Solver coarse_grid_solver )
```

(Optional) Set the coarse grid solver. Currently uses BoomerAMG. The default, if not set, is BoomerAMG with default options.



## Parameters

<i>solver</i>	[IN] solver or preconditioner object
<i>coarse_grid_solver_solve</i>	[IN] solve routine for BoomerAMG
<i>coarse_grid_solver_setup</i>	[IN] setup routine for BoomerAMG
<i>coarse_grid_solver</i>	[IN] BoomerAMG solver

**3.6.4.245 HYPRE\_MGRSetCpointsByBlock()**

```

HYPRE_Int HYPRE_MGRSetCpointsByBlock (
    HYPRE_Solver solver,
    HYPRE_Int block_size,
    HYPRE_Int max_num_levels,
    HYPRE_Int * num_block_coarse_points,
    HYPRE_Int ** block_coarse_indexes )

```

Set the block data (by grid points) and prescribe the coarse indexes per block for each reduction level.

## Parameters

<i>solver</i>	[IN] solver or preconditioner object
<i>block_size</i>	[IN] system block size
<i>max_num_levels</i>	[IN] maximum number of reduction levels
<i>num_block_coarse_points</i>	[IN] number of coarse points per block per level
<i>block_coarse_indexes</i>	[IN] index for each block coarse point per level

**3.6.4.246 HYPRE\_MGRSetCpointsByContiguousBlock()**

```

HYPRE_Int HYPRE_MGRSetCpointsByContiguousBlock (
    HYPRE_Solver solver,
    HYPRE_Int block_size,
    HYPRE_Int max_num_levels,
    HYPRE_BigInt * idx_array,
    HYPRE_Int * num_block_coarse_points,
    HYPRE_Int ** block_coarse_indexes )

```

Set the block data assuming that the physical variables are ordered contiguously, i.e.  $p_1, p_2, \dots, p_n, s_1, s_2, \dots, s_n, \dots$

## Parameters

<i>solver</i>	[IN] solver or preconditioner object
<i>block_size</i>	[IN] system block size
<i>max_num_levels</i>	[IN] maximum number of reduction levels
<i>num_block_coarse_points</i>	[IN] number of coarse points per block per level
<i>block_coarse_indexes</i>	[IN] index for each block coarse point per level

### 3.6.4.247 HYPRE\_MGRSetCpointsByPointMarkerArray()

```
HYPRE_Int HYPRE_MGRSetCpointsByPointMarkerArray (
    HYPRE_Solver solver,
    HYPRE_Int block_size,
    HYPRE_Int max_num_levels,
    HYPRE_Int * num_block_coarse_points,
    HYPRE_Int ** lvl_block_coarse_indexes,
    HYPRE_Int * point_marker_array )
```

Set the coarse indices for the levels using an array of tags for all the local degrees of freedom. TODO: Rename the function to make it more descriptive.

#### Parameters

<i>solver</i>	[IN] solver or preconditioner object
<i>block_size</i>	[IN] system block size
<i>max_num_levels</i>	[IN] maximum number of reduction levels
<i>num_block_coarse_points</i>	[IN] number of coarse points per block per level
<i>lvl_block_coarse_indexes</i>	[IN] indices for the coarse points per level
<i>point_marker_array</i>	[IN] array of tags for the local degrees of freedom

### 3.6.4.248 HYPRE\_MGRSetFRelaxMethod()

```
HYPRE_Int HYPRE_MGRSetFRelaxMethod (
    HYPRE_Solver solver,
    HYPRE_Int relax_method )
```

(Optional) Set the strategy for F-relaxation. Options for *relax\_method* are:

- 0 : Single-level relaxation sweeps for F-relaxation as prescribed by *MGRSetRelaxType*
- 1 : Multi-level relaxation strategy for F-relaxation (V(1,0) cycle currently supported).

### 3.6.4.249 HYPRE\_MGRSetFrelaxPrintLevel()

```
HYPRE_Int HYPRE_MGRSetFrelaxPrintLevel (
    HYPRE_Solver solver,
    HYPRE_Int print_level )
```

### 3.6.4.250 HYPRE\_MGRSetFSolver()

```
HYPRE_Int HYPRE_MGRSetFSolver (
    HYPRE_Solver solver,
    HYPRE_PtrToParSolverFcn fine_grid_solver_solve,
    HYPRE_PtrToParSolverFcn fine_grid_solver_setup,
    HYPRE_Solver fsolver )
```

**3.6.4.251 HYPRE\_MGRSetGlobalSmoothType()**

```
HYPRE_Int HYPRE_MGRSetGlobalSmoothType (
    HYPRE_Solver solver,
    HYPRE_Int smooth_type )
```

(Optional) Determines type of global smoother. Options for *smooth\_type* are:

- 0 : block Jacobi (default)
- 1 : Jacobi
- 2 : Gauss-Seidel, sequential (very slow!)
- 3 : Gauss-Seidel, interior points in parallel, boundary sequential (slow!)
- 4 : hybrid Gauss-Seidel or SOR, forward solve
- 5 : hybrid Gauss-Seidel or SOR, backward solve
- 6 : hybrid chaotic Gauss-Seidel (works only with OpenMP)
- 7 : hybrid symmetric Gauss-Seidel or SSOR
- 8 : Euclid (ILU)

**3.6.4.252 HYPRE\_MGRSetInterpType()**

```
HYPRE_Int HYPRE_MGRSetInterpType (
    HYPRE_Solver solver,
    HYPRE_Int interp_type )
```

(Optional) Set the strategy for computing the MGR interpolation operator. Options for *interp\_type* are:

- 0 : injection  $[0I]^T$
- 1 : unscaled (not recommended)
- 2 : diagonal scaling (Jacobi)
- 3 : classical modified interpolation
- 4 : approximate inverse
- else : classical modified interpolation

The default is diagonal scaling.

**3.6.4.253 HYPRE\_MGRSetLevelFRelaxMethod()**

```
HYPRE_Int HYPRE_MGRSetLevelFRelaxMethod (
    HYPRE_Solver solver,
    HYPRE_Int * relax_method )
```

**3.6.4.254 HYPRE\_MGRSetLevelFRelaxNumFunctions()**

```
HYPRE_Int HYPRE_MGRSetLevelFRelaxNumFunctions (
    HYPRE_Solver solver,
    HYPRE_Int * num_functions )
```

(Optional) Set the number of functions for F-relaxation V-cycle. For problems like elasticity, one may want to perform coarsening and interpolation for block matrices. The number of functions corresponds to the number of scalar PDEs in the system.

**3.6.4.255 HYPRE\_MGRSetLevelInterpType()**

```
HYPRE_Int HYPRE_MGRSetLevelInterpType (
    HYPRE_Solver solver,
    HYPRE_Int * interp_type )
```

**3.6.4.256 HYPRE\_MGRSetLevelRestrictType()**

```
HYPRE_Int HYPRE_MGRSetLevelRestrictType (
    HYPRE_Solver solver,
    HYPRE_Int * restrict_type )
```

**3.6.4.257 HYPRE\_MGRSetLogging()**

```
HYPRE_Int HYPRE_MGRSetLogging (
    HYPRE_Solver solver,
    HYPRE_Int logging )
```

(Optional) Requests logging of solver diagnostics. Requests additional computations for diagnostic and similar data to be logged by the user. Default to 0 for do nothing. The latest residual will be available if logging > 1.

**3.6.4.258 HYPRE\_MGRSetMaxCoarseLevels()**

```
HYPRE_Int HYPRE_MGRSetMaxCoarseLevels (
    HYPRE_Solver solver,
    HYPRE_Int maxlev )
```

(Optional) Set maximum number of coarsening (or reduction) levels. The default is 10.

**3.6.4.259 HYPRE\_MGRSetMaxGlobalSmoothIters()**

```
HYPRE_Int HYPRE_MGRSetMaxGlobalSmoothIters (
    HYPRE_Solver solver,
    HYPRE_Int smooth_iter )
```

(Optional) Determines how many sweeps of global smoothing to do. Default is 0 (no global smoothing).

**3.6.4.260 HYPRE\_MGRSetMaxIter()**

```
HYPRE_Int HYPRE_MGRSetMaxIter (
    HYPRE_Solver solver,
    HYPRE_Int max_iter )
```

(Optional) Set maximum number of iterations if used as a solver. Set this to 1 if MGR is used as a preconditioner. The default is 20.

**3.6.4.261 HYPRE\_MGRSetNonCpointsToFpoints()**

```
HYPRE_Int HYPRE_MGRSetNonCpointsToFpoints (
    HYPRE_Solver solver,
    HYPRE_Int nonCptToFptFlag )
```

(Optional) Set non C-points to F-points. This routine determines how the coarse points are selected for the next level reduction. Options for *nonCptToFptFlag* are:

- 0 : Allow points not prescribed as C points to be potentially set as C points using classical AMG coarsening strategies (currently uses CLJP-coarsening).
- 1 : Fix points not prescribed as C points to be F points for the next reduction

**3.6.4.262 HYPRE\_MGRSetNumInterpSweeps()**

```
HYPRE_Int HYPRE_MGRSetNumInterpSweeps (
    HYPRE_Solver solver,
    HYPRE_Int nsweeps )
```

(Optional) Set number of interpolation sweeps. This option is for *interp\_type* > 2.

**3.6.4.263 HYPRE\_MGRSetNumRelaxSweeps()**

```
HYPRE_Int HYPRE_MGRSetNumRelaxSweeps (
    HYPRE_Solver solver,
    HYPRE_Int nsweeps )
```

(Optional) Set number of relaxation sweeps. This option is for the "single level" F-relaxation (*relax\_method* = 0).

**3.6.4.264 HYPRE\_MGRSetNumRestrictSweeps()**

```
HYPRE_Int HYPRE_MGRSetNumRestrictSweeps (
    HYPRE_Solver solver,
    HYPRE_Int nsweeps )
```

(Optional) Set number of restriction sweeps. This option is for *restrict\_type* > 2.

### 3.6.4.265 HYPRE\_MGRSetPMaxElmts()

```
HYPRE_Int HYPRE_MGRSetPMaxElmts (
    HYPRE_Solver solver,
    HYPRE_Int P_max_elmts )
```

(Optional) Set the number of maximum points for interpolation operator.

### 3.6.4.266 HYPRE\_MGRSetPrintLevel()

```
HYPRE_Int HYPRE_MGRSetPrintLevel (
    HYPRE_Solver solver,
    HYPRE_Int print_level )
```

(Optional) Set the print level to print setup and solve information.

- 0 : no printout (default)
- 1 : print setup information
- 2 : print solve information
- 3 : print both setup and solve information

### 3.6.4.267 HYPRE\_MGRSetRelaxType()

```
HYPRE_Int HYPRE_MGRSetRelaxType (
    HYPRE_Solver solver,
    HYPRE_Int relax_type )
```

(Optional) Set the relaxation type for F-relaxation. Currently supports the following flavors of relaxation types as described in the *BoomerAMGSetRelaxType*: *relax\_type* 0 - 8, 13, 14, 18, 19, 98.

### 3.6.4.268 HYPRE\_MGRSetReservedCoarseNodes()

```
HYPRE_Int HYPRE_MGRSetReservedCoarseNodes (
    HYPRE_Solver solver,
    HYPRE_Int reserved_coarse_size,
    HYPRE_BigInt * reserved_coarse_nodes )
```

(Optional) Defines indexes of coarse nodes to be kept to the coarsest level. These indexes are passed down through the MGR hierarchy to the coarsest grid of the coarse grid (BoomerAMG) solver.

#### Parameters

<i>solver</i>	[IN] solver or preconditioner object
<i>reserved_coarse_size</i>	[IN] number of reserved coarse points
<i>reserved_coarse_nodes</i>	[IN] (global) indexes of reserved coarse points

**3.6.4.269 HYPRE\_MGRSetReservedCpointsLevelToKeep()**

```
HYPRE_Int HYPRE_MGRSetReservedCpointsLevelToKeep (
    HYPRE_Solver solver,
    HYPRE_Int level )
```

**3.6.4.270 HYPRE\_MGRSetRestrictType()**

```
HYPRE_Int HYPRE_MGRSetRestrictType (
    HYPRE_Solver solver,
    HYPRE_Int restrict_type )
```

(Optional) Set the strategy for computing the MGR restriction operator.

Options for *restrict\_type* are:

- 0 : injection [0I]
- 1 : unscaled (not recommended)
- 2 : diagonal scaling (Jacobi)
- 3 : approximate inverse
- 4 : pAIR distance 1
- 5 : pAIR distance 2
- else : use classical modified interpolation

The default is injection.

**3.6.4.271 HYPRE\_MGRSetTol()**

```
HYPRE_Int HYPRE_MGRSetTol (
    HYPRE_Solver solver,
    HYPRE_Real tol )
```

(Optional) Set the convergence tolerance for the MGR solver. Use *tol* = 0.0 if MGR is used as a preconditioner. The default is 1.e-6.

**3.6.4.272 HYPRE\_MGRSetTruncateCoarseGridThreshold()**

```
HYPRE_Int HYPRE_MGRSetTruncateCoarseGridThreshold (
    HYPRE_Solver solver,
    HYPRE_Real threshold )
```

(Optional) Set the threshold to compress the coarse grid at each level Use *threshold* = 0.0 if no truncation is applied. Otherwise, set the threshold value for dropping entries for the coarse grid. The default is 0.0.

**3.6.4.273 HYPRE\_MGRSetup()**

```
HYPRE_Int HYPRE_MGRSetup (
    HYPRE_Solver solver,
    HYPRE_ParCSRMatrix A,
    HYPRE_ParVector b,
    HYPRE_ParVector x )
```

Setup the MGR solver or preconditioner. If used as a preconditioner, this function should be passed to the iterative solver *SetPrecond* function.

## Parameters

<i>solver</i>	[IN] object to be set up.
<i>A</i>	[IN] ParCSR matrix used to construct the solver/preconditioner.
<i>b</i>	right-hand-side of the linear system to be solved (Ignored by this function).
<i>x</i>	approximate solution of the linear system to be solved (Ignored by this function).

**3.6.4.274 HYPRE\_MGRSolve()**

```

HYPRE_Int HYPRE_MGRSolve (
    HYPRE_Solver solver,
    HYPRE_ParCSRMatrix A,
    HYPRE_ParVector b,
    HYPRE_ParVector x )

```

Solve the system or apply MGR as a preconditioner. If used as a preconditioner, this function should be passed to the iterative solver *SetPrecond* function.

## Parameters

<i>solver</i>	[IN] solver or preconditioner object to be applied.
<i>A</i>	[IN] ParCSR matrix, matrix of the linear system to be solved
<i>b</i>	[IN] right hand side of the linear system to be solved
<i>x</i>	[OUT] approximated solution of the linear system to be solved

**3.6.4.275 HYPRE\_ParaSailsBuildIJMatrix()**

```

HYPRE_Int HYPRE_ParaSailsBuildIJMatrix (
    HYPRE_Solver solver,
    HYPRE_IJMatrix * pij_A )

```

Build IJ Matrix of the sparse approximate inverse (factor). This function explicitly creates the IJ Matrix corresponding to the sparse approximate inverse or the inverse factor. Example: `HYPRE_IJMatrix ij_A; HYPRE_ParaSailsBuildIJMatrix(solver, &ij_A);`

## Parameters

<i>solver</i>	[IN] Preconditioner object.
<i>pij_A</i>	[OUT] Pointer to the IJ Matrix.

**3.6.4.276 HYPRE\_ParaSailsCreate()**

```

HYPRE_Int HYPRE_ParaSailsCreate (
    MPI_Comm comm,
    HYPRE_Solver * solver )

```

Create a ParaSails preconditioner.



**3.6.4.277 HYPRE\_ParaSailsDestroy()**

```
HYPRE_Int HYPRE_ParaSailsDestroy (
    HYPRE_Solver solver )
```

Destroy a ParaSails preconditioner.

**3.6.4.278 HYPRE\_ParaSailsSetFilter()**

```
HYPRE_Int HYPRE_ParaSailsSetFilter (
    HYPRE_Solver solver,
    HYPRE_Real filter )
```

Set the filter parameter for the ParaSails preconditioner.

**Parameters**

<i>solver</i>	[IN] Preconditioner object for which to set filter parameter.
<i>filter</i>	[IN] Value of filter parameter. The filter parameter is used to drop small nonzeros in the preconditioner, to reduce the cost of applying the preconditioner. Values from 0.05 to 0.1 are recommended. The default value is 0.1.

**3.6.4.279 HYPRE\_ParaSailsSetLoadbal()**

```
HYPRE_Int HYPRE_ParaSailsSetLoadbal (
    HYPRE_Solver solver,
    HYPRE_Real loadbal )
```

Set the load balance parameter for the ParaSails preconditioner.

**Parameters**

<i>solver</i>	[IN] Preconditioner object for which to set the load balance parameter.
<i>loadbal</i>	[IN] Value of the load balance parameter, $0 \leq \text{loadbal} \leq 1$ . A zero value indicates that no load balance is attempted; a value of unity indicates that perfect load balance will be attempted. The recommended value is 0.9 to balance the overhead of data exchanges for load balancing. No load balancing is needed if the preconditioner is very sparse and fast to construct. The default value when this parameter is not set is 0.

**3.6.4.280 HYPRE\_ParaSailsSetLogging()**

```
HYPRE_Int HYPRE_ParaSailsSetLogging (
    HYPRE_Solver solver,
    HYPRE_Int logging )
```

Set the logging parameter for the ParaSails preconditioner.

## Parameters

<i>solver</i>	[IN] Preconditioner object for which to set the logging parameter.
<i>logging</i>	[IN] Value of the logging parameter. A nonzero value sends statistics of the setup procedure to stdout. The default value when this parameter is not set is 0.

**3.6.4.281 HYPRE\_ParaSailsSetParams()**

```
HYPRE_Int HYPRE_ParaSailsSetParams (
    HYPRE_Solver solver,
    HYPRE_Real thresh,
    HYPRE_Int nlevels )
```

Set the threshold and levels parameter for the ParaSails preconditioner. The accuracy and cost of ParaSails are parameterized by these two parameters. Lower values of the threshold parameter and higher values of levels parameter lead to more accurate, but more expensive preconditioners.

## Parameters

<i>solver</i>	[IN] Preconditioner object for which to set parameters.
<i>thresh</i>	[IN] Value of threshold parameter, $0 \leq \text{thresh} \leq 1$ . The default value is 0.1.
<i>nlevels</i>	[IN] Value of levels parameter, $0 \leq \text{nlevels}$ . The default value is 1.

**3.6.4.282 HYPRE\_ParaSailsSetReuse()**

```
HYPRE_Int HYPRE_ParaSailsSetReuse (
    HYPRE_Solver solver,
    HYPRE_Int reuse )
```

Set the pattern reuse parameter for the ParaSails preconditioner.

## Parameters

<i>solver</i>	[IN] Preconditioner object for which to set the pattern reuse parameter.
<i>reuse</i>	[IN] Value of the pattern reuse parameter. A nonzero value indicates that the pattern of the preconditioner should be reused for subsequent constructions of the preconditioner. A zero value indicates that the preconditioner should be constructed from scratch. The default value when this parameter is not set is 0.

**3.6.4.283 HYPRE\_ParaSailsSetSym()**

```
HYPRE_Int HYPRE_ParaSailsSetSym (
    HYPRE_Solver solver,
    HYPRE_Int sym )
```

Set the symmetry parameter for the ParaSails preconditioner.

Values for *sym*

- 0 : nonsymmetric and/or indefinite problem, and nonsymmetric preconditioner
- 1 : SPD problem, and SPD (factored) preconditioner
- 2 : nonsymmetric, definite problem, and SPD (factored) preconditioner

**Parameters**

<i>solver</i>	[IN] Preconditioner object for which to set symmetry parameter.
<i>sym</i>	[IN] Symmetry parameter.

**3.6.4.284 HYPRE\_ParaSailsSetup()**

```
HYPRE_Int HYPRE_ParaSailsSetup (
    HYPRE_Solver solver,
    HYPRE_ParCSRMatrix A,
    HYPRE_ParVector b,
    HYPRE_ParVector x )
```

Set up the ParaSails preconditioner. This function should be passed to the iterative solver *SetPrecond* function.

**Parameters**

<i>solver</i>	[IN] Preconditioner object to set up.
<i>A</i>	[IN] ParCSR matrix used to construct the preconditioner.
<i>b</i>	Ignored by this function.
<i>x</i>	Ignored by this function.

**3.6.4.285 HYPRE\_ParaSailsSolve()**

```
HYPRE_Int HYPRE_ParaSailsSolve (
    HYPRE_Solver solver,
    HYPRE_ParCSRMatrix A,
    HYPRE_ParVector b,
    HYPRE_ParVector x )
```

Apply the ParaSails preconditioner. This function should be passed to the iterative solver *SetPrecond* function.

**Parameters**

<i>solver</i>	[IN] Preconditioner object to apply.
<i>A</i>	Ignored by this function.
<i>b</i>	[IN] Vector to precondition.
<i>x</i>	[OUT] Preconditioned vector.

**3.6.4.286 HYPRE\_ParCSRBICGSTABCreate()**

```
HYPRE_Int HYPRE_ParCSRBICGSTABCreate (
```

```
MPI_Comm comm,
HYPRE_Solver * solver )
```

Create a solver object

#### 3.6.4.287 HYPRE\_ParCSRBiCGSTABDestroy()

```
HYPRE_Int HYPRE_ParCSRBiCGSTABDestroy (
HYPRE_Solver solver )
```

Destroy a solver object.

#### 3.6.4.288 HYPRE\_ParCSRBiCGSTABGetFinalRelativeResidualNorm()

```
HYPRE_Int HYPRE_ParCSRBiCGSTABGetFinalRelativeResidualNorm (
HYPRE_Solver solver,
HYPRE_Real * norm )
```

#### 3.6.4.289 HYPRE\_ParCSRBiCGSTABGetNumIterations()

```
HYPRE_Int HYPRE_ParCSRBiCGSTABGetNumIterations (
HYPRE_Solver solver,
HYPRE_Int * num_iterations )
```

#### 3.6.4.290 HYPRE\_ParCSRBiCGSTABGetPrecond()

```
HYPRE_Int HYPRE_ParCSRBiCGSTABGetPrecond (
HYPRE_Solver solver,
HYPRE_Solver * precondition_data )
```

#### 3.6.4.291 HYPRE\_ParCSRBiCGSTABGetResidual()

```
HYPRE_Int HYPRE_ParCSRBiCGSTABGetResidual (
HYPRE_Solver solver,
HYPRE_ParVector * residual )
```

#### 3.6.4.292 HYPRE\_ParCSRBiCGSTABSetAbsoluteTol()

```
HYPRE_Int HYPRE_ParCSRBiCGSTABSetAbsoluteTol (
HYPRE_Solver solver,
HYPRE_Real a_tol )
```

#### 3.6.4.293 HYPRE\_ParCSRBiCGSTABSetLogging()

```
HYPRE_Int HYPRE_ParCSRBiCGSTABSetLogging (
HYPRE_Solver solver,
HYPRE_Int logging )
```

**3.6.4.294 HYPRE\_ParCSRBICGSTABSetMaxIter()**

```
HYPRE_Int HYPRE_ParCSRBICGSTABSetMaxIter (
    HYPRE_Solver solver,
    HYPRE_Int max_iter )
```

**3.6.4.295 HYPRE\_ParCSRBICGSTABSetMinIter()**

```
HYPRE_Int HYPRE_ParCSRBICGSTABSetMinIter (
    HYPRE_Solver solver,
    HYPRE_Int min_iter )
```

**3.6.4.296 HYPRE\_ParCSRBICGSTABSetPrecond()**

```
HYPRE_Int HYPRE_ParCSRBICGSTABSetPrecond (
    HYPRE_Solver solver,
    HYPRE_PtrToParSolverFcn precondition,
    HYPRE_PtrToParSolverFcn precondition_setup,
    HYPRE_Solver precondition_solver )
```

**3.6.4.297 HYPRE\_ParCSRBICGSTABSetPrintLevel()**

```
HYPRE_Int HYPRE_ParCSRBICGSTABSetPrintLevel (
    HYPRE_Solver solver,
    HYPRE_Int print_level )
```

**3.6.4.298 HYPRE\_ParCSRBICGSTABSetStopCrit()**

```
HYPRE_Int HYPRE_ParCSRBICGSTABSetStopCrit (
    HYPRE_Solver solver,
    HYPRE_Int stop_crit )
```

**3.6.4.299 HYPRE\_ParCSRBICGSTABSetTol()**

```
HYPRE_Int HYPRE_ParCSRBICGSTABSetTol (
    HYPRE_Solver solver,
    HYPRE_Real tol )
```

**3.6.4.300 HYPRE\_ParCSRBICGSTABSetup()**

```
HYPRE_Int HYPRE_ParCSRBICGSTABSetup (
    HYPRE_Solver solver,
    HYPRE_ParCSRMatrix A,
    HYPRE_ParVector b,
    HYPRE_ParVector x )
```

#### 3.6.4.301 HYPRE\_ParCSRBiCGSTABSolve()

```
HYPRE_Int HYPRE_ParCSRBiCGSTABSolve (
    HYPRE_Solver solver,
    HYPRE_ParCSRMatrix A,
    HYPRE_ParVector b,
    HYPRE_ParVector x )
```

#### 3.6.4.302 HYPRE\_ParCSRCGNRCreate()

```
HYPRE_Int HYPRE_ParCSRCGNRCreate (
    MPI_Comm comm,
    HYPRE_Solver * solver )
```

#### 3.6.4.303 HYPRE\_ParCSRCGNRDestroy()

```
HYPRE_Int HYPRE_ParCSRCGNRDestroy (
    HYPRE_Solver solver )
```

#### 3.6.4.304 HYPRE\_ParCSRCGNRGetFinalRelativeResidualNorm()

```
HYPRE_Int HYPRE_ParCSRCGNRGetFinalRelativeResidualNorm (
    HYPRE_Solver solver,
    HYPRE_Real * norm )
```

#### 3.6.4.305 HYPRE\_ParCSRCGNRGetNumIterations()

```
HYPRE_Int HYPRE_ParCSRCGNRGetNumIterations (
    HYPRE_Solver solver,
    HYPRE_Int * num_iterations )
```

#### 3.6.4.306 HYPRE\_ParCSRCGNRGetPrecond()

```
HYPRE_Int HYPRE_ParCSRCGNRGetPrecond (
    HYPRE_Solver solver,
    HYPRE_Solver * precondition_data )
```

#### 3.6.4.307 HYPRE\_ParCSRCGNRSetLogging()

```
HYPRE_Int HYPRE_ParCSRCGNRSetLogging (
    HYPRE_Solver solver,
    HYPRE_Int logging )
```

**3.6.4.308 HYPRE\_ParCSRConjSetMaxIter()**

```
HYPRE_Int HYPRE_ParCSRConjSetMaxIter (
    HYPRE_Solver solver,
    HYPRE_Int max_iter )
```

**3.6.4.309 HYPRE\_ParCSRConjSetMinIter()**

```
HYPRE_Int HYPRE_ParCSRConjSetMinIter (
    HYPRE_Solver solver,
    HYPRE_Int min_iter )
```

**3.6.4.310 HYPRE\_ParCSRConjSetPrecond()**

```
HYPRE_Int HYPRE_ParCSRConjSetPrecond (
    HYPRE_Solver solver,
    HYPRE_PtrToParSolverFcn precondition,
    HYPRE_PtrToParSolverFcn preconditionT,
    HYPRE_PtrToParSolverFcn preconditionSetup,
    HYPRE_Solver preconditionSolver )
```

**3.6.4.311 HYPRE\_ParCSRConjSetStopCrit()**

```
HYPRE_Int HYPRE_ParCSRConjSetStopCrit (
    HYPRE_Solver solver,
    HYPRE_Int stop_crit )
```

**3.6.4.312 HYPRE\_ParCSRConjSetTol()**

```
HYPRE_Int HYPRE_ParCSRConjSetTol (
    HYPRE_Solver solver,
    HYPRE_Real tol )
```

**3.6.4.313 HYPRE\_ParCSRConjSetup()**

```
HYPRE_Int HYPRE_ParCSRConjSetup (
    HYPRE_Solver solver,
    HYPRE_ParCSRMatrix A,
    HYPRE_ParVector b,
    HYPRE_ParVector x )
```

**3.6.4.314 HYPRE\_ParCSRConjSolve()**

```
HYPRE_Int HYPRE_ParCSRConjSolve (
    HYPRE_Solver solver,
    HYPRE_ParCSRMatrix A,
    HYPRE_ParVector b,
    HYPRE_ParVector x )
```

#### 3.6.4.315 HYPRE\_ParCSRCOGMRESCreate()

```
HYPRE_Int HYPRE_ParCSRCOGMRESCreate (
    MPI_Comm comm,
    HYPRE_Solver * solver )
```

Create a solver object.

#### 3.6.4.316 HYPRE\_ParCSRCOGMRESDestroy()

```
HYPRE_Int HYPRE_ParCSRCOGMRESDestroy (
    HYPRE_Solver solver )
```

Destroy a solver object.

#### 3.6.4.317 HYPRE\_ParCSRCOGMRESGetFinalRelativeResidualNorm()

```
HYPRE_Int HYPRE_ParCSRCOGMRESGetFinalRelativeResidualNorm (
    HYPRE_Solver solver,
    HYPRE_Real * norm )
```

#### 3.6.4.318 HYPRE\_ParCSRCOGMRESGetNumIterations()

```
HYPRE_Int HYPRE_ParCSRCOGMRESGetNumIterations (
    HYPRE_Solver solver,
    HYPRE_Int * num_iterations )
```

#### 3.6.4.319 HYPRE\_ParCSRCOGMRESGetPrecond()

```
HYPRE_Int HYPRE_ParCSRCOGMRESGetPrecond (
    HYPRE_Solver solver,
    HYPRE_Solver * precondition_data )
```

#### 3.6.4.320 HYPRE\_ParCSRCOGMRESGetResidual()

```
HYPRE_Int HYPRE_ParCSRCOGMRESGetResidual (
    HYPRE_Solver solver,
    HYPRE_ParVector * residual )
```

Returns the residual.

#### 3.6.4.321 HYPRE\_ParCSRCOGMRESSetAbsoluteTol()

```
HYPRE_Int HYPRE_ParCSRCOGMRESSetAbsoluteTol (
    HYPRE_Solver solver,
    HYPRE_Real a_tol )
```



**3.6.4.322 HYPRE\_ParCSRCONMRESSetCGS()**

```
HYPRE_Int HYPRE_ParCSRCONMRESSetCGS (
    HYPRE_Solver solver,
    HYPRE_Int cgs )
```

**3.6.4.323 HYPRE\_ParCSRCONMRESSetKDim()**

```
HYPRE_Int HYPRE_ParCSRCONMRESSetKDim (
    HYPRE_Solver solver,
    HYPRE_Int k_dim )
```

**3.6.4.324 HYPRE\_ParCSRCONMRESSetLogging()**

```
HYPRE_Int HYPRE_ParCSRCONMRESSetLogging (
    HYPRE_Solver solver,
    HYPRE_Int logging )
```

**3.6.4.325 HYPRE\_ParCSRCONMRESSetMaxIter()**

```
HYPRE_Int HYPRE_ParCSRCONMRESSetMaxIter (
    HYPRE_Solver solver,
    HYPRE_Int max_iter )
```

**3.6.4.326 HYPRE\_ParCSRCONMRESSetMinIter()**

```
HYPRE_Int HYPRE_ParCSRCONMRESSetMinIter (
    HYPRE_Solver solver,
    HYPRE_Int min_iter )
```

**3.6.4.327 HYPRE\_ParCSRCONMRESSetPrecond()**

```
HYPRE_Int HYPRE_ParCSRCONMRESSetPrecond (
    HYPRE_Solver solver,
    HYPRE_PtrToParSolverFcn precondition,
    HYPRE_PtrToParSolverFcn precondition_setup,
    HYPRE_Solver precondition_solver )
```

**3.6.4.328 HYPRE\_ParCSRCONMRESSetPrintLevel()**

```
HYPRE_Int HYPRE_ParCSRCONMRESSetPrintLevel (
    HYPRE_Solver solver,
    HYPRE_Int print_level )
```

**3.6.4.329 HYPRE\_ParCSRCOGMRESSetTol()**

```
HYPRE_Int HYPRE_ParCSRCOGMRESSetTol (
    HYPRE_Solver solver,
    HYPRE_Real tol )
```

**3.6.4.330 HYPRE\_ParCSRCOGMRESSetUnroll()**

```
HYPRE_Int HYPRE_ParCSRCOGMRESSetUnroll (
    HYPRE_Solver solver,
    HYPRE_Int unroll )
```

**3.6.4.331 HYPRE\_ParCSRCOGMRESSetup()**

```
HYPRE_Int HYPRE_ParCSRCOGMRESSetup (
    HYPRE_Solver solver,
    HYPRE_ParCSRMatrix A,
    HYPRE_ParVector b,
    HYPRE_ParVector x )
```

**3.6.4.332 HYPRE\_ParCSRCOGMRESSolve()**

```
HYPRE_Int HYPRE_ParCSRCOGMRESSolve (
    HYPRE_Solver solver,
    HYPRE_ParCSRMatrix A,
    HYPRE_ParVector b,
    HYPRE_ParVector x )
```

**3.6.4.333 HYPRE\_ParCSRDiagScale()**

```
HYPRE_Int HYPRE_ParCSRDiagScale (
    HYPRE_Solver solver,
    HYPRE_ParCSRMatrix HA,
    HYPRE_ParVector Hy,
    HYPRE_ParVector Hx )
```

Solve routine for diagonal preconditioning.

**3.6.4.334 HYPRE\_ParCSRDiagScaleSetup()**

```
HYPRE_Int HYPRE_ParCSRDiagScaleSetup (
    HYPRE_Solver solver,
    HYPRE_ParCSRMatrix A,
    HYPRE_ParVector y,
    HYPRE_ParVector x )
```

Setup routine for diagonal preconditioning.

**3.6.4.335 HYPRE\_ParCSRFlexGMRESCreate()**

```
HYPRE_Int HYPRE_ParCSRFlexGMRESCreate (
    MPI_Comm comm,
    HYPRE_Solver * solver )
```

Create a solver object.

**3.6.4.336 HYPRE\_ParCSRFlexGMRESDestroy()**

```
HYPRE_Int HYPRE_ParCSRFlexGMRESDestroy (
    HYPRE_Solver solver )
```

Destroy a solver object.

**3.6.4.337 HYPRE\_ParCSRFlexGMRESGetFinalRelativeResidualNorm()**

```
HYPRE_Int HYPRE_ParCSRFlexGMRESGetFinalRelativeResidualNorm (
    HYPRE_Solver solver,
    HYPRE_Real * norm )
```

**3.6.4.338 HYPRE\_ParCSRFlexGMRESGetNumIterations()**

```
HYPRE_Int HYPRE_ParCSRFlexGMRESGetNumIterations (
    HYPRE_Solver solver,
    HYPRE_Int * num_iterations )
```

**3.6.4.339 HYPRE\_ParCSRFlexGMRESGetPrecond()**

```
HYPRE_Int HYPRE_ParCSRFlexGMRESGetPrecond (
    HYPRE_Solver solver,
    HYPRE_Solver * precondition_data )
```

**3.6.4.340 HYPRE\_ParCSRFlexGMRESGetResidual()**

```
HYPRE_Int HYPRE_ParCSRFlexGMRESGetResidual (
    HYPRE_Solver solver,
    HYPRE_ParVector * residual )
```

**3.6.4.341 HYPRE\_ParCSRFlexGMRESSetAbsoluteTol()**

```
HYPRE_Int HYPRE_ParCSRFlexGMRESSetAbsoluteTol (
    HYPRE_Solver solver,
    HYPRE_Real a_tol )
```

**3.6.4.342 HYPRE\_ParCSRFlexGMRESSetKDim()**

```
HYPRE_Int HYPRE_ParCSRFlexGMRESSetKDim (
    HYPRE_Solver solver,
    HYPRE_Int k_dim )
```

**3.6.4.343 HYPRE\_ParCSRFlexGMRESSetLogging()**

```
HYPRE_Int HYPRE_ParCSRFlexGMRESSetLogging (
    HYPRE_Solver solver,
    HYPRE_Int logging )
```

**3.6.4.344 HYPRE\_ParCSRFlexGMRESSetMaxIter()**

```
HYPRE_Int HYPRE_ParCSRFlexGMRESSetMaxIter (
    HYPRE_Solver solver,
    HYPRE_Int max_iter )
```

**3.6.4.345 HYPRE\_ParCSRFlexGMRESSetMinIter()**

```
HYPRE_Int HYPRE_ParCSRFlexGMRESSetMinIter (
    HYPRE_Solver solver,
    HYPRE_Int min_iter )
```

**3.6.4.346 HYPRE\_ParCSRFlexGMRESSetModifyPC()**

```
HYPRE_Int HYPRE_ParCSRFlexGMRESSetModifyPC (
    HYPRE_Solver solver,
    HYPRE_PtrToModifyPCFcn modify_pc )
```

**3.6.4.347 HYPRE\_ParCSRFlexGMRESSetPrecond()**

```
HYPRE_Int HYPRE_ParCSRFlexGMRESSetPrecond (
    HYPRE_Solver solver,
    HYPRE_PtrToParSolverFcn precond,
    HYPRE_PtrToParSolverFcn precond_setup,
    HYPRE_Solver precond_solver )
```

**3.6.4.348 HYPRE\_ParCSRFlexGMRESSetPrintLevel()**

```
HYPRE_Int HYPRE_ParCSRFlexGMRESSetPrintLevel (
    HYPRE_Solver solver,
    HYPRE_Int print_level )
```

**3.6.4.349 HYPRE\_ParCSRFlexGMRESSetTol()**

```
HYPRE_Int HYPRE_ParCSRFlexGMRESSetTol (
    HYPRE_Solver solver,
    HYPRE_Real tol )
```

**3.6.4.350 HYPRE\_ParCSRFlexGMRESSetup()**

```
HYPRE_Int HYPRE_ParCSRFlexGMRESSetup (
    HYPRE_Solver solver,
    HYPRE_ParCSRMatrix A,
    HYPRE_ParVector b,
    HYPRE_ParVector x )
```

**3.6.4.351 HYPRE\_ParCSRFlexGMRESSolve()**

```
HYPRE_Int HYPRE_ParCSRFlexGMRESSolve (
    HYPRE_Solver solver,
    HYPRE_ParCSRMatrix A,
    HYPRE_ParVector b,
    HYPRE_ParVector x )
```

**3.6.4.352 HYPRE\_ParCSRGMRESCreate()**

```
HYPRE_Int HYPRE_ParCSRGMRESCreate (
    MPI_Comm comm,
    HYPRE_Solver * solver )
```

Create a solver object.

**3.6.4.353 HYPRE\_ParCSRGMRESDestroy()**

```
HYPRE_Int HYPRE_ParCSRGMRESDestroy (
    HYPRE_Solver solver )
```

Destroy a solver object.

**3.6.4.354 HYPRE\_ParCSRGMRESGetFinalRelativeResidualNorm()**

```
HYPRE_Int HYPRE_ParCSRGMRESGetFinalRelativeResidualNorm (
    HYPRE_Solver solver,
    HYPRE_Real * norm )
```

**3.6.4.355 HYPRE\_ParCSRGMRESGetNumIterations()**

```
HYPRE_Int HYPRE_ParCSRGMRESGetNumIterations (
    HYPRE_Solver solver,
    HYPRE_Int * num_iterations )
```

**3.6.4.356 HYPRE\_ParCSRGMRESGetPrecond()**

```
HYPRE_Int HYPRE_ParCSRGMRESGetPrecond (
    HYPRE_Solver solver,
    HYPRE_Solver * precondition_data )
```

**3.6.4.357 HYPRE\_ParCSRGMRESGetResidual()**

```
HYPRE_Int HYPRE_ParCSRGMRESGetResidual (
    HYPRE_Solver solver,
    HYPRE_ParVector * residual )
```

Returns the residual.

**3.6.4.358 HYPRE\_ParCSRGMRESSetAbsoluteTol()**

```
HYPRE_Int HYPRE_ParCSRGMRESSetAbsoluteTol (
    HYPRE_Solver solver,
    HYPRE_Real a_tol )
```

**3.6.4.359 HYPRE\_ParCSRGMRESSetKDim()**

```
HYPRE_Int HYPRE_ParCSRGMRESSetKDim (
    HYPRE_Solver solver,
    HYPRE_Int k_dim )
```

**3.6.4.360 HYPRE\_ParCSRGMRESSetLogging()**

```
HYPRE_Int HYPRE_ParCSRGMRESSetLogging (
    HYPRE_Solver solver,
    HYPRE_Int logging )
```

**3.6.4.361 HYPRE\_ParCSRGMRESSetMaxIter()**

```
HYPRE_Int HYPRE_ParCSRGMRESSetMaxIter (
    HYPRE_Solver solver,
    HYPRE_Int max_iter )
```

**3.6.4.362 HYPRE\_ParCSRGMRESSetMinIter()**

```
HYPRE_Int HYPRE_ParCSRGMRESSetMinIter (
    HYPRE_Solver solver,
    HYPRE_Int min_iter )
```

**3.6.4.363 HYPRE\_ParCSRGMRESSetPrecond()**

```
HYPRE_Int HYPRE_ParCSRGMRESSetPrecond (
    HYPRE_Solver solver,
    HYPRE_PtrToParSolverFcn precond,
    HYPRE_PtrToParSolverFcn precond_setup,
    HYPRE_Solver precond_solver )
```

**3.6.4.364 HYPRE\_ParCSRGMRESSetPrintLevel()**

```
HYPRE_Int HYPRE_ParCSRGMRESSetPrintLevel (
    HYPRE_Solver solver,
    HYPRE_Int print_level )
```

**3.6.4.365 HYPRE\_ParCSRGMRESSetStopCrit()**

```
HYPRE_Int HYPRE_ParCSRGMRESSetStopCrit (
    HYPRE_Solver solver,
    HYPRE_Int stop_crit )
```

**3.6.4.366 HYPRE\_ParCSRGMRESSetTol()**

```
HYPRE_Int HYPRE_ParCSRGMRESSetTol (
    HYPRE_Solver solver,
    HYPRE_Real tol )
```

**3.6.4.367 HYPRE\_ParCSRGMRESSetup()**

```
HYPRE_Int HYPRE_ParCSRGMRESSetup (
    HYPRE_Solver solver,
    HYPRE_ParCSRMatrix A,
    HYPRE_ParVector b,
    HYPRE_ParVector x )
```

**3.6.4.368 HYPRE\_ParCSRGMRESSolve()**

```
HYPRE_Int HYPRE_ParCSRGMRESSolve (
    HYPRE_Solver solver,
    HYPRE_ParCSRMatrix A,
    HYPRE_ParVector b,
    HYPRE_ParVector x )
```

**3.6.4.369 HYPRE\_ParCSRHybridCreate()**

```
HYPRE_Int HYPRE_ParCSRHybridCreate (
    HYPRE_Solver * solver )
```

Create solver object

#### 3.6.4.370 HYPRE\_ParCSRHybridDestroy()

```
HYPRE_Int HYPRE_ParCSRHybridDestroy (
    HYPRE_Solver solver )
```

Destroy solver object

#### 3.6.4.371 HYPRE\_ParCSRHybridGetDSCGNumIterations()

```
HYPRE_Int HYPRE_ParCSRHybridGetDSCGNumIterations (
    HYPRE_Solver solver,
    HYPRE_Int * dscg_num_its )
```

Retrieves the number of iterations used by the diagonally scaled solver.

#### 3.6.4.372 HYPRE\_ParCSRHybridGetFinalRelativeResidualNorm()

```
HYPRE_Int HYPRE_ParCSRHybridGetFinalRelativeResidualNorm (
    HYPRE_Solver solver,
    HYPRE_Real * norm )
```

Retrieves the final relative residual norm.

#### 3.6.4.373 HYPRE\_ParCSRHybridGetNumIterations()

```
HYPRE_Int HYPRE_ParCSRHybridGetNumIterations (
    HYPRE_Solver solver,
    HYPRE_Int * num_its )
```

Retrieves the total number of iterations.

#### 3.6.4.374 HYPRE\_ParCSRHybridGetPCGNumIterations()

```
HYPRE_Int HYPRE_ParCSRHybridGetPCGNumIterations (
    HYPRE_Solver solver,
    HYPRE_Int * pcg_num_its )
```

Retrieves the number of iterations used by the AMG preconditioned solver.

#### 3.6.4.375 HYPRE\_ParCSRHybridGetRecomputeResidual()

```
HYPRE_Int HYPRE_ParCSRHybridGetRecomputeResidual (
    HYPRE_Solver solver,
    HYPRE_Int * recompute_residual )
```

(Optional) Get recompute residual option.



**3.6.4.376 HYPRE\_ParCSRHybridGetRecomputeResidualP()**

```
HYPRE_Int HYPRE_ParCSRHybridGetRecomputeResidualP (
    HYPRE_Solver solver,
    HYPRE_Int * recompute_residual_p )
```

(Optional) Get recompute residual period option.

**3.6.4.377 HYPRE\_ParCSRHybridGetSetupSolveTime()**

```
HYPRE_Int HYPRE_ParCSRHybridGetSetupSolveTime (
    HYPRE_Solver solver,
    HYPRE_Real * time )
```

**3.6.4.378 HYPRE\_ParCSRHybridSetAbsoluteTol()**

```
HYPRE_Int HYPRE_ParCSRHybridSetAbsoluteTol (
    HYPRE_Solver solver,
    HYPRE_Real tol )
```

Set the absolute convergence tolerance for the Krylov solver. The default is 0.

**3.6.4.379 HYPRE\_ParCSRHybridSetAggInterpType()**

```
HYPRE_Int HYPRE_ParCSRHybridSetAggInterpType (
    HYPRE_Solver solver,
    HYPRE_Int agg_interp_type )
```

**3.6.4.380 HYPRE\_ParCSRHybridSetAggNumLevels()**

```
HYPRE_Int HYPRE_ParCSRHybridSetAggNumLevels (
    HYPRE_Solver solver,
    HYPRE_Int agg_num_levels )
```

(Optional) Defines the number of levels of aggressive coarsening, starting with the finest level. The default is 0, i.e. no aggressive coarsening.

### 3.6.4.381 HYPRE\_ParCSRHybridSetCoarsenType()

```
HYPRE_Int HYPRE_ParCSRHybridSetCoarsenType (
    HYPRE_Solver solver,
    HYPRE_Int coarsen_type )
```

(Optional) Defines which parallel coarsening algorithm is used. There are the following options for *coarsen\_type*:

- 0 : CLJP-coarsening (a parallel coarsening algorithm using independent sets).
- 1 : classical Ruge-Stueben coarsening on each processor, no boundary treatment
- 3 : classical Ruge-Stueben coarsening on each processor, followed by a third pass, which adds coarse points on the boundaries
- 6 : Falgout coarsening (uses 1 first, followed by CLJP using the interior coarse points generated by 1 as its first independent set)
- 7 : CLJP-coarsening (using a fixed random vector, for debugging purposes only)
- 8 : PMIS-coarsening (a parallel coarsening algorithm using independent sets with lower complexities than CLJP, might also lead to slower convergence)
- 9 : PMIS-coarsening (using a fixed random vector, for debugging purposes only)
- 10 : HMIS-coarsening (uses one pass Ruge-Stueben on each processor independently, followed by PMIS using the interior C-points as its first independent set)
- 11 : one-pass Ruge-Stueben coarsening on each processor, no boundary treatment

The default is 10.

### 3.6.4.382 HYPRE\_ParCSRHybridSetConvergenceTol()

```
HYPRE_Int HYPRE_ParCSRHybridSetConvergenceTol (
    HYPRE_Solver solver,
    HYPRE_Real cf_tol )
```

Set the desired convergence factor

### 3.6.4.383 HYPRE\_ParCSRHybridSetCycleNumSweeps()

```
HYPRE_Int HYPRE_ParCSRHybridSetCycleNumSweeps (
    HYPRE_Solver solver,
    HYPRE_Int num_sweeps,
    HYPRE_Int k )
```

(Optional) Sets the number of sweeps at a specified cycle. There are the following options for *k*:

- 1 : the down cycle
- 2 : the up cycle
- 3 : the coarsest level

**3.6.4.384 HYPRE\_ParCSRHbridSetCycleRelaxType()**

```
HYPRE_Int HYPRE_ParCSRHbridSetCycleRelaxType (
    HYPRE_Solver solver,
    HYPRE_Int relax_type,
    HYPRE_Int k )
```

(Optional) Defines the smoother at a given cycle. For options of *relax\_type* see description of HYPRE\_Boomer↔AMGSetRelaxType). Options for k are

- 1 : the down cycle
- 2 : the up cycle
- 3 : the coarsest level

**3.6.4.385 HYPRE\_ParCSRHbridSetCycleType()**

```
HYPRE_Int HYPRE_ParCSRHbridSetCycleType (
    HYPRE_Solver solver,
    HYPRE_Int cycle_type )
```

(Optional) Defines the type of cycle. For a V-cycle, set *cycle\_type* to 1, for a W-cycle set *cycle\_type* to 2. The default is 1.

**3.6.4.386 HYPRE\_ParCSRHbridSetDofFunc()**

```
HYPRE_Int HYPRE_ParCSRHbridSetDofFunc (
    HYPRE_Solver solver,
    HYPRE_Int * dof_func )
```

(Optional) Sets the mapping that assigns the function to each variable, if using the systems version. If no assignment is made and the number of functions is  $k > 1$ , the mapping generated is (0,1,...,k-1,0,1,...,k-1,...).

**3.6.4.387 HYPRE\_ParCSRHbridSetDSCGMaxIter()**

```
HYPRE_Int HYPRE_ParCSRHbridSetDSCGMaxIter (
    HYPRE_Solver solver,
    HYPRE_Int dscg_max_its )
```

Set the maximal number of iterations for the diagonally preconditioned solver

**3.6.4.388 HYPRE\_ParCSRHbridSetGridRelaxPoints()**

```
HYPRE_Int HYPRE_ParCSRHbridSetGridRelaxPoints (
    HYPRE_Solver solver,
    HYPRE_Int ** grid_relax_points )
```

**3.6.4.389 HYPRE\_ParCSRHybridSetGridRelaxType()**

```
HYPRE_Int HYPRE_ParCSRHybridSetGridRelaxType (
    HYPRE_Solver solver,
    HYPRE_Int * grid_relax_type )
```

**3.6.4.390 HYPRE\_ParCSRHybridSetInterpType()**

```
HYPRE_Int HYPRE_ParCSRHybridSetInterpType (
    HYPRE_Solver solver,
    HYPRE_Int interp_type )
```

(Optional) Specifies which interpolation operator is used The default is ext+i interpolation truncated to at most 4 elements per row.

**3.6.4.391 HYPRE\_ParCSRHybridSetKDim()**

```
HYPRE_Int HYPRE_ParCSRHybridSetKDim (
    HYPRE_Solver solver,
    HYPRE_Int k_dim )
```

Set the Krylov dimension for restarted GMRES. The default is 5.

**3.6.4.392 HYPRE\_ParCSRHybridSetKeepTranspose()**

```
HYPRE_Int HYPRE_ParCSRHybridSetKeepTranspose (
    HYPRE_Solver solver,
    HYPRE_Int keepT )
```

(Optional) Sets whether to store local transposed interpolation The default is 0 (don't store).

**3.6.4.393 HYPRE\_ParCSRHybridSetLevelOuterWt()**

```
HYPRE_Int HYPRE_ParCSRHybridSetLevelOuterWt (
    HYPRE_Solver solver,
    HYPRE_Real outer_wt,
    HYPRE_Int level )
```

(Optional) Defines the outer relaxation weight for hybrid SOR or SSOR on the user defined level. Note that the finest level is denoted 0, the next coarser level 1, etc. For nonpositive omega, the parameter is determined on the given level as described for HYPRE\_BoomerAMGSetOuterWt. The default is 1.

**3.6.4.394 HYPRE\_ParCSRHybridSetLevelRelaxWt()**

```
HYPRE_Int HYPRE_ParCSRHybridSetLevelRelaxWt (
    HYPRE_Solver solver,
    HYPRE_Real relax_wt,
    HYPRE_Int level )
```

(Optional) Defines the relaxation weight for smoothed Jacobi and hybrid SOR on the user defined level. Note that the finest level is denoted 0, the next coarser level 1, etc. For nonpositive *relax\_weight*, the parameter is determined on the given level as described for HYPRE\_BoomerAMGSetRelaxWt. The default is 1.

**3.6.4.395 HYPRE\_ParCSRHybridSetLogging()**

```
HYPRE_Int HYPRE_ParCSRHybridSetLogging (
    HYPRE_Solver solver,
    HYPRE_Int logging )
```

Set logging parameter (default: 0, no logging).

**3.6.4.396 HYPRE\_ParCSRHybridSetMaxCoarseSize()**

```
HYPRE_Int HYPRE_ParCSRHybridSetMaxCoarseSize (
    HYPRE_Solver solver,
    HYPRE_Int max_coarse_size )
```

(Optional) Defines the maximal coarse grid size. The default is 9.

**3.6.4.397 HYPRE\_ParCSRHybridSetMaxLevels()**

```
HYPRE_Int HYPRE_ParCSRHybridSetMaxLevels (
    HYPRE_Solver solver,
    HYPRE_Int max_levels )
```

(Optional) Defines the maximal number of levels used for AMG. The default is 25.

**3.6.4.398 HYPRE\_ParCSRHybridSetMaxRowSum()**

```
HYPRE_Int HYPRE_ParCSRHybridSetMaxRowSum (
    HYPRE_Solver solver,
    HYPRE_Real max_row_sum )
```

(Optional) Sets a parameter to modify the definition of strength for diagonal dominant portions of the matrix. The default is 0.9. If *max\_row\_sum* is 1, no checking for diagonally dominant rows is performed.

**3.6.4.399 HYPRE\_ParCSRHybridSetMeasureType()**

```
HYPRE_Int HYPRE_ParCSRHybridSetMeasureType (
    HYPRE_Solver solver,
    HYPRE_Int measure_type )
```

(Optional) Defines whether local or global measures are used.

**3.6.4.400 HYPRE\_ParCSRHybridSetMinCoarseSize()**

```
HYPRE_Int HYPRE_ParCSRHybridSetMinCoarseSize (
    HYPRE_Solver solver,
    HYPRE_Int min_coarse_size )
```

(Optional) Defines the minimal coarse grid size. The default is 0.

**3.6.4.401 HYPRE\_ParCSRHybridSetNodal()**

```
HYPRE_Int HYPRE_ParCSRHybridSetNodal (
    HYPRE_Solver solver,
    HYPRE_Int nodal )
```

(Optional) Sets whether to use the nodal systems version. The default is 0 (the unknown based approach).

**3.6.4.402 HYPRE\_ParCSRHybridSetNonGalerkinTol()**

```
HYPRE_Int HYPRE_ParCSRHybridSetNonGalerkinTol (
    HYPRE_Solver solver,
    HYPRE_Int num_levels,
    HYPRE_Real * nongalerkin_tol )
```

(Optional) Sets whether to use non-Galerkin option The default is no non-Galerkin option num\_levels sets the number of levels where to use it nongalerkin\_tol contains the tolerances for <num\_levels> levels

**3.6.4.403 HYPRE\_ParCSRHybridSetNumFunctions()**

```
HYPRE_Int HYPRE_ParCSRHybridSetNumFunctions (
    HYPRE_Solver solver,
    HYPRE_Int num_functions )
```

(Optional) Sets the size of the system of PDEs, if using the systems version. The default is 1.

**3.6.4.404 HYPRE\_ParCSRHybridSetNumGridSweeps()**

```
HYPRE_Int HYPRE_ParCSRHybridSetNumGridSweeps (
    HYPRE_Solver solver,
    HYPRE_Int * num_grid_sweeps )
```

**3.6.4.405 HYPRE\_ParCSRHybridSetNumPaths()**

```
HYPRE_Int HYPRE_ParCSRHybridSetNumPaths (
    HYPRE_Solver solver,
    HYPRE_Int num_paths )
```

(Optional) Defines the degree of aggressive coarsening. The default is 1, which leads to the most aggressive coarsening. Setting num\_paths to 2 will increase complexity somewhat, but can lead to better convergence.

**3.6.4.406 HYPRE\_ParCSRHybridSetNumSweeps()**

```
HYPRE_Int HYPRE_ParCSRHybridSetNumSweeps (
    HYPRE_Solver solver,
    HYPRE_Int num_sweeps )
```

(Optional) Sets the number of sweeps. On the finest level, the up and the down cycle the number of sweeps are set to num\_sweeps and on the coarsest level to 1. The default is 1.

**3.6.4.407 HYPRE\_ParCSRHybridSetOmega()**

```
HYPRE_Int HYPRE_ParCSRHybridSetOmega (
    HYPRE_Solver solver,
    HYPRE_Real * omega )
```

**3.6.4.408 HYPRE\_ParCSRHybridSetOuterWt()**

```
HYPRE_Int HYPRE_ParCSRHybridSetOuterWt (
    HYPRE_Solver solver,
    HYPRE_Real outer_wt )
```

(Optional) Defines the outer relaxation weight for hybrid SOR and SSOR on all levels.

Values for *outer\_wt* are

- $> 0$  : this assigns the same outer relaxation weight omega on each level
- $= -k$  : an outer relaxation weight is determined with at most k CG steps on each level (this only makes sense for symmetric positive definite problems and smoothers such as SSOR)

The default is 1.

**3.6.4.409 HYPRE\_ParCSRHybridSetPCGMaxIter()**

```
HYPRE_Int HYPRE_ParCSRHybridSetPCGMaxIter (
    HYPRE_Solver solver,
    HYPRE_Int pcg_max_its )
```

Set the maximal number of iterations for the AMG preconditioned solver

**3.6.4.410 HYPRE\_ParCSRHybridSetPMaxElmts()**

```
HYPRE_Int HYPRE_ParCSRHybridSetPMaxElmts (
    HYPRE_Solver solver,
    HYPRE_Int P_max_elmts )
```

(Optional) Defines the maximal number of elements per row for the interpolation. The default is 0.

**3.6.4.411 HYPRE\_ParCSRHybridSetPrecond()**

```
HYPRE_Int HYPRE_ParCSRHybridSetPrecond (
    HYPRE_Solver solver,
    HYPRE_PtrToParSolverFcn precondition,
    HYPRE_PtrToParSolverFcn precondition_setup,
    HYPRE_Solver precondition_solver )
```

Set preconditioner if wanting to use one that is not set up by the hybrid solver.

**3.6.4.412 HYPRE\_ParCSRHybridSetPrintLevel()**

```
HYPRE_Int HYPRE_ParCSRHybridSetPrintLevel (
    HYPRE_Solver solver,
    HYPRE_Int print_level )
```

Set print level (default: 0, no printing) 2 will print residual norms per iteration 10 will print AMG setup information if AMG is used 12 both Setup information and iterations.

**3.6.4.413 HYPRE\_ParCSRHybridSetRecomputeResidual()**

```
HYPRE_Int HYPRE_ParCSRHybridSetRecomputeResidual (
    HYPRE_Solver solver,
    HYPRE_Int recompute_residual )
```

(Optional) Set recompute residual (don't rely on 3-term recurrence).

**3.6.4.414 HYPRE\_ParCSRHybridSetRecomputeResidualP()**

```
HYPRE_Int HYPRE_ParCSRHybridSetRecomputeResidualP (
    HYPRE_Solver solver,
    HYPRE_Int recompute_residual_p )
```

(Optional) Set recompute residual period (don't rely on 3-term recurrence).

Recomputes residual after every specified number of iterations.

**3.6.4.415 HYPRE\_ParCSRHybridSetRelaxOrder()**

```
HYPRE_Int HYPRE_ParCSRHybridSetRelaxOrder (
    HYPRE_Solver solver,
    HYPRE_Int relax_order )
```

(Optional) Defines in which order the points are relaxed. There are the following options for *relax\_order*:

- 0 : the points are relaxed in natural or lexicographic order on each processor
- 1 : CF-relaxation is used, i.e on the fine grid and the down cycle the coarse points are relaxed first, followed by the fine points; on the up cycle the F-points are relaxed first, followed by the C-points. On the coarsest level, if an iterative scheme is used, the points are relaxed in lexicographic order.

The default is 0 (CF-relaxation).



**3.6.4.416 HYPRE\_ParCSRHybridSetRelaxType()**

```
HYPRE_Int HYPRE_ParCSRHybridSetRelaxType (
    HYPRE_Solver solver,
    HYPRE_Int relax_type )
```

(Optional) Defines the smoother to be used. It uses the given smoother on the fine grid, the up and the down cycle and sets the solver on the coarsest level to Gaussian elimination (9). The default is l1-Gauss-Seidel, forward solve on the down cycle (13) and backward solve on the up cycle (14).

There are the following options for *relax\_type*:

- 0 : Jacobi
- 1 : Gauss-Seidel, sequential (very slow!)
- 2 : Gauss-Seidel, interior points in parallel, boundary sequential (slow!)
- 3 : hybrid Gauss-Seidel or SOR, forward solve
- 4 : hybrid Gauss-Seidel or SOR, backward solve
- 6 : hybrid symmetric Gauss-Seidel or SSOR
- 8 : hybrid symmetric l1-Gauss-Seidel or SSOR
- 13 : l1-Gauss-Seidel, forward solve
- 14 : l1-Gauss-Seidel, backward solve
- 18 : l1-Jacobi
- 9 : Gaussian elimination (only on coarsest level)

**3.6.4.417 HYPRE\_ParCSRHybridSetRelaxWeight()**

```
HYPRE_Int HYPRE_ParCSRHybridSetRelaxWeight (
    HYPRE_Solver solver,
    HYPRE_Real * relax_weight )
```

**3.6.4.418 HYPRE\_ParCSRHybridSetRelaxWt()**

```
HYPRE_Int HYPRE_ParCSRHybridSetRelaxWt (
    HYPRE_Solver solver,
    HYPRE_Real relax_wt )
```

(Optional) Defines the relaxation weight for smoothed Jacobi and hybrid SOR on all levels.

Values for *relax\_wt* are

- $> 0$  : this assigns the given relaxation weight on all levels
- $= 0$  : the weight is determined on each level with the estimate  $\frac{3}{4\|D^{-1/2}AD^{-1/2}\|}$ , where  $D$  is the diagonal of  $A$  (this should only be used with Jacobi)
- $= -k$  : the relaxation weight is determined with at most  $k$  CG steps on each level (this should only be used for symmetric positive definite problems)

The default is 1.

**3.6.4.419 HYPRE\_ParCSRHybridSetRelChange()**

```
HYPRE_Int HYPRE_ParCSRHybridSetRelChange (
    HYPRE_Solver solver,
    HYPRE_Int rel_change )
```

**3.6.4.420 HYPRE\_ParCSRHybridSetSeqThreshold()**

```
HYPRE_Int HYPRE_ParCSRHybridSetSeqThreshold (
    HYPRE_Solver solver,
    HYPRE_Int seq_threshold )
```

(Optional) enables redundant coarse grid size. If the system size becomes smaller than seq\_threshold, sequential AMG is used on all remaining processors. The default is 0.

**3.6.4.421 HYPRE\_ParCSRHybridSetSetupType()**

```
HYPRE_Int HYPRE_ParCSRHybridSetSetupType (
    HYPRE_Solver solver,
    HYPRE_Int setup_type )
```

**3.6.4.422 HYPRE\_ParCSRHybridSetSolverType()**

```
HYPRE_Int HYPRE_ParCSRHybridSetSolverType (
    HYPRE_Solver solver,
    HYPRE_Int solver_type )
```

Set the desired solver type. There are the following options:

- 1 : PCG (default)
- 2 : GMRES
- 3 : BiCGSTAB

**3.6.4.423 HYPRE\_ParCSRHybridSetStopCrit()**

```
HYPRE_Int HYPRE_ParCSRHybridSetStopCrit (
    HYPRE_Solver solver,
    HYPRE_Int stop_crit )
```

RE-VISIT

**3.6.4.424 HYPRE\_ParCSRHybridSetStrongThreshold()**

```
HYPRE_Int HYPRE_ParCSRHybridSetStrongThreshold (
    HYPRE_Solver solver,
    HYPRE_Real strong_threshold )
```

(Optional) Sets AMG strength threshold. The default is 0.25. For elasticity problems, a larger strength threshold, such as 0.7 or 0.8, is often better.

**3.6.4.425 HYPRE\_ParCSRHybridSetTol()**

```
HYPRE_Int HYPRE_ParCSRHybridSetTol (
    HYPRE_Solver solver,
    HYPRE_Real tol )
```

Set the convergence tolerance for the Krylov solver. The default is 1.e-6.

**3.6.4.426 HYPRE\_ParCSRHybridSetTruncFactor()**

```
HYPRE_Int HYPRE_ParCSRHybridSetTruncFactor (
    HYPRE_Solver solver,
    HYPRE_Real trunc_factor )
```

(Optional) Defines a truncation factor for the interpolation. The default is 0.

**3.6.4.427 HYPRE\_ParCSRHybridSetTwoNorm()**

```
HYPRE_Int HYPRE_ParCSRHybridSetTwoNorm (
    HYPRE_Solver solver,
    HYPRE_Int two_norm )
```

Set the type of norm for PCG.

**3.6.4.428 HYPRE\_ParCSRHybridSetup()**

```
HYPRE_Int HYPRE_ParCSRHybridSetup (
    HYPRE_Solver solver,
    HYPRE_ParCSRMatrix A,
    HYPRE_ParVector b,
    HYPRE_ParVector x )
```

Setup the hybrid solver

**Parameters**

<i>solver</i>	[IN] object to be set up.
<i>A</i>	[IN] ParCSR matrix used to construct the solver/preconditioner.
<i>b</i>	Ignored by this function.
<i>x</i>	Ignored by this function.

**3.6.4.429 HYPRE\_ParCSRHybridSolve()**

```
HYPRE_Int HYPRE_ParCSRHybridSolve (
    HYPRE_Solver solver,
    HYPRE_ParCSRMatrix A,
    HYPRE_ParVector b,
    HYPRE_ParVector x )
```

Solve linear system

## Parameters

<i>solver</i>	[IN] solver or preconditioner object to be applied.
<i>A</i>	[IN] ParCSR matrix, matrix of the linear system to be solved
<i>b</i>	[IN] right hand side of the linear system to be solved
<i>x</i>	[OUT] approximated solution of the linear system to be solved

**3.6.4.430 HYPRE\_ParCSRLGMRESCreate()**

```
HYPRE_Int HYPRE_ParCSRLGMRESCreate (
    MPI_Comm comm,
    HYPRE_Solver * solver )
```

Create a solver object.

**3.6.4.431 HYPRE\_ParCSRLGMRESDestroy()**

```
HYPRE_Int HYPRE_ParCSRLGMRESDestroy (
    HYPRE_Solver solver )
```

Destroy a solver object.

**3.6.4.432 HYPRE\_ParCSRLGMRESGetFinalRelativeResidualNorm()**

```
HYPRE_Int HYPRE_ParCSRLGMRESGetFinalRelativeResidualNorm (
    HYPRE_Solver solver,
    HYPRE_Real * norm )
```

**3.6.4.433 HYPRE\_ParCSRLGMRESGetNumIterations()**

```
HYPRE_Int HYPRE_ParCSRLGMRESGetNumIterations (
    HYPRE_Solver solver,
    HYPRE_Int * num_iterations )
```

**3.6.4.434 HYPRE\_ParCSRLGMRESGetPrecond()**

```
HYPRE_Int HYPRE_ParCSRLGMRESGetPrecond (
    HYPRE_Solver solver,
    HYPRE_Solver * precondition_data )
```

**3.6.4.435 HYPRE\_ParCSRLGMRESGetResidual()**

```
HYPRE_Int HYPRE_ParCSRLGMRESGetResidual (
    HYPRE_Solver solver,
    HYPRE_ParVector * residual )
```

**3.6.4.436 HYPRE\_ParCSRLGMRESSetAbsoluteTol()**

```
HYPRE_Int HYPRE_ParCSRLGMRESSetAbsoluteTol (
    HYPRE_Solver solver,
    HYPRE_Real a_tol )
```

**3.6.4.437 HYPRE\_ParCSRLGMRESSetAugDim()**

```
HYPRE_Int HYPRE_ParCSRLGMRESSetAugDim (
    HYPRE_Solver solver,
    HYPRE_Int aug_dim )
```

**3.6.4.438 HYPRE\_ParCSRLGMRESSetKDim()**

```
HYPRE_Int HYPRE_ParCSRLGMRESSetKDim (
    HYPRE_Solver solver,
    HYPRE_Int k_dim )
```

**3.6.4.439 HYPRE\_ParCSRLGMRESSetLogging()**

```
HYPRE_Int HYPRE_ParCSRLGMRESSetLogging (
    HYPRE_Solver solver,
    HYPRE_Int logging )
```

**3.6.4.440 HYPRE\_ParCSRLGMRESSetMaxIter()**

```
HYPRE_Int HYPRE_ParCSRLGMRESSetMaxIter (
    HYPRE_Solver solver,
    HYPRE_Int max_iter )
```

**3.6.4.441 HYPRE\_ParCSRLGMRESSetMinIter()**

```
HYPRE_Int HYPRE_ParCSRLGMRESSetMinIter (
    HYPRE_Solver solver,
    HYPRE_Int min_iter )
```

**3.6.4.442 HYPRE\_ParCSRLGMRESSetPrecond()**

```
HYPRE_Int HYPRE_ParCSRLGMRESSetPrecond (
    HYPRE_Solver solver,
    HYPRE_PtrToParSolverFcn precondition,
    HYPRE_PtrToParSolverFcn precondition_setup,
    HYPRE_Solver precondition_solver )
```

**3.6.4.443 HYPRE\_ParCSRLGMRESsetPrintLevel()**

```
HYPRE_Int HYPRE_ParCSRLGMRESsetPrintLevel (
    HYPRE_Solver solver,
    HYPRE_Int print_level )
```

**3.6.4.444 HYPRE\_ParCSRLGMRESsetTol()**

```
HYPRE_Int HYPRE_ParCSRLGMRESsetTol (
    HYPRE_Solver solver,
    HYPRE_Real tol )
```

**3.6.4.445 HYPRE\_ParCSRLGMRESsetup()**

```
HYPRE_Int HYPRE_ParCSRLGMRESsetup (
    HYPRE_Solver solver,
    HYPRE_ParCSRMatrix A,
    HYPRE_ParVector b,
    HYPRE_ParVector x )
```

**3.6.4.446 HYPRE\_ParCSRLGMRESSolve()**

```
HYPRE_Int HYPRE_ParCSRLGMRESSolve (
    HYPRE_Solver solver,
    HYPRE_ParCSRMatrix A,
    HYPRE_ParVector b,
    HYPRE_ParVector x )
```

**3.6.4.447 HYPRE\_ParCSRMultiVectorPrint()**

```
HYPRE_Int HYPRE_ParCSRMultiVectorPrint (
    void * x_,
    const char * fileName )
```

**3.6.4.448 HYPRE\_ParCSRMultiVectorRead()**

```
void * HYPRE_ParCSRMultiVectorRead (
    MPI_Comm comm,
    void * ii_,
    const char * fileName )
```

**3.6.4.449 HYPRE\_ParCSROnProcTriSetup()**

```
HYPRE_Int HYPRE_ParCSROnProcTriSetup (
    HYPRE_Solver solver,
    HYPRE_ParCSRMatrix HA,
    HYPRE_ParVector Hy,
    HYPRE_ParVector Hx )
```

**3.6.4.450 HYPRE\_ParCSROnProcTriSolve()**

```
HYPRE_Int HYPRE_ParCSROnProcTriSolve (
    HYPRE_Solver solver,
    HYPRE_ParCSRMatrix HA,
    HYPRE_ParVector Hy,
    HYPRE_ParVector Hx )
```

**3.6.4.451 HYPRE\_ParCSRParaSailsCreate()**

```
HYPRE_Int HYPRE_ParCSRParaSailsCreate (
    MPI_Comm comm,
    HYPRE_Solver * solver )
```

**3.6.4.452 HYPRE\_ParCSRParaSailsDestroy()**

```
HYPRE_Int HYPRE_ParCSRParaSailsDestroy (
    HYPRE_Solver solver )
```

**3.6.4.453 HYPRE\_ParCSRParaSailsSetFilter()**

```
HYPRE_Int HYPRE_ParCSRParaSailsSetFilter (
    HYPRE_Solver solver,
    HYPRE_Real filter )
```

**3.6.4.454 HYPRE\_ParCSRParaSailsSetLoadbal()**

```
HYPRE_Int HYPRE_ParCSRParaSailsSetLoadbal (
    HYPRE_Solver solver,
    HYPRE_Real loadbal )
```

**3.6.4.455 HYPRE\_ParCSRParaSailsSetLogging()**

```
HYPRE_Int HYPRE_ParCSRParaSailsSetLogging (
    HYPRE_Solver solver,
    HYPRE_Int logging )
```

**3.6.4.456 HYPRE\_ParCSRParaSailsSetParams()**

```
HYPRE_Int HYPRE_ParCSRParaSailsSetParams (
    HYPRE_Solver solver,
    HYPRE_Real thresh,
    HYPRE_Int nlevels )
```



**3.6.4.457 HYPRE\_ParCSRParaSailsSetReuse()**

```
HYPRE_Int HYPRE_ParCSRParaSailsSetReuse (
    HYPRE_Solver solver,
    HYPRE_Int reuse )
```

**3.6.4.458 HYPRE\_ParCSRParaSailsSetSym()**

```
HYPRE_Int HYPRE_ParCSRParaSailsSetSym (
    HYPRE_Solver solver,
    HYPRE_Int sym )
```

**3.6.4.459 HYPRE\_ParCSRParaSailsSetup()**

```
HYPRE_Int HYPRE_ParCSRParaSailsSetup (
    HYPRE_Solver solver,
    HYPRE_ParCSRMatrix A,
    HYPRE_ParVector b,
    HYPRE_ParVector x )
```

**3.6.4.460 HYPRE\_ParCSRParaSailsSolve()**

```
HYPRE_Int HYPRE_ParCSRParaSailsSolve (
    HYPRE_Solver solver,
    HYPRE_ParCSRMatrix A,
    HYPRE_ParVector b,
    HYPRE_ParVector x )
```

**3.6.4.461 HYPRE\_ParCSRPCGCreate()**

```
HYPRE_Int HYPRE_ParCSRPCGCreate (
    MPI_Comm comm,
    HYPRE_Solver * solver )
```

Create a solver object.

**3.6.4.462 HYPRE\_ParCSRPCGDestroy()**

```
HYPRE_Int HYPRE_ParCSRPCGDestroy (
    HYPRE_Solver solver )
```

Destroy a solver object.

**3.6.4.463 HYPRE\_ParCSRPCGGetFinalRelativeResidualNorm()**

```
HYPRE_Int HYPRE_ParCSRPCGGetFinalRelativeResidualNorm (
    HYPRE_Solver solver,
    HYPRE_Real * norm )
```

**3.6.4.464 HYPRE\_ParCSRPCGGetNumIterations()**

```
HYPRE_Int HYPRE_ParCSRPCGGetNumIterations (
    HYPRE_Solver solver,
    HYPRE_Int * num_iterations )
```

**3.6.4.465 HYPRE\_ParCSRPCGGetPrecond()**

```
HYPRE_Int HYPRE_ParCSRPCGGetPrecond (
    HYPRE_Solver solver,
    HYPRE_Solver * precondition_data )
```

**3.6.4.466 HYPRE\_ParCSRPCGGetResidual()**

```
HYPRE_Int HYPRE_ParCSRPCGGetResidual (
    HYPRE_Solver solver,
    HYPRE_ParVector * residual )
```

Returns the residual.

**3.6.4.467 HYPRE\_ParCSRPCGSetAbsoluteTol()**

```
HYPRE_Int HYPRE_ParCSRPCGSetAbsoluteTol (
    HYPRE_Solver solver,
    HYPRE_Real tol )
```

**3.6.4.468 HYPRE\_ParCSRPCGSetLogging()**

```
HYPRE_Int HYPRE_ParCSRPCGSetLogging (
    HYPRE_Solver solver,
    HYPRE_Int logging )
```

**3.6.4.469 HYPRE\_ParCSRPCGSetMaxIter()**

```
HYPRE_Int HYPRE_ParCSRPCGSetMaxIter (
    HYPRE_Solver solver,
    HYPRE_Int max_iter )
```

**3.6.4.470 HYPRE\_ParCSRPCGSetPrecond()**

```
HYPRE_Int HYPRE_ParCSRPCGSetPrecond (
    HYPRE_Solver solver,
    HYPRE_PtrToParSolverFcn precondition,
    HYPRE_PtrToParSolverFcn precondition_setup,
    HYPRE_Solver precondition_solver )
```

**3.6.4.471 HYPRE\_ParCSRPCGSetPrintLevel()**

```
HYPRE_Int HYPRE_ParCSRPCGSetPrintLevel (
    HYPRE_Solver solver,
    HYPRE_Int print_level )
```

**3.6.4.472 HYPRE\_ParCSRPCGSetRelChange()**

```
HYPRE_Int HYPRE_ParCSRPCGSetRelChange (
    HYPRE_Solver solver,
    HYPRE_Int rel_change )
```

**3.6.4.473 HYPRE\_ParCSRPCGSetStopCrit()**

```
HYPRE_Int HYPRE_ParCSRPCGSetStopCrit (
    HYPRE_Solver solver,
    HYPRE_Int stop_crit )
```

**3.6.4.474 HYPRE\_ParCSRPCGSetTol()**

```
HYPRE_Int HYPRE_ParCSRPCGSetTol (
    HYPRE_Solver solver,
    HYPRE_Real tol )
```

**3.6.4.475 HYPRE\_ParCSRPCGSetTwoNorm()**

```
HYPRE_Int HYPRE_ParCSRPCGSetTwoNorm (
    HYPRE_Solver solver,
    HYPRE_Int two_norm )
```

**3.6.4.476 HYPRE\_ParCSRPCGSetup()**

```
HYPRE_Int HYPRE_ParCSRPCGSetup (
    HYPRE_Solver solver,
    HYPRE_ParCSRMatrix A,
    HYPRE_ParVector b,
    HYPRE_ParVector x )
```

**3.6.4.477 HYPRE\_ParCSRPCGSolve()**

```
HYPRE_Int HYPRE_ParCSRPCGSolve (
    HYPRE_Solver solver,
    HYPRE_ParCSRMatrix A,
    HYPRE_ParVector b,
    HYPRE_ParVector x )
```

#### 3.6.4.478 HYPRE\_ParCSRPilutCreate()

```
HYPRE_Int HYPRE_ParCSRPilutCreate (
    MPI_Comm comm,
    HYPRE_Solver * solver )
```

Create a preconditioner object.

#### 3.6.4.479 HYPRE\_ParCSRPilutDestroy()

```
HYPRE_Int HYPRE_ParCSRPilutDestroy (
    HYPRE_Solver solver )
```

Destroy a preconditioner object.

#### 3.6.4.480 HYPRE\_ParCSRPilutSetDropTolerance()

```
HYPRE_Int HYPRE_ParCSRPilutSetDropTolerance (
    HYPRE_Solver solver,
    HYPRE_Real tol )
```

(Optional)

#### 3.6.4.481 HYPRE\_ParCSRPilutSetFactorRowSize()

```
HYPRE_Int HYPRE_ParCSRPilutSetFactorRowSize (
    HYPRE_Solver solver,
    HYPRE_Int size )
```

(Optional)

#### 3.6.4.482 HYPRE\_ParCSRPilutSetLogging()

```
HYPRE_Int HYPRE_ParCSRPilutSetLogging (
    HYPRE_Solver solver,
    HYPRE_Int logging )
```

#### 3.6.4.483 HYPRE\_ParCSRPilutSetMaxIter()

```
HYPRE_Int HYPRE_ParCSRPilutSetMaxIter (
    HYPRE_Solver solver,
    HYPRE_Int max_iter )
```

(Optional) Set maximum number of iterations.

**3.6.4.484 HYPRE\_ParCSRPilutSetup()**

```
HYPRE_Int HYPRE_ParCSRPilutSetup (
    HYPRE_Solver solver,
    HYPRE_ParCSRMatrix A,
    HYPRE_ParVector b,
    HYPRE_ParVector x )
```

**3.6.4.485 HYPRE\_ParCSRPilutSolve()**

```
HYPRE_Int HYPRE_ParCSRPilutSolve (
    HYPRE_Solver solver,
    HYPRE_ParCSRMatrix A,
    HYPRE_ParVector b,
    HYPRE_ParVector x )
```

Precondition the system.

**3.6.4.486 HYPRE\_ParCSRSetupInterpreter()**

```
HYPRE_Int HYPRE_ParCSRSetupInterpreter (
    mv_InterfaceInterpreter * i )
```

Load interface interpreter. Vector part loaded with hypre\_ParkKrylov functions and multivector part loaded with mv↔\_TempMultiVector functions.

**3.6.4.487 HYPRE\_ParCSRSetupMatvec()**

```
HYPRE_Int HYPRE_ParCSRSetupMatvec (
    HYPRE_MatvecFunctions * mv )
```

Load Matvec interpreter with hypre\_ParkKrylov functions.

**3.6.4.488 HYPRE\_SchwarzCreate()**

```
HYPRE_Int HYPRE_SchwarzCreate (
    HYPRE_Solver * solver )
```

**3.6.4.489 HYPRE\_SchwarzDestroy()**

```
HYPRE_Int HYPRE_SchwarzDestroy (
    HYPRE_Solver solver )
```

**3.6.4.490 HYPRE\_SchwarzSetDofFunc()**

```
HYPRE_Int HYPRE_SchwarzSetDofFunc (
    HYPRE_Solver solver,
    HYPRE_Int * dof_func )
```

**3.6.4.491 HYPRE\_SchwarzSetDomainStructure()**

```
HYPRE_Int HYPRE_SchwarzSetDomainStructure (
    HYPRE_Solver solver,
    HYPRE_CSRMatrix domain_structure )
```

**3.6.4.492 HYPRE\_SchwarzSetDomainType()**

```
HYPRE_Int HYPRE_SchwarzSetDomainType (
    HYPRE_Solver solver,
    HYPRE_Int domain_type )
```

**3.6.4.493 HYPRE\_SchwarzSetNonSymm()**

```
HYPRE_Int HYPRE_SchwarzSetNonSymm (
    HYPRE_Solver solver,
    HYPRE_Int use_nonsymm )
```

**3.6.4.494 HYPRE\_SchwarzSetNumFunctions()**

```
HYPRE_Int HYPRE_SchwarzSetNumFunctions (
    HYPRE_Solver solver,
    HYPRE_Int num_functions )
```

**3.6.4.495 HYPRE\_SchwarzSetOverlap()**

```
HYPRE_Int HYPRE_SchwarzSetOverlap (
    HYPRE_Solver solver,
    HYPRE_Int overlap )
```

**3.6.4.496 HYPRE\_SchwarzSetRelaxWeight()**

```
HYPRE_Int HYPRE_SchwarzSetRelaxWeight (
    HYPRE_Solver solver,
    HYPRE_Real relax_weight )
```

**3.6.4.497 HYPRE\_SchwarzSetup()**

```
HYPRE_Int HYPRE_SchwarzSetup (
    HYPRE_Solver solver,
    HYPRE_ParCSRMatrix A,
    HYPRE_ParVector b,
    HYPRE_ParVector x )
```

**3.6.4.498 HYPRE\_SchwarzSetVariant()**

```
HYPRE_Int HYPRE_SchwarzSetVariant (
    HYPRE_Solver solver,
    HYPRE_Int variant )
```

**3.6.4.499 HYPRE\_SchwarzSolve()**

```
HYPRE_Int HYPRE_SchwarzSolve (
    HYPRE_Solver solver,
    HYPRE_ParCSRMatrix A,
    HYPRE_ParVector b,
    HYPRE_ParVector x )
```

## 3.7 Krylov Solvers

### Krylov Solvers

- typedef struct hypre\_Solver\_struct \* [HYPRE\\_Solver](#)
- typedef struct hypre\_Matrix\_struct \* [HYPRE\\_Matrix](#)
- typedef struct hypre\_Vector\_struct \* [HYPRE\\_Vector](#)
- typedef HYPRE\_Int(\* [HYPRE\\_PtrToSolverFcn](#)) ([HYPRE\\_Solver](#), [HYPRE\\_Matrix](#), [HYPRE\\_Vector](#), [HYPRE\\_Vector](#))
- typedef HYPRE\_Int(\* [HYPRE\\_PtrToModifyPCFcn](#)) ([HYPRE\\_Solver](#), HYPRE\_Int, HYPRE\_Real)
- #define [HYPRE\\_SOLVER\\_STRUCT](#)
- #define [HYPRE\\_MATRIX\\_STRUCT](#)
- #define [HYPRE\\_VECTOR\\_STRUCT](#)
- #define [HYPRE\\_MODIFYPC](#)

### PCG Solver

- HYPRE\_Int [HYPRE\\_PCGSetup](#) ([HYPRE\\_Solver](#) solver, [HYPRE\\_Matrix](#) A, [HYPRE\\_Vector](#) b, [HYPRE\\_Vector](#) x)
- HYPRE\_Int [HYPRE\\_PCGSolve](#) ([HYPRE\\_Solver](#) solver, [HYPRE\\_Matrix](#) A, [HYPRE\\_Vector](#) b, [HYPRE\\_Vector](#) x)
- HYPRE\_Int [HYPRE\\_PCGSetTol](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_PCGSetAbsoluteTol](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Real a\_tol)
- HYPRE\_Int [HYPRE\\_PCGSetResidualTol](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Real rtol)
- HYPRE\_Int [HYPRE\\_PCGSetAbsoluteTolFactor](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Real abstolf)
- HYPRE\_Int [HYPRE\\_PCGSetConvergenceFactorTol](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Real cf\_tol)
- HYPRE\_Int [HYPRE\\_PCGSetStopCrit](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int stop\_crit)
- HYPRE\_Int [HYPRE\\_PCGSetMaxIter](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int max\_iter)
- HYPRE\_Int [HYPRE\\_PCGSetTwoNorm](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int two\_norm)
- HYPRE\_Int [HYPRE\\_PCGSetRelChange](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int rel\_change)
- HYPRE\_Int [HYPRE\\_PCGSetRecomputeResidual](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int recompute\_residual)
- HYPRE\_Int [HYPRE\\_PCGSetRecomputeResidualP](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int recompute\_↵ residual\_p)
- HYPRE\_Int [HYPRE\\_PCGSetPrecond](#) ([HYPRE\\_Solver](#) solver, [HYPRE\\_PtrToSolverFcn](#) precondition, [HYPRE\\_PtrToSolverFcn](#) precondition\_setup, [HYPRE\\_Solver](#) precondition\_solver)
- HYPRE\_Int [HYPRE\\_PCGSetLogging](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int logging)
- HYPRE\_Int [HYPRE\\_PCGSetPrintLevel](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int level)

- HYPRE\_Int [HYPRE\\_PCGGetNumIterations](#) (HYPRE\_Solver solver, HYPRE\_Int \*num\_iterations)
- HYPRE\_Int [HYPRE\\_PCGGetFinalRelativeResidualNorm](#) (HYPRE\_Solver solver, HYPRE\_Real \*norm)
- HYPRE\_Int [HYPRE\\_PCGGetResidual](#) (HYPRE\_Solver solver, void \*residual)
- HYPRE\_Int [HYPRE\\_PCGGetTol](#) (HYPRE\_Solver solver, HYPRE\_Real \*tol)
- HYPRE\_Int [HYPRE\\_PCGGetResidualTol](#) (HYPRE\_Solver solver, HYPRE\_Real \*rtol)
- HYPRE\_Int [HYPRE\\_PCGGetAbsoluteTolFactor](#) (HYPRE\_Solver solver, HYPRE\_Real \*abstolf)
- HYPRE\_Int [HYPRE\\_PCGGetConvergenceFactorTol](#) (HYPRE\_Solver solver, HYPRE\_Real \*cf\_tol)
- HYPRE\_Int [HYPRE\\_PCGGetStopCrit](#) (HYPRE\_Solver solver, HYPRE\_Int \*stop\_crit)
- HYPRE\_Int [HYPRE\\_PCGGetMaxIter](#) (HYPRE\_Solver solver, HYPRE\_Int \*max\_iter)
- HYPRE\_Int [HYPRE\\_PCGGetTwoNorm](#) (HYPRE\_Solver solver, HYPRE\_Int \*two\_norm)
- HYPRE\_Int [HYPRE\\_PCGGetRelChange](#) (HYPRE\_Solver solver, HYPRE\_Int \*rel\_change)
- HYPRE\_Int [HYPRE\\_GMRESGetSkipRealResidualCheck](#) (HYPRE\_Solver solver, HYPRE\_Int \*skip\_real\_r\_check)
- HYPRE\_Int [HYPRE\\_PCGGetPrecond](#) (HYPRE\_Solver solver, HYPRE\_Solver \*precond\_data\_ptr)
- HYPRE\_Int [HYPRE\\_PCGGetLogging](#) (HYPRE\_Solver solver, HYPRE\_Int \*level)
- HYPRE\_Int [HYPRE\\_PCGGetPrintLevel](#) (HYPRE\_Solver solver, HYPRE\_Int \*level)
- HYPRE\_Int [HYPRE\\_PCGGetConverged](#) (HYPRE\_Solver solver, HYPRE\_Int \*converged)

## GMRES Solver

- HYPRE\_Int [HYPRE\\_GMRESSetup](#) (HYPRE\_Solver solver, HYPRE\_Matrix A, HYPRE\_Vector b, HYPRE\_Vector x)
- HYPRE\_Int [HYPRE\\_GMRESSolve](#) (HYPRE\_Solver solver, HYPRE\_Matrix A, HYPRE\_Vector b, HYPRE\_Vector x)
- HYPRE\_Int [HYPRE\\_GMRESSetTol](#) (HYPRE\_Solver solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_GMRESSetAbsoluteTol](#) (HYPRE\_Solver solver, HYPRE\_Real a\_tol)
- HYPRE\_Int [HYPRE\\_GMRESSetConvergenceFactorTol](#) (HYPRE\_Solver solver, HYPRE\_Real cf\_tol)
- HYPRE\_Int [HYPRE\\_GMRESSetStopCrit](#) (HYPRE\_Solver solver, HYPRE\_Int stop\_crit)
- HYPRE\_Int [HYPRE\\_GMRESSetMinIter](#) (HYPRE\_Solver solver, HYPRE\_Int min\_iter)
- HYPRE\_Int [HYPRE\\_GMRESSetMaxIter](#) (HYPRE\_Solver solver, HYPRE\_Int max\_iter)
- HYPRE\_Int [HYPRE\\_GMRESSetKDim](#) (HYPRE\_Solver solver, HYPRE\_Int k\_dim)
- HYPRE\_Int [HYPRE\\_GMRESSetRelChange](#) (HYPRE\_Solver solver, HYPRE\_Int rel\_change)
- HYPRE\_Int [HYPRE\\_GMRESSetSkipRealResidualCheck](#) (HYPRE\_Solver solver, HYPRE\_Int skip\_real\_r\_check)
- HYPRE\_Int [HYPRE\\_GMRESSetPrecond](#) (HYPRE\_Solver solver, HYPRE\_PtrToSolverFcn precondition, HYPRE\_PtrToSolverFcn precondition\_setup, HYPRE\_Solver precondition\_solver)
- HYPRE\_Int [HYPRE\\_GMRESSetLogging](#) (HYPRE\_Solver solver, HYPRE\_Int logging)
- HYPRE\_Int [HYPRE\\_GMRESSetPrintLevel](#) (HYPRE\_Solver solver, HYPRE\_Int level)
- HYPRE\_Int [HYPRE\\_GMRESGetNumIterations](#) (HYPRE\_Solver solver, HYPRE\_Int \*num\_iterations)
- HYPRE\_Int [HYPRE\\_GMRESGetFinalRelativeResidualNorm](#) (HYPRE\_Solver solver, HYPRE\_Real \*norm)
- HYPRE\_Int [HYPRE\\_GMRESGetResidual](#) (HYPRE\_Solver solver, void \*residual)
- HYPRE\_Int [HYPRE\\_GMRESGetTol](#) (HYPRE\_Solver solver, HYPRE\_Real \*tol)
- HYPRE\_Int [HYPRE\\_GMRESGetAbsoluteTol](#) (HYPRE\_Solver solver, HYPRE\_Real \*tol)
- HYPRE\_Int [HYPRE\\_GMRESGetConvergenceFactorTol](#) (HYPRE\_Solver solver, HYPRE\_Real \*cf\_tol)
- HYPRE\_Int [HYPRE\\_GMRESGetStopCrit](#) (HYPRE\_Solver solver, HYPRE\_Int \*stop\_crit)
- HYPRE\_Int [HYPRE\\_GMRESGetMinIter](#) (HYPRE\_Solver solver, HYPRE\_Int \*min\_iter)
- HYPRE\_Int [HYPRE\\_GMRESGetMaxIter](#) (HYPRE\_Solver solver, HYPRE\_Int \*max\_iter)
- HYPRE\_Int [HYPRE\\_GMRESGetKDim](#) (HYPRE\_Solver solver, HYPRE\_Int \*k\_dim)
- HYPRE\_Int [HYPRE\\_GMRESGetRelChange](#) (HYPRE\_Solver solver, HYPRE\_Int \*rel\_change)
- HYPRE\_Int [HYPRE\\_GMRESGetPrecond](#) (HYPRE\_Solver solver, HYPRE\_Solver \*precond\_data\_ptr)
- HYPRE\_Int [HYPRE\\_GMRESGetLogging](#) (HYPRE\_Solver solver, HYPRE\_Int \*level)
- HYPRE\_Int [HYPRE\\_GMRESGetPrintLevel](#) (HYPRE\_Solver solver, HYPRE\_Int \*level)
- HYPRE\_Int [HYPRE\\_GMRESGetConverged](#) (HYPRE\_Solver solver, HYPRE\_Int \*converged)



**FlexGMRES Solver**

- HYPRE\_Int [HYPRE\\_FlexGMRESSetup](#) (HYPRE\_Solver solver, HYPRE\_Matrix A, HYPRE\_Vector b, HYPRE\_Vector x)
- HYPRE\_Int [HYPRE\\_FlexGMRESSolve](#) (HYPRE\_Solver solver, HYPRE\_Matrix A, HYPRE\_Vector b, HYPRE\_Vector x)
- HYPRE\_Int [HYPRE\\_FlexGMRESSetTol](#) (HYPRE\_Solver solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_FlexGMRESSetAbsoluteTol](#) (HYPRE\_Solver solver, HYPRE\_Real a\_tol)
- HYPRE\_Int [HYPRE\\_FlexGMRESSetConvergenceFactorTol](#) (HYPRE\_Solver solver, HYPRE\_Real cf\_tol)
- HYPRE\_Int [HYPRE\\_FlexGMRESSetMinIter](#) (HYPRE\_Solver solver, HYPRE\_Int min\_iter)
- HYPRE\_Int [HYPRE\\_FlexGMRESSetMaxIter](#) (HYPRE\_Solver solver, HYPRE\_Int max\_iter)
- HYPRE\_Int [HYPRE\\_FlexGMRESSetKDim](#) (HYPRE\_Solver solver, HYPRE\_Int k\_dim)
- HYPRE\_Int [HYPRE\\_FlexGMRESSetPrecond](#) (HYPRE\_Solver solver, HYPRE\_PtrToSolverFcn precondition, HYPRE\_PtrToSolverFcn precondition\_setup, HYPRE\_Solver precondition\_solver)
- HYPRE\_Int [HYPRE\\_FlexGMRESSetLogging](#) (HYPRE\_Solver solver, HYPRE\_Int logging)
- HYPRE\_Int [HYPRE\\_FlexGMRESSetPrintLevel](#) (HYPRE\_Solver solver, HYPRE\_Int level)
- HYPRE\_Int [HYPRE\\_FlexGMRESGetNumIterations](#) (HYPRE\_Solver solver, HYPRE\_Int \*num\_iterations)
- HYPRE\_Int [HYPRE\\_FlexGMRESGetFinalRelativeResidualNorm](#) (HYPRE\_Solver solver, HYPRE\_Real \*norm)
- HYPRE\_Int [HYPRE\\_FlexGMRESGetResidual](#) (HYPRE\_Solver solver, void \*residual)
- HYPRE\_Int [HYPRE\\_FlexGMRESGetTol](#) (HYPRE\_Solver solver, HYPRE\_Real \*tol)
- HYPRE\_Int [HYPRE\\_FlexGMRESGetConvergenceFactorTol](#) (HYPRE\_Solver solver, HYPRE\_Real \*cf\_tol)
- HYPRE\_Int [HYPRE\\_FlexGMRESGetStopCrit](#) (HYPRE\_Solver solver, HYPRE\_Int \*stop\_crit)
- HYPRE\_Int [HYPRE\\_FlexGMRESGetMinIter](#) (HYPRE\_Solver solver, HYPRE\_Int \*min\_iter)
- HYPRE\_Int [HYPRE\\_FlexGMRESGetMaxIter](#) (HYPRE\_Solver solver, HYPRE\_Int \*max\_iter)
- HYPRE\_Int [HYPRE\\_FlexGMRESGetKDim](#) (HYPRE\_Solver solver, HYPRE\_Int \*k\_dim)
- HYPRE\_Int [HYPRE\\_FlexGMRESGetPrecond](#) (HYPRE\_Solver solver, HYPRE\_Solver \*precond\_data\_ptr)
- HYPRE\_Int [HYPRE\\_FlexGMRESGetLogging](#) (HYPRE\_Solver solver, HYPRE\_Int \*level)
- HYPRE\_Int [HYPRE\\_FlexGMRESGetPrintLevel](#) (HYPRE\_Solver solver, HYPRE\_Int \*level)
- HYPRE\_Int [HYPRE\\_FlexGMRESGetConverged](#) (HYPRE\_Solver solver, HYPRE\_Int \*converged)
- HYPRE\_Int [HYPRE\\_FlexGMRESSetModifyPC](#) (HYPRE\_Solver solver, HYPRE\_PtrToModifyPCFcn modify\_pc)

**LGMRES Solver**

- HYPRE\_Int [HYPRE\\_LGMRESSetup](#) (HYPRE\_Solver solver, HYPRE\_Matrix A, HYPRE\_Vector b, HYPRE\_Vector x)
- HYPRE\_Int [HYPRE\\_LGMRESSolve](#) (HYPRE\_Solver solver, HYPRE\_Matrix A, HYPRE\_Vector b, HYPRE\_Vector x)
- HYPRE\_Int [HYPRE\\_LGMRESSetTol](#) (HYPRE\_Solver solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_LGMRESSetAbsoluteTol](#) (HYPRE\_Solver solver, HYPRE\_Real a\_tol)
- HYPRE\_Int [HYPRE\\_LGMRESSetConvergenceFactorTol](#) (HYPRE\_Solver solver, HYPRE\_Real cf\_tol)
- HYPRE\_Int [HYPRE\\_LGMRESSetMinIter](#) (HYPRE\_Solver solver, HYPRE\_Int min\_iter)
- HYPRE\_Int [HYPRE\\_LGMRESSetMaxIter](#) (HYPRE\_Solver solver, HYPRE\_Int max\_iter)
- HYPRE\_Int [HYPRE\\_LGMRESSetKDim](#) (HYPRE\_Solver solver, HYPRE\_Int k\_dim)
- HYPRE\_Int [HYPRE\\_LGMRESSetAugDim](#) (HYPRE\_Solver solver, HYPRE\_Int aug\_dim)
- HYPRE\_Int [HYPRE\\_LGMRESSetPrecond](#) (HYPRE\_Solver solver, HYPRE\_PtrToSolverFcn precondition, HYPRE\_PtrToSolverFcn precondition\_setup, HYPRE\_Solver precondition\_solver)
- HYPRE\_Int [HYPRE\\_LGMRESSetLogging](#) (HYPRE\_Solver solver, HYPRE\_Int logging)
- HYPRE\_Int [HYPRE\\_LGMRESSetPrintLevel](#) (HYPRE\_Solver solver, HYPRE\_Int level)
- HYPRE\_Int [HYPRE\\_LGMRESGetNumIterations](#) (HYPRE\_Solver solver, HYPRE\_Int \*num\_iterations)
- HYPRE\_Int [HYPRE\\_LGMRESGetFinalRelativeResidualNorm](#) (HYPRE\_Solver solver, HYPRE\_Real \*norm)
- HYPRE\_Int [HYPRE\\_LGMRESGetResidual](#) (HYPRE\_Solver solver, void \*residual)
- HYPRE\_Int [HYPRE\\_LGMRESGetTol](#) (HYPRE\_Solver solver, HYPRE\_Real \*tol)

- HYPRE\_Int [HYPRE\\_LGMRESGetConvergenceFactorTol](#) (HYPRE\_Solver solver, HYPRE\_Real \*cf\_tol)
- HYPRE\_Int [HYPRE\\_LGMRESGetStopCrit](#) (HYPRE\_Solver solver, HYPRE\_Int \*stop\_crit)
- HYPRE\_Int [HYPRE\\_LGMRESGetMinIter](#) (HYPRE\_Solver solver, HYPRE\_Int \*min\_iter)
- HYPRE\_Int [HYPRE\\_LGMRESGetMaxIter](#) (HYPRE\_Solver solver, HYPRE\_Int \*max\_iter)
- HYPRE\_Int [HYPRE\\_LGMRESGetKDim](#) (HYPRE\_Solver solver, HYPRE\_Int \*k\_dim)
- HYPRE\_Int [HYPRE\\_LGMRESGetAugDim](#) (HYPRE\_Solver solver, HYPRE\_Int \*k\_dim)
- HYPRE\_Int [HYPRE\\_LGMRESGetPrecond](#) (HYPRE\_Solver solver, HYPRE\_Solver \*precond\_data\_ptr)
- HYPRE\_Int [HYPRE\\_LGMRESGetLogging](#) (HYPRE\_Solver solver, HYPRE\_Int \*level)
- HYPRE\_Int [HYPRE\\_LGMRESGetPrintLevel](#) (HYPRE\_Solver solver, HYPRE\_Int \*level)
- HYPRE\_Int [HYPRE\\_LGMRESGetConverged](#) (HYPRE\_Solver solver, HYPRE\_Int \*converged)

## COGMRES Solver

- HYPRE\_Int [HYPRE\\_COGMRESSetup](#) (HYPRE\_Solver solver, HYPRE\_Matrix A, HYPRE\_Vector b, HYPRE\_Vector x)
- HYPRE\_Int [HYPRE\\_COGMRESSolve](#) (HYPRE\_Solver solver, HYPRE\_Matrix A, HYPRE\_Vector b, HYPRE\_Vector x)
- HYPRE\_Int [HYPRE\\_COGMRESSetTol](#) (HYPRE\_Solver solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_COGMRESSetAbsoluteTol](#) (HYPRE\_Solver solver, HYPRE\_Real a\_tol)
- HYPRE\_Int [HYPRE\\_COGMRESSetConvergenceFactorTol](#) (HYPRE\_Solver solver, HYPRE\_Real cf\_tol)
- HYPRE\_Int [HYPRE\\_COGMRESSetMinIter](#) (HYPRE\_Solver solver, HYPRE\_Int min\_iter)
- HYPRE\_Int [HYPRE\\_COGMRESSetMaxIter](#) (HYPRE\_Solver solver, HYPRE\_Int max\_iter)
- HYPRE\_Int [HYPRE\\_COGMRESSetKDim](#) (HYPRE\_Solver solver, HYPRE\_Int k\_dim)
- HYPRE\_Int [HYPRE\\_COGMRESSetUnroll](#) (HYPRE\_Solver solver, HYPRE\_Int unroll)
- HYPRE\_Int [HYPRE\\_COGMRESSetCGS](#) (HYPRE\_Solver solver, HYPRE\_Int cgs)
- HYPRE\_Int [HYPRE\\_COGMRESSetPrecond](#) (HYPRE\_Solver solver, HYPRE\_PtrToSolverFcn precondition, HYPRE\_PtrToSolverFcn precondition\_setup, HYPRE\_Solver precondition\_solver)
- HYPRE\_Int [HYPRE\\_COGMRESSetLogging](#) (HYPRE\_Solver solver, HYPRE\_Int logging)
- HYPRE\_Int [HYPRE\\_COGMRESSetPrintLevel](#) (HYPRE\_Solver solver, HYPRE\_Int level)
- HYPRE\_Int [HYPRE\\_COGMRESGetNumIterations](#) (HYPRE\_Solver solver, HYPRE\_Int \*num\_iterations)
- HYPRE\_Int [HYPRE\\_COGMRESGetFinalRelativeResidualNorm](#) (HYPRE\_Solver solver, HYPRE\_Real \*norm)
- HYPRE\_Int [HYPRE\\_COGMRESGetResidual](#) (HYPRE\_Solver solver, void \*residual)
- HYPRE\_Int [HYPRE\\_COGMRESGetTol](#) (HYPRE\_Solver solver, HYPRE\_Real \*tol)
- HYPRE\_Int [HYPRE\\_COGMRESGetConvergenceFactorTol](#) (HYPRE\_Solver solver, HYPRE\_Real \*cf\_tol)
- HYPRE\_Int [HYPRE\\_COGMRESGetMinIter](#) (HYPRE\_Solver solver, HYPRE\_Int \*min\_iter)
- HYPRE\_Int [HYPRE\\_COGMRESGetMaxIter](#) (HYPRE\_Solver solver, HYPRE\_Int \*max\_iter)
- HYPRE\_Int [HYPRE\\_COGMRESGetKDim](#) (HYPRE\_Solver solver, HYPRE\_Int \*k\_dim)
- HYPRE\_Int [HYPRE\\_COGMRESGetUnroll](#) (HYPRE\_Solver solver, HYPRE\_Int \*unroll)
- HYPRE\_Int [HYPRE\\_COGMRESGetCGS](#) (HYPRE\_Solver solver, HYPRE\_Int \*cgs)
- HYPRE\_Int [HYPRE\\_COGMRESGetPrecond](#) (HYPRE\_Solver solver, HYPRE\_Solver \*precond\_data\_ptr)
- HYPRE\_Int [HYPRE\\_COGMRESGetLogging](#) (HYPRE\_Solver solver, HYPRE\_Int \*level)
- HYPRE\_Int [HYPRE\\_COGMRESGetPrintLevel](#) (HYPRE\_Solver solver, HYPRE\_Int \*level)
- HYPRE\_Int [HYPRE\\_COGMRESGetConverged](#) (HYPRE\_Solver solver, HYPRE\_Int \*converged)
- HYPRE\_Int [HYPRE\\_COGMRESSetModifyPC](#) (HYPRE\_Solver solver, HYPRE\_PtrToModifyPCFcn modify\_pc)

**BiCGSTAB Solver**

- HYPRE\_Int [HYPRE\\_BiCGSTABDestroy](#) (HYPRE\_Solver solver)
- HYPRE\_Int [HYPRE\\_BiCGSTABSetup](#) (HYPRE\_Solver solver, HYPRE\_Matrix A, HYPRE\_Vector b, HYPRE\_Vector x)
- HYPRE\_Int [HYPRE\\_BiCGSTABSolve](#) (HYPRE\_Solver solver, HYPRE\_Matrix A, HYPRE\_Vector b, HYPRE\_Vector x)
- HYPRE\_Int [HYPRE\\_BiCGSTABSetTol](#) (HYPRE\_Solver solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_BiCGSTABSetAbsoluteTol](#) (HYPRE\_Solver solver, HYPRE\_Real a\_tol)
- HYPRE\_Int [HYPRE\\_BiCGSTABSetConvergenceFactorTol](#) (HYPRE\_Solver solver, HYPRE\_Real cf\_tol)
- HYPRE\_Int [HYPRE\\_BiCGSTABSetStopCrit](#) (HYPRE\_Solver solver, HYPRE\_Int stop\_crit)
- HYPRE\_Int [HYPRE\\_BiCGSTABSetMinIter](#) (HYPRE\_Solver solver, HYPRE\_Int min\_iter)
- HYPRE\_Int [HYPRE\\_BiCGSTABSetMaxIter](#) (HYPRE\_Solver solver, HYPRE\_Int max\_iter)
- HYPRE\_Int [HYPRE\\_BiCGSTABSetPrecond](#) (HYPRE\_Solver solver, HYPRE\_PtrToSolverFcn precondition, HYPRE\_PtrToSolverFcn precondition\_setup, HYPRE\_Solver precondition\_solver)
- HYPRE\_Int [HYPRE\\_BiCGSTABSetLogging](#) (HYPRE\_Solver solver, HYPRE\_Int logging)
- HYPRE\_Int [HYPRE\\_BiCGSTABSetPrintLevel](#) (HYPRE\_Solver solver, HYPRE\_Int level)
- HYPRE\_Int [HYPRE\\_BiCGSTABGetNumIterations](#) (HYPRE\_Solver solver, HYPRE\_Int \*num\_iterations)
- HYPRE\_Int [HYPRE\\_BiCGSTABGetFinalRelativeResidualNorm](#) (HYPRE\_Solver solver, HYPRE\_Real \*norm)
- HYPRE\_Int [HYPRE\\_BiCGSTABGetResidual](#) (HYPRE\_Solver solver, void \*residual)
- HYPRE\_Int [HYPRE\\_BiCGSTABGetPrecond](#) (HYPRE\_Solver solver, HYPRE\_Solver \*precond\_data\_ptr)

**CGNR Solver**

- HYPRE\_Int [HYPRE\\_CGNRDestroy](#) (HYPRE\_Solver solver)
- HYPRE\_Int [HYPRE\\_CGNRSetup](#) (HYPRE\_Solver solver, HYPRE\_Matrix A, HYPRE\_Vector b, HYPRE\_Vector x)
- HYPRE\_Int [HYPRE\\_CGNRSolve](#) (HYPRE\_Solver solver, HYPRE\_Matrix A, HYPRE\_Vector b, HYPRE\_Vector x)
- HYPRE\_Int [HYPRE\\_CGNRSetTol](#) (HYPRE\_Solver solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_CGNRSetStopCrit](#) (HYPRE\_Solver solver, HYPRE\_Int stop\_crit)
- HYPRE\_Int [HYPRE\\_CGNRSetMinIter](#) (HYPRE\_Solver solver, HYPRE\_Int min\_iter)
- HYPRE\_Int [HYPRE\\_CGNRSetMaxIter](#) (HYPRE\_Solver solver, HYPRE\_Int max\_iter)
- HYPRE\_Int [HYPRE\\_CGNRSetPrecond](#) (HYPRE\_Solver solver, HYPRE\_PtrToSolverFcn precondition, HYPRE\_PtrToSolverFcn preconditionT, HYPRE\_PtrToSolverFcn precondition\_setup, HYPRE\_Solver precondition\_solver)
- HYPRE\_Int [HYPRE\\_CGNRSetLogging](#) (HYPRE\_Solver solver, HYPRE\_Int logging)
- HYPRE\_Int [HYPRE\\_CGNRGetNumIterations](#) (HYPRE\_Solver solver, HYPRE\_Int \*num\_iterations)
- HYPRE\_Int [HYPRE\\_CGNRGetFinalRelativeResidualNorm](#) (HYPRE\_Solver solver, HYPRE\_Real \*norm)
- HYPRE\_Int [HYPRE\\_CGNRGetPrecond](#) (HYPRE\_Solver solver, HYPRE\_Solver \*precond\_data\_ptr)

**3.7.1 Detailed Description**

These solvers support many of the matrix/vector storage schemes in hypre. They should be used in conjunction with the storage-specific interfaces, particularly the specific Create() and Destroy() functions.

@memo A basic interface for Krylov solvers

**3.7.2 Macro Definition Documentation****3.7.2.1 HYPRE\_MATRIX\_STRUCT**

```
#define HYPRE_MATRIX_STRUCT
```

### 3.7.2.2 HYPRE\_MODIFYPC

```
#define HYPRE_MODIFYPC
```

### 3.7.2.3 HYPRE\_SOLVER\_STRUCT

```
#define HYPRE_SOLVER_STRUCT
```

### 3.7.2.4 HYPRE\_VECTOR\_STRUCT

```
#define HYPRE_VECTOR_STRUCT
```

## 3.7.3 Typedef Documentation

### 3.7.3.1 HYPRE\_Matrix

```
typedef struct hypre_Matrix_struct* HYPRE_Matrix
```

The matrix object.

### 3.7.3.2 HYPRE\_PtrToModifyPCFcn

```
typedef HYPRE_Int(* HYPRE_PtrToModifyPCFcn) (HYPRE_Solver, HYPRE_Int, HYPRE_Real)
```

### 3.7.3.3 HYPRE\_PtrToSolverFcn

```
typedef HYPRE_Int(* HYPRE_PtrToSolverFcn) (HYPRE_Solver, HYPRE_Matrix, HYPRE_Vector, HYPRE_Vector)
```

### 3.7.3.4 HYPRE\_Solver

```
typedef struct hypre_Solver_struct* HYPRE_Solver
```

The solver object.

### 3.7.3.5 HYPRE\_Vector

```
typedef struct hypre_Vector_struct* HYPRE_Vector
```

The vector object.

### 3.7.4 Function Documentation

#### 3.7.4.1 HYPRE\_BiCGSTABDestroy()

```
HYPRE_Int HYPRE_BiCGSTABDestroy (
    HYPRE_Solver solver )
```

#### 3.7.4.2 HYPRE\_BiCGSTABGetFinalRelativeResidualNorm()

```
HYPRE_Int HYPRE_BiCGSTABGetFinalRelativeResidualNorm (
    HYPRE_Solver solver,
    HYPRE_Real * norm )
```

Return the norm of the final relative residual.

#### 3.7.4.3 HYPRE\_BiCGSTABGetNumIterations()

```
HYPRE_Int HYPRE_BiCGSTABGetNumIterations (
    HYPRE_Solver solver,
    HYPRE_Int * num_iterations )
```

Return the number of iterations taken.

#### 3.7.4.4 HYPRE\_BiCGSTABGetPrecond()

```
HYPRE_Int HYPRE_BiCGSTABGetPrecond (
    HYPRE_Solver solver,
    HYPRE_Solver * precondition_data_ptr )
```

#### 3.7.4.5 HYPRE\_BiCGSTABGetResidual()

```
HYPRE_Int HYPRE_BiCGSTABGetResidual (
    HYPRE_Solver solver,
    void * residual )
```

Return the residual.

#### 3.7.4.6 HYPRE\_BiCGSTABSetAbsoluteTol()

```
HYPRE_Int HYPRE_BiCGSTABSetAbsoluteTol (
    HYPRE_Solver solver,
    HYPRE_Real a_tol )
```

(Optional) Set the absolute convergence tolerance (default is 0). If one desires the convergence test to check the absolute convergence tolerance *only*, then set the relative convergence tolerance to 0.0. (The convergence test is  $\|r\| \leq \max(\text{relative\_tolerance} * \|b\|, \text{absolute\_tolerance})$ .)

#### 3.7.4.7 HYPRE\_BiCGSTABSetConvergenceFactorTol()

```
HYPRE_Int HYPRE_BiCGSTABSetConvergenceFactorTol (
    HYPRE_Solver solver,
    HYPRE_Real cf_tol )
```

#### 3.7.4.8 HYPRE\_BiCGSTABSetLogging()

```
HYPRE_Int HYPRE_BiCGSTABSetLogging (
    HYPRE_Solver solver,
    HYPRE_Int logging )
```

(Optional) Set the amount of logging to do.

#### 3.7.4.9 HYPRE\_BiCGSTABSetMaxIter()

```
HYPRE_Int HYPRE_BiCGSTABSetMaxIter (
    HYPRE_Solver solver,
    HYPRE_Int max_iter )
```

(Optional) Set maximum number of iterations.

#### 3.7.4.10 HYPRE\_BiCGSTABSetMinIter()

```
HYPRE_Int HYPRE_BiCGSTABSetMinIter (
    HYPRE_Solver solver,
    HYPRE_Int min_iter )
```

#### 3.7.4.11 HYPRE\_BiCGSTABSetPrecond()

```
HYPRE_Int HYPRE_BiCGSTABSetPrecond (
    HYPRE_Solver solver,
    HYPRE_PtrToSolverFcn precondition,
    HYPRE_PtrToSolverFcn precondition_setup,
    HYPRE_Solver precondition_solver )
```

(Optional) Set the preconditioner to use.

#### 3.7.4.12 HYPRE\_BiCGSTABSetPrintLevel()

```
HYPRE_Int HYPRE_BiCGSTABSetPrintLevel (
    HYPRE_Solver solver,
    HYPRE_Int level )
```

(Optional) Set the amount of printing to do to the screen.

**3.7.4.13 HYPRE\_BiCGSTABSetStopCrit()**

```
HYPRE_Int HYPRE_BiCGSTABSetStopCrit (
    HYPRE_Solver solver,
    HYPRE_Int stop_crit )
```

**3.7.4.14 HYPRE\_BiCGSTABSetTol()**

```
HYPRE_Int HYPRE_BiCGSTABSetTol (
    HYPRE_Solver solver,
    HYPRE_Real tol )
```

(Optional) Set the convergence tolerance.

**3.7.4.15 HYPRE\_BiCGSTABSetup()**

```
HYPRE_Int HYPRE_BiCGSTABSetup (
    HYPRE_Solver solver,
    HYPRE_Matrix A,
    HYPRE_Vector b,
    HYPRE_Vector x )
```

Prepare to solve the system. The coefficient data in *b* and *x* is ignored here, but information about the layout of the data may be used.

**3.7.4.16 HYPRE\_BiCGSTABsolve()**

```
HYPRE_Int HYPRE_BiCGSTABsolve (
    HYPRE_Solver solver,
    HYPRE_Matrix A,
    HYPRE_Vector b,
    HYPRE_Vector x )
```

Solve the system.

**3.7.4.17 HYPRE\_CGNRDestroy()**

```
HYPRE_Int HYPRE_CGNRDestroy (
    HYPRE_Solver solver )
```

**3.7.4.18 HYPRE\_CGNRGetFinalRelativeResidualNorm()**

```
HYPRE_Int HYPRE_CGNRGetFinalRelativeResidualNorm (
    HYPRE_Solver solver,
    HYPRE_Real * norm )
```

Return the norm of the final relative residual.

**3.7.4.19 HYPRE\_CGNRGetNumIterations()**

```
HYPRE_Int HYPRE_CGNRGetNumIterations (
    HYPRE_Solver solver,
    HYPRE_Int * num_iterations )
```

Return the number of iterations taken.

**3.7.4.20 HYPRE\_CGNRGetPrecond()**

```
HYPRE_Int HYPRE_CGNRGetPrecond (
    HYPRE_Solver solver,
    HYPRE_Solver * precondition_data_ptr )
```

**3.7.4.21 HYPRE\_CGNRSetLogging()**

```
HYPRE_Int HYPRE_CGNRSetLogging (
    HYPRE_Solver solver,
    HYPRE_Int logging )
```

(Optional) Set the amount of logging to do.

**3.7.4.22 HYPRE\_CGNRSetMaxIter()**

```
HYPRE_Int HYPRE_CGNRSetMaxIter (
    HYPRE_Solver solver,
    HYPRE_Int max_iter )
```

(Optional) Set maximum number of iterations.

**3.7.4.23 HYPRE\_CGNRSetMinIter()**

```
HYPRE_Int HYPRE_CGNRSetMinIter (
    HYPRE_Solver solver,
    HYPRE_Int min_iter )
```

**3.7.4.24 HYPRE\_CGNRSetPrecond()**

```
HYPRE_Int HYPRE_CGNRSetPrecond (
    HYPRE_Solver solver,
    HYPRE_PtrToSolverFcn precondition,
    HYPRE_PtrToSolverFcn preconditionT,
    HYPRE_PtrToSolverFcn precondition_setup,
    HYPRE_Solver precondition_solver )
```

(Optional) Set the preconditioner to use. Note that the only preconditioner available in hypre for use with CGNR is currently BoomerAMG. It requires to use Jacobi as a smoother without CF smoothing, i.e. `relax_type` needs to be set to 0 or 7 and `relax_order` needs to be set to 0 by the user, since these are not default values. It can be used with a relaxation weight for Jacobi, which can significantly improve convergence.



**3.7.4.25 HYPRE\_CGNRSetStopCrit()**

```
HYPRE_Int HYPRE_CGNRSetStopCrit (
    HYPRE_Solver solver,
    HYPRE_Int stop_crit )
```

**3.7.4.26 HYPRE\_CGNRSetTol()**

```
HYPRE_Int HYPRE_CGNRSetTol (
    HYPRE_Solver solver,
    HYPRE_Real tol )
```

(Optional) Set the convergence tolerance.

**3.7.4.27 HYPRE\_CGNRSetup()**

```
HYPRE_Int HYPRE_CGNRSetup (
    HYPRE_Solver solver,
    HYPRE_Matrix A,
    HYPRE_Vector b,
    HYPRE_Vector x )
```

Prepare to solve the system. The coefficient data in *b* and *x* is ignored here, but information about the layout of the data may be used.

**3.7.4.28 HYPRE\_CGNRSolve()**

```
HYPRE_Int HYPRE_CGNRSolve (
    HYPRE_Solver solver,
    HYPRE_Matrix A,
    HYPRE_Vector b,
    HYPRE_Vector x )
```

Solve the system.

**3.7.4.29 HYPRE\_COGMRESGetCGS()**

```
HYPRE_Int HYPRE_COGMRESGetCGS (
    HYPRE_Solver solver,
    HYPRE_Int * cgs )
```

**3.7.4.30 HYPRE\_COGMRESGetConverged()**

```
HYPRE_Int HYPRE_COGMRESGetConverged (
    HYPRE_Solver solver,
    HYPRE_Int * converged )
```

#### 3.7.4.31 HYPRE\_COGMRESGetConvergenceFactorTol()

```
HYPRE_Int HYPRE_COGMRESGetConvergenceFactorTol (
    HYPRE_Solver solver,
    HYPRE_Real * cf_tol )
```

#### 3.7.4.32 HYPRE\_COGMRESGetFinalRelativeResidualNorm()

```
HYPRE_Int HYPRE_COGMRESGetFinalRelativeResidualNorm (
    HYPRE_Solver solver,
    HYPRE_Real * norm )
```

Return the norm of the final relative residual.

#### 3.7.4.33 HYPRE\_COGMRESGetKDim()

```
HYPRE_Int HYPRE_COGMRESGetKDim (
    HYPRE_Solver solver,
    HYPRE_Int * k_dim )
```

#### 3.7.4.34 HYPRE\_COGMRESGetLogging()

```
HYPRE_Int HYPRE_COGMRESGetLogging (
    HYPRE_Solver solver,
    HYPRE_Int * level )
```

#### 3.7.4.35 HYPRE\_COGMRESGetMaxIter()

```
HYPRE_Int HYPRE_COGMRESGetMaxIter (
    HYPRE_Solver solver,
    HYPRE_Int * max_iter )
```

#### 3.7.4.36 HYPRE\_COGMRESGetMinIter()

```
HYPRE_Int HYPRE_COGMRESGetMinIter (
    HYPRE_Solver solver,
    HYPRE_Int * min_iter )
```

#### 3.7.4.37 HYPRE\_COGMRESGetNumIterations()

```
HYPRE_Int HYPRE_COGMRESGetNumIterations (
    HYPRE_Solver solver,
    HYPRE_Int * num_iterations )
```

Return the number of iterations taken.

**3.7.4.38 HYPRE\_COGMRESGetPrecond()**

```
HYPRE_Int HYPRE_COGMRESGetPrecond (
    HYPRE_Solver solver,
    HYPRE_Solver * precondition_data_ptr )
```

**3.7.4.39 HYPRE\_COGMRESGetPrintLevel()**

```
HYPRE_Int HYPRE_COGMRESGetPrintLevel (
    HYPRE_Solver solver,
    HYPRE_Int * level )
```

**3.7.4.40 HYPRE\_COGMRESGetResidual()**

```
HYPRE_Int HYPRE_COGMRESGetResidual (
    HYPRE_Solver solver,
    void * residual )
```

Return the residual.

**3.7.4.41 HYPRE\_COGMRESGetTol()**

```
HYPRE_Int HYPRE_COGMRESGetTol (
    HYPRE_Solver solver,
    HYPRE_Real * tol )
```

**3.7.4.42 HYPRE\_COGMRESGetUnroll()**

```
HYPRE_Int HYPRE_COGMRESGetUnroll (
    HYPRE_Solver solver,
    HYPRE_Int * unroll )
```

**3.7.4.43 HYPRE\_COGMRESSetAbsoluteTol()**

```
HYPRE_Int HYPRE_COGMRESSetAbsoluteTol (
    HYPRE_Solver solver,
    HYPRE_Real a_tol )
```

(Optional) Set the absolute convergence tolerance (default is 0). If one desires the convergence test to check the absolute convergence tolerance *only*, then set the relative convergence tolerance to 0.0. (The convergence test is  $\|r\| \leq \max(\text{relative\_tolerance} * \|b\|, \text{absolute\_tolerance})$ .)

**3.7.4.44 HYPRE\_COGMRESSetCGS()**

```
HYPRE_Int HYPRE_COGMRESSetCGS (
    HYPRE_Solver solver,
    HYPRE_Int cgs )
```

(Optional) Set the number of orthogonalizations in COGMRES (at most 2).

#### 3.7.4.45 HYPRE\_COGMRESSetConvergenceFactorTol()

```
HYPRE_Int HYPRE_COGMRESSetConvergenceFactorTol (
    HYPRE_Solver solver,
    HYPRE_Real cf_tol )
```

#### 3.7.4.46 HYPRE\_COGMRESSetKDim()

```
HYPRE_Int HYPRE_COGMRESSetKDim (
    HYPRE_Solver solver,
    HYPRE_Int k_dim )
```

(Optional) Set the maximum size of the Krylov space.

#### 3.7.4.47 HYPRE\_COGMRESSetLogging()

```
HYPRE_Int HYPRE_COGMRESSetLogging (
    HYPRE_Solver solver,
    HYPRE_Int logging )
```

(Optional) Set the amount of logging to do.

#### 3.7.4.48 HYPRE\_COGMRESSetMaxIter()

```
HYPRE_Int HYPRE_COGMRESSetMaxIter (
    HYPRE_Solver solver,
    HYPRE_Int max_iter )
```

(Optional) Set maximum number of iterations.

#### 3.7.4.49 HYPRE\_COGMRESSetMinIter()

```
HYPRE_Int HYPRE_COGMRESSetMinIter (
    HYPRE_Solver solver,
    HYPRE_Int min_iter )
```

#### 3.7.4.50 HYPRE\_COGMRESSetModifyPC()

```
HYPRE_Int HYPRE_COGMRESSetModifyPC (
    HYPRE_Solver solver,
    HYPRE_PtrToModifyPCFcn modify_pc )
```

(Optional) Set a user-defined function to modify solve-time preconditioner attributes.

**3.7.4.51 HYPRE\_COGMRESSetPrecond()**

```
HYPRE_Int HYPRE_COGMRESSetPrecond (
    HYPRE_Solver solver,
    HYPRE_PtrToSolverFcn precondition,
    HYPRE_PtrToSolverFcn precondition_setup,
    HYPRE_Solver precondition_solver )
```

(Optional) Set the preconditioner to use.

**3.7.4.52 HYPRE\_COGMRESSetPrintLevel()**

```
HYPRE_Int HYPRE_COGMRESSetPrintLevel (
    HYPRE_Solver solver,
    HYPRE_Int level )
```

(Optional) Set the amount of printing to do to the screen.

**3.7.4.53 HYPRE\_COGMRESSetTol()**

```
HYPRE_Int HYPRE_COGMRESSetTol (
    HYPRE_Solver solver,
    HYPRE_Real tol )
```

(Optional) Set the convergence tolerance.

**3.7.4.54 HYPRE\_COGMRESSetUnroll()**

```
HYPRE_Int HYPRE_COGMRESSetUnroll (
    HYPRE_Solver solver,
    HYPRE_Int unroll )
```

(Optional) Set number of unrolling in mass functions in COGMRES Can be 4 or 8. Default: no unrolling.

**3.7.4.55 HYPRE\_COGMRESSetup()**

```
HYPRE_Int HYPRE_COGMRESSetup (
    HYPRE_Solver solver,
    HYPRE_Matrix A,
    HYPRE_Vector b,
    HYPRE_Vector x )
```

Prepare to solve the system. The coefficient data in *b* and *x* is ignored here, but information about the layout of the data may be used.

#### 3.7.4.56 HYPRE\_COGMRESSolve()

```
HYPRE_Int HYPRE_COGMRESSolve (
    HYPRE_Solver solver,
    HYPRE_Matrix A,
    HYPRE_Vector b,
    HYPRE_Vector x )
```

Solve the system.

#### 3.7.4.57 HYPRE\_FlexGMRESGetConverged()

```
HYPRE_Int HYPRE_FlexGMRESGetConverged (
    HYPRE_Solver solver,
    HYPRE_Int * converged )
```

#### 3.7.4.58 HYPRE\_FlexGMRESGetConvergenceFactorTol()

```
HYPRE_Int HYPRE_FlexGMRESGetConvergenceFactorTol (
    HYPRE_Solver solver,
    HYPRE_Real * cf_tol )
```

#### 3.7.4.59 HYPRE\_FlexGMRESGetFinalRelativeResidualNorm()

```
HYPRE_Int HYPRE_FlexGMRESGetFinalRelativeResidualNorm (
    HYPRE_Solver solver,
    HYPRE_Real * norm )
```

Return the norm of the final relative residual.

#### 3.7.4.60 HYPRE\_FlexGMRESGetKDim()

```
HYPRE_Int HYPRE_FlexGMRESGetKDim (
    HYPRE_Solver solver,
    HYPRE_Int * k_dim )
```

#### 3.7.4.61 HYPRE\_FlexGMRESGetLogging()

```
HYPRE_Int HYPRE_FlexGMRESGetLogging (
    HYPRE_Solver solver,
    HYPRE_Int * level )
```

#### 3.7.4.62 HYPRE\_FlexGMRESGetMaxIter()

```
HYPRE_Int HYPRE_FlexGMRESGetMaxIter (
    HYPRE_Solver solver,
    HYPRE_Int * max_iter )
```

**3.7.4.63 HYPRE\_FlexGMRESGetMinIter()**

```
HYPRE_Int HYPRE_FlexGMRESGetMinIter (
    HYPRE_Solver solver,
    HYPRE_Int * min_iter )
```

**3.7.4.64 HYPRE\_FlexGMRESGetNumIterations()**

```
HYPRE_Int HYPRE_FlexGMRESGetNumIterations (
    HYPRE_Solver solver,
    HYPRE_Int * num_iterations )
```

Return the number of iterations taken.

**3.7.4.65 HYPRE\_FlexGMRESGetPrecond()**

```
HYPRE_Int HYPRE_FlexGMRESGetPrecond (
    HYPRE_Solver solver,
    HYPRE_Solver * precondition_data_ptr )
```

**3.7.4.66 HYPRE\_FlexGMRESGetPrintLevel()**

```
HYPRE_Int HYPRE_FlexGMRESGetPrintLevel (
    HYPRE_Solver solver,
    HYPRE_Int * level )
```

**3.7.4.67 HYPRE\_FlexGMRESGetResidual()**

```
HYPRE_Int HYPRE_FlexGMRESGetResidual (
    HYPRE_Solver solver,
    void * residual )
```

Return the residual.

**3.7.4.68 HYPRE\_FlexGMRESGetStopCrit()**

```
HYPRE_Int HYPRE_FlexGMRESGetStopCrit (
    HYPRE_Solver solver,
    HYPRE_Int * stop_crit )
```

**3.7.4.69 HYPRE\_FlexGMRESGetTol()**

```
HYPRE_Int HYPRE_FlexGMRESGetTol (
    HYPRE_Solver solver,
    HYPRE_Real * tol )
```

#### 3.7.4.70 HYPRE\_FlexGMRESSetAbsoluteTol()

```
HYPRE_Int HYPRE_FlexGMRESSetAbsoluteTol (
    HYPRE_Solver solver,
    HYPRE_Real a_tol )
```

(Optional) Set the absolute convergence tolerance (default is 0). If one desires the convergence test to check the absolute convergence tolerance *only*, then set the relative convergence tolerance to 0.0. (The convergence test is  $\|r\| \leq \max(\text{relative\_tolerance} * \|b\|, \text{absolute\_tolerance})$ .)

#### 3.7.4.71 HYPRE\_FlexGMRESSetConvergenceFactorTol()

```
HYPRE_Int HYPRE_FlexGMRESSetConvergenceFactorTol (
    HYPRE_Solver solver,
    HYPRE_Real cf_tol )
```

#### 3.7.4.72 HYPRE\_FlexGMRESSetKDim()

```
HYPRE_Int HYPRE_FlexGMRESSetKDim (
    HYPRE_Solver solver,
    HYPRE_Int k_dim )
```

(Optional) Set the maximum size of the Krylov space.

#### 3.7.4.73 HYPRE\_FlexGMRESSetLogging()

```
HYPRE_Int HYPRE_FlexGMRESSetLogging (
    HYPRE_Solver solver,
    HYPRE_Int logging )
```

(Optional) Set the amount of logging to do.

#### 3.7.4.74 HYPRE\_FlexGMRESSetMaxIter()

```
HYPRE_Int HYPRE_FlexGMRESSetMaxIter (
    HYPRE_Solver solver,
    HYPRE_Int max_iter )
```

(Optional) Set maximum number of iterations.

#### 3.7.4.75 HYPRE\_FlexGMRESSetMinIter()

```
HYPRE_Int HYPRE_FlexGMRESSetMinIter (
    HYPRE_Solver solver,
    HYPRE_Int min_iter )
```



**3.7.4.76 HYPRE\_FlexGMRESSetModifyPC()**

```
HYPRE_Int HYPRE_FlexGMRESSetModifyPC (
    HYPRE_Solver solver,
    HYPRE_PtrToModifyPCFcn modify_pc )
```

(Optional) Set a user-defined function to modify solve-time preconditioner attributes.

**3.7.4.77 HYPRE\_FlexGMRESSetPrecond()**

```
HYPRE_Int HYPRE_FlexGMRESSetPrecond (
    HYPRE_Solver solver,
    HYPRE_PtrToSolverFcn precondition,
    HYPRE_PtrToSolverFcn precondition_setup,
    HYPRE_Solver precondition_solver )
```

(Optional) Set the preconditioner to use.

**3.7.4.78 HYPRE\_FlexGMRESSetPrintLevel()**

```
HYPRE_Int HYPRE_FlexGMRESSetPrintLevel (
    HYPRE_Solver solver,
    HYPRE_Int level )
```

(Optional) Set the amount of printing to do to the screen.

**3.7.4.79 HYPRE\_FlexGMRESSetTol()**

```
HYPRE_Int HYPRE_FlexGMRESSetTol (
    HYPRE_Solver solver,
    HYPRE_Real tol )
```

(Optional) Set the convergence tolerance.

**3.7.4.80 HYPRE\_FlexGMRESSetup()**

```
HYPRE_Int HYPRE_FlexGMRESSetup (
    HYPRE_Solver solver,
    HYPRE_Matrix A,
    HYPRE_Vector b,
    HYPRE_Vector x )
```

Prepare to solve the system. The coefficient data in *b* and *x* is ignored here, but information about the layout of the data may be used.

#### 3.7.4.81 HYPRE\_FlexGMRESSolve()

```
HYPRE_Int HYPRE_FlexGMRESSolve (
    HYPRE_Solver solver,
    HYPRE_Matrix A,
    HYPRE_Vector b,
    HYPRE_Vector x )
```

Solve the system.

#### 3.7.4.82 HYPRE\_GMRESGetAbsoluteTol()

```
HYPRE_Int HYPRE_GMRESGetAbsoluteTol (
    HYPRE_Solver solver,
    HYPRE_Real * tol )
```

#### 3.7.4.83 HYPRE\_GMRESGetConverged()

```
HYPRE_Int HYPRE_GMRESGetConverged (
    HYPRE_Solver solver,
    HYPRE_Int * converged )
```

#### 3.7.4.84 HYPRE\_GMRESGetConvergenceFactorTol()

```
HYPRE_Int HYPRE_GMRESGetConvergenceFactorTol (
    HYPRE_Solver solver,
    HYPRE_Real * cf_tol )
```

#### 3.7.4.85 HYPRE\_GMRESGetFinalRelativeResidualNorm()

```
HYPRE_Int HYPRE_GMRESGetFinalRelativeResidualNorm (
    HYPRE_Solver solver,
    HYPRE_Real * norm )
```

Return the norm of the final relative residual.

#### 3.7.4.86 HYPRE\_GMRESGetKDim()

```
HYPRE_Int HYPRE_GMRESGetKDim (
    HYPRE_Solver solver,
    HYPRE_Int * k_dim )
```

#### 3.7.4.87 HYPRE\_GMRESGetLogging()

```
HYPRE_Int HYPRE_GMRESGetLogging (
    HYPRE_Solver solver,
    HYPRE_Int * level )
```

**3.7.4.88 HYPRE\_GMRESGetMaxIter()**

```
HYPRE_Int HYPRE_GMRESGetMaxIter (
    HYPRE_Solver solver,
    HYPRE_Int * max_iter )
```

**3.7.4.89 HYPRE\_GMRESGetMinIter()**

```
HYPRE_Int HYPRE_GMRESGetMinIter (
    HYPRE_Solver solver,
    HYPRE_Int * min_iter )
```

**3.7.4.90 HYPRE\_GMRESGetNumIterations()**

```
HYPRE_Int HYPRE_GMRESGetNumIterations (
    HYPRE_Solver solver,
    HYPRE_Int * num_iterations )
```

Return the number of iterations taken.

**3.7.4.91 HYPRE\_GMRESGetPrecond()**

```
HYPRE_Int HYPRE_GMRESGetPrecond (
    HYPRE_Solver solver,
    HYPRE_Solver * precondition_data_ptr )
```

**3.7.4.92 HYPRE\_GMRESGetPrintLevel()**

```
HYPRE_Int HYPRE_GMRESGetPrintLevel (
    HYPRE_Solver solver,
    HYPRE_Int * level )
```

**3.7.4.93 HYPRE\_GMRESGetRelChange()**

```
HYPRE_Int HYPRE_GMRESGetRelChange (
    HYPRE_Solver solver,
    HYPRE_Int * rel_change )
```

**3.7.4.94 HYPRE\_GMRESGetResidual()**

```
HYPRE_Int HYPRE_GMRESGetResidual (
    HYPRE_Solver solver,
    void * residual )
```

Return the residual.

**3.7.4.95 HYPRE\_GMRESGetSkipRealResidualCheck()**

```
HYPRE_Int HYPRE_GMRESGetSkipRealResidualCheck (
    HYPRE_Solver solver,
    HYPRE_Int * skip_real_r_check )
```

**3.7.4.96 HYPRE\_GMRESGetStopCrit()**

```
HYPRE_Int HYPRE_GMRESGetStopCrit (
    HYPRE_Solver solver,
    HYPRE_Int * stop_crit )
```

**3.7.4.97 HYPRE\_GMRESGetTol()**

```
HYPRE_Int HYPRE_GMRESGetTol (
    HYPRE_Solver solver,
    HYPRE_Real * tol )
```

**3.7.4.98 HYPRE\_GMRESSetAbsoluteTol()**

```
HYPRE_Int HYPRE_GMRESSetAbsoluteTol (
    HYPRE_Solver solver,
    HYPRE_Real a_tol )
```

(Optional) Set the absolute convergence tolerance (default is 0). If one desires the convergence test to check the absolute convergence tolerance *only*, then set the relative convergence tolerance to 0.0. (The convergence test is  $\|r\| \leq \max(\text{relative\_tolerance} * \|b\|, \text{absolute\_tolerance})$ .)

**3.7.4.99 HYPRE\_GMRESSetConvergenceFactorTol()**

```
HYPRE_Int HYPRE_GMRESSetConvergenceFactorTol (
    HYPRE_Solver solver,
    HYPRE_Real cf_tol )
```

**3.7.4.100 HYPRE\_GMRESSetKDim()**

```
HYPRE_Int HYPRE_GMRESSetKDim (
    HYPRE_Solver solver,
    HYPRE_Int k_dim )
```

(Optional) Set the maximum size of the Krylov space.

**3.7.4.101 HYPRE\_GMRESSetLogging()**

```
HYPRE_Int HYPRE_GMRESSetLogging (
    HYPRE_Solver solver,
    HYPRE_Int logging )
```

(Optional) Set the amount of logging to do.

**3.7.4.102 HYPRE\_GMRESsetMaxIter()**

```
HYPRE_Int HYPRE_GMRESsetMaxIter (
    HYPRE_Solver solver,
    HYPRE_Int max_iter )
```

(Optional) Set maximum number of iterations.

**3.7.4.103 HYPRE\_GMRESsetMinIter()**

```
HYPRE_Int HYPRE_GMRESsetMinIter (
    HYPRE_Solver solver,
    HYPRE_Int min_iter )
```

**3.7.4.104 HYPRE\_GMRESsetPrecond()**

```
HYPRE_Int HYPRE_GMRESsetPrecond (
    HYPRE_Solver solver,
    HYPRE_PtrToSolverFcn precondition,
    HYPRE_PtrToSolverFcn precondition_setup,
    HYPRE_Solver precondition_solver )
```

(Optional) Set the preconditioner to use.

**3.7.4.105 HYPRE\_GMRESsetPrintLevel()**

```
HYPRE_Int HYPRE_GMRESsetPrintLevel (
    HYPRE_Solver solver,
    HYPRE_Int level )
```

(Optional) Set the amount of printing to do to the screen.

**3.7.4.106 HYPRE\_GMRESsetRelChange()**

```
HYPRE_Int HYPRE_GMRESsetRelChange (
    HYPRE_Solver solver,
    HYPRE_Int rel_change )
```

(Optional) Additionally require that the relative difference in successive iterates be small.

**3.7.4.107 HYPRE\_GMRESsetSkipRealResidualCheck()**

```
HYPRE_Int HYPRE_GMRESsetSkipRealResidualCheck (
    HYPRE_Solver solver,
    HYPRE_Int skip_real_r_check )
```

(Optional) By default, hypre checks for convergence by evaluating the actual residual before returning from GMRES (with restart if the true residual does not indicate convergence). This option allows users to skip the evaluation and the check of the actual residual for badly conditioned problems where restart is not expected to be beneficial.

#### 3.7.4.108 HYPRE\_GMRESSetStopCrit()

```
HYPRE_Int HYPRE_GMRESSetStopCrit (
    HYPRE_Solver solver,
    HYPRE_Int stop_crit )
```

#### 3.7.4.109 HYPRE\_GMRESSetTol()

```
HYPRE_Int HYPRE_GMRESSetTol (
    HYPRE_Solver solver,
    HYPRE_Real tol )
```

(Optional) Set the relative convergence tolerance.

#### 3.7.4.110 HYPRE\_GMRESSetup()

```
HYPRE_Int HYPRE_GMRESSetup (
    HYPRE_Solver solver,
    HYPRE_Matrix A,
    HYPRE_Vector b,
    HYPRE_Vector x )
```

Prepare to solve the system. The coefficient data in *b* and *x* is ignored here, but information about the layout of the data may be used.

#### 3.7.4.111 HYPRE\_GMRESSolve()

```
HYPRE_Int HYPRE_GMRESSolve (
    HYPRE_Solver solver,
    HYPRE_Matrix A,
    HYPRE_Vector b,
    HYPRE_Vector x )
```

Solve the system.

#### 3.7.4.112 HYPRE\_LGMRESGetAugDim()

```
HYPRE_Int HYPRE_LGMRESGetAugDim (
    HYPRE_Solver solver,
    HYPRE_Int * k_dim )
```

#### 3.7.4.113 HYPRE\_LGMRESGetConverged()

```
HYPRE_Int HYPRE_LGMRESGetConverged (
    HYPRE_Solver solver,
    HYPRE_Int * converged )
```

**3.7.4.114 HYPRE\_LGMRESGetConvergenceFactorTol()**

```
HYPRE_Int HYPRE_LGMRESGetConvergenceFactorTol (
    HYPRE_Solver solver,
    HYPRE_Real * cf_tol )
```

**3.7.4.115 HYPRE\_LGMRESGetFinalRelativeResidualNorm()**

```
HYPRE_Int HYPRE_LGMRESGetFinalRelativeResidualNorm (
    HYPRE_Solver solver,
    HYPRE_Real * norm )
```

Return the norm of the final relative residual.

**3.7.4.116 HYPRE\_LGMRESGetKDim()**

```
HYPRE_Int HYPRE_LGMRESGetKDim (
    HYPRE_Solver solver,
    HYPRE_Int * k_dim )
```

**3.7.4.117 HYPRE\_LGMRESGetLogging()**

```
HYPRE_Int HYPRE_LGMRESGetLogging (
    HYPRE_Solver solver,
    HYPRE_Int * level )
```

**3.7.4.118 HYPRE\_LGMRESGetMaxIter()**

```
HYPRE_Int HYPRE_LGMRESGetMaxIter (
    HYPRE_Solver solver,
    HYPRE_Int * max_iter )
```

**3.7.4.119 HYPRE\_LGMRESGetMinIter()**

```
HYPRE_Int HYPRE_LGMRESGetMinIter (
    HYPRE_Solver solver,
    HYPRE_Int * min_iter )
```

**3.7.4.120 HYPRE\_LGMRESGetNumIterations()**

```
HYPRE_Int HYPRE_LGMRESGetNumIterations (
    HYPRE_Solver solver,
    HYPRE_Int * num_iterations )
```

Return the number of iterations taken.

**3.7.4.121 HYPRE\_LGMRESGetPrecond()**

```
HYPRE_Int HYPRE_LGMRESGetPrecond (
    HYPRE_Solver solver,
    HYPRE_Solver * precondition_data_ptr )
```

**3.7.4.122 HYPRE\_LGMRESGetPrintLevel()**

```
HYPRE_Int HYPRE_LGMRESGetPrintLevel (
    HYPRE_Solver solver,
    HYPRE_Int * level )
```

**3.7.4.123 HYPRE\_LGMRESGetResidual()**

```
HYPRE_Int HYPRE_LGMRESGetResidual (
    HYPRE_Solver solver,
    void * residual )
```

Return the residual.

**3.7.4.124 HYPRE\_LGMRESGetStopCrit()**

```
HYPRE_Int HYPRE_LGMRESGetStopCrit (
    HYPRE_Solver solver,
    HYPRE_Int * stop_crit )
```

**3.7.4.125 HYPRE\_LGMRESGetTol()**

```
HYPRE_Int HYPRE_LGMRESGetTol (
    HYPRE_Solver solver,
    HYPRE_Real * tol )
```

**3.7.4.126 HYPRE\_LGMRESSetAbsoluteTol()**

```
HYPRE_Int HYPRE_LGMRESSetAbsoluteTol (
    HYPRE_Solver solver,
    HYPRE_Real a_tol )
```

(Optional) Set the absolute convergence tolerance (default is 0). If one desires the convergence test to check the absolute convergence tolerance *only*, then set the relative convergence tolerance to 0.0. (The convergence test is  $\|r\| \leq \max(\text{relative\_tolerance} * \|b\|, \text{absolute\_tolerance})$ .)

**3.7.4.127 HYPRE\_LGMRESSetAugDim()**

```
HYPRE_Int HYPRE_LGMRESSetAugDim (
    HYPRE_Solver solver,
    HYPRE_Int aug_dim )
```

(Optional) Set the number of augmentation vectors (default: 2).



**3.7.4.128 HYPRE\_LGMRESSetConvergenceFactorTol()**

```
HYPRE_Int HYPRE_LGMRESSetConvergenceFactorTol (
    HYPRE_Solver solver,
    HYPRE_Real cf_tol )
```

**3.7.4.129 HYPRE\_LGMRESSetKDim()**

```
HYPRE_Int HYPRE_LGMRESSetKDim (
    HYPRE_Solver solver,
    HYPRE_Int k_dim )
```

(Optional) Set the maximum size of the approximation space (includes the augmentation vectors).

**3.7.4.130 HYPRE\_LGMRESSetLogging()**

```
HYPRE_Int HYPRE_LGMRESSetLogging (
    HYPRE_Solver solver,
    HYPRE_Int logging )
```

(Optional) Set the amount of logging to do.

**3.7.4.131 HYPRE\_LGMRESSetMaxIter()**

```
HYPRE_Int HYPRE_LGMRESSetMaxIter (
    HYPRE_Solver solver,
    HYPRE_Int max_iter )
```

(Optional) Set maximum number of iterations.

**3.7.4.132 HYPRE\_LGMRESSetMinIter()**

```
HYPRE_Int HYPRE_LGMRESSetMinIter (
    HYPRE_Solver solver,
    HYPRE_Int min_iter )
```

**3.7.4.133 HYPRE\_LGMRESSetPrecond()**

```
HYPRE_Int HYPRE_LGMRESSetPrecond (
    HYPRE_Solver solver,
    HYPRE_PtrToSolverFcn precond,
    HYPRE_PtrToSolverFcn precond_setup,
    HYPRE_Solver precond_solver )
```

(Optional) Set the preconditioner to use.

**3.7.4.134 HYPRE\_LGMRESSetPrintLevel()**

```
HYPRE_Int HYPRE_LGMRESSetPrintLevel (
    HYPRE_Solver solver,
    HYPRE_Int level )
```

(Optional) Set the amount of printing to do to the screen.

**3.7.4.135 HYPRE\_LGMRESSetTol()**

```
HYPRE_Int HYPRE_LGMRESSetTol (
    HYPRE_Solver solver,
    HYPRE_Real tol )
```

(Optional) Set the convergence tolerance.

**3.7.4.136 HYPRE\_LGMRESSetup()**

```
HYPRE_Int HYPRE_LGMRESSetup (
    HYPRE_Solver solver,
    HYPRE_Matrix A,
    HYPRE_Vector b,
    HYPRE_Vector x )
```

Prepare to solve the system. The coefficient data in *b* and *x* is ignored here, but information about the layout of the data may be used.

**3.7.4.137 HYPRE\_LGMRESSolve()**

```
HYPRE_Int HYPRE_LGMRESSolve (
    HYPRE_Solver solver,
    HYPRE_Matrix A,
    HYPRE_Vector b,
    HYPRE_Vector x )
```

Solve the system. Details on LGMRES may be found in A. H. Baker, E.R. Jessup, and T.A. Manteuffel, "A technique for accelerating the convergence of restarted GMRES." SIAM Journal on Matrix Analysis and Applications, 26 (2005), pp. 962-984. LGMRES(m,k) in the paper corresponds to LGMRES(Kdim+AugDim, AugDim).

**3.7.4.138 HYPRE\_PCGGetAbsoluteTolFactor()**

```
HYPRE_Int HYPRE_PCGGetAbsoluteTolFactor (
    HYPRE_Solver solver,
    HYPRE_Real * abstolf )
```

**3.7.4.139 HYPRE\_PCGGetConverged()**

```
HYPRE_Int HYPRE_PCGGetConverged (
    HYPRE_Solver solver,
    HYPRE_Int * converged )
```

**3.7.4.140 HYPRE\_PCGGetConvergenceFactorTol()**

```
HYPRE_Int HYPRE_PCGGetConvergenceFactorTol (
    HYPRE_Solver solver,
    HYPRE_Real * cf_tol )
```

**3.7.4.141 HYPRE\_PCGGetFinalRelativeResidualNorm()**

```
HYPRE_Int HYPRE_PCGGetFinalRelativeResidualNorm (
    HYPRE_Solver solver,
    HYPRE_Real * norm )
```

Return the norm of the final relative residual.

**3.7.4.142 HYPRE\_PCGGetLogging()**

```
HYPRE_Int HYPRE_PCGGetLogging (
    HYPRE_Solver solver,
    HYPRE_Int * level )
```

**3.7.4.143 HYPRE\_PCGGetMaxIter()**

```
HYPRE_Int HYPRE_PCGGetMaxIter (
    HYPRE_Solver solver,
    HYPRE_Int * max_iter )
```

**3.7.4.144 HYPRE\_PCGGetNumIterations()**

```
HYPRE_Int HYPRE_PCGGetNumIterations (
    HYPRE_Solver solver,
    HYPRE_Int * num_iterations )
```

Return the number of iterations taken.

**3.7.4.145 HYPRE\_PCGGetPrecond()**

```
HYPRE_Int HYPRE_PCGGetPrecond (
    HYPRE_Solver solver,
    HYPRE_Solver * precondition_data_ptr )
```

**3.7.4.146 HYPRE\_PCGGetPrintLevel()**

```
HYPRE_Int HYPRE_PCGGetPrintLevel (
    HYPRE_Solver solver,
    HYPRE_Int * level )
```

**3.7.4.147 HYPRE\_PCGGetRelChange()**

```
HYPRE_Int HYPRE_PCGGetRelChange (
    HYPRE_Solver solver,
    HYPRE_Int * rel_change )
```

**3.7.4.148 HYPRE\_PCGGetResidual()**

```
HYPRE_Int HYPRE_PCGGetResidual (
    HYPRE_Solver solver,
    void * residual )
```

Return the residual.

**3.7.4.149 HYPRE\_PCGGetResidualTol()**

```
HYPRE_Int HYPRE_PCGGetResidualTol (
    HYPRE_Solver solver,
    HYPRE_Real * rtol )
```

**3.7.4.150 HYPRE\_PCGGetStopCrit()**

```
HYPRE_Int HYPRE_PCGGetStopCrit (
    HYPRE_Solver solver,
    HYPRE_Int * stop_crit )
```

**3.7.4.151 HYPRE\_PCGGetTol()**

```
HYPRE_Int HYPRE_PCGGetTol (
    HYPRE_Solver solver,
    HYPRE_Real * tol )
```

**3.7.4.152 HYPRE\_PCGGetTwoNorm()**

```
HYPRE_Int HYPRE_PCGGetTwoNorm (
    HYPRE_Solver solver,
    HYPRE_Int * two_norm )
```

**3.7.4.153 HYPRE\_PCGSetAbsoluteTol()**

```
HYPRE_Int HYPRE_PCGSetAbsoluteTol (
    HYPRE_Solver solver,
    HYPRE_Real a_tol )
```

(Optional) Set the absolute convergence tolerance (default is 0). If one desires the convergence test to check the absolute convergence tolerance *only*, then set the relative convergence tolerance to 0.0. (The default convergence test is  $< C * r, r > \leq \max(\text{relative\_tolerance}^2 * < C * b, b >, \text{absolute\_tolerance}^2)$ .)

**3.7.4.154 HYPRE\_PCGSetAbsoluteTolFactor()**

```
HYPRE_Int HYPRE_PCGSetAbsoluteTolFactor (
    HYPRE_Solver solver,
    HYPRE_Real abstolf )
```

**3.7.4.155 HYPRE\_PCGSetConvergenceFactorTol()**

```
HYPRE_Int HYPRE_PCGSetConvergenceFactorTol (
    HYPRE_Solver solver,
    HYPRE_Real cf_tol )
```

**3.7.4.156 HYPRE\_PCGSetLogging()**

```
HYPRE_Int HYPRE_PCGSetLogging (
    HYPRE_Solver solver,
    HYPRE_Int logging )
```

(Optional) Set the amount of logging to do.

**3.7.4.157 HYPRE\_PCGSetMaxIter()**

```
HYPRE_Int HYPRE_PCGSetMaxIter (
    HYPRE_Solver solver,
    HYPRE_Int max_iter )
```

(Optional) Set maximum number of iterations.

**3.7.4.158 HYPRE\_PCGSetPrecond()**

```
HYPRE_Int HYPRE_PCGSetPrecond (
    HYPRE_Solver solver,
    HYPRE_PtrToSolverFcn precondition,
    HYPRE_PtrToSolverFcn precondition_setup,
    HYPRE_Solver precondition_solver )
```

(Optional) Set the preconditioner to use.

**3.7.4.159 HYPRE\_PCGSetPrintLevel()**

```
HYPRE_Int HYPRE_PCGSetPrintLevel (
    HYPRE_Solver solver,
    HYPRE_Int level )
```

(Optional) Set the amount of printing to do to the screen.

**3.7.4.160 HYPRE\_PCGSetRecomputeResidual()**

```
HYPRE_Int HYPRE_PCGSetRecomputeResidual (
    HYPRE_Solver solver,
    HYPRE_Int recompute_residual )
```

(Optional) Recompute the residual at the end to double-check convergence.

**3.7.4.161 HYPRE\_PCGSetRecomputeResidualP()**

```
HYPRE_Int HYPRE_PCGSetRecomputeResidualP (
    HYPRE_Solver solver,
    HYPRE_Int recompute_residual_p )
```

(Optional) Periodically recompute the residual while iterating.

**3.7.4.162 HYPRE\_PCGSetRelChange()**

```
HYPRE_Int HYPRE_PCGSetRelChange (
    HYPRE_Solver solver,
    HYPRE_Int rel_change )
```

(Optional) Additionally require that the relative difference in successive iterates be small.

**3.7.4.163 HYPRE\_PCGSetResidualTol()**

```
HYPRE_Int HYPRE_PCGSetResidualTol (
    HYPRE_Solver solver,
    HYPRE_Real rtol )
```

(Optional) Set a residual-based convergence tolerance which checks if  $\|r_{old} - r_{new}\| < rtol\|b\|$ . This is useful when trying to converge to very low relative and/or absolute tolerances, in order to bail-out before roundoff errors affect the approximation.

**3.7.4.164 HYPRE\_PCGSetStopCrit()**

```
HYPRE_Int HYPRE_PCGSetStopCrit (
    HYPRE_Solver solver,
    HYPRE_Int stop_crit )
```

**3.7.4.165 HYPRE\_PCGSetTol()**

```
HYPRE_Int HYPRE_PCGSetTol (
    HYPRE_Solver solver,
    HYPRE_Real tol )
```

(Optional) Set the relative convergence tolerance.

**3.7.4.166 HYPRE\_PCGSetTwoNorm()**

```
HYPRE_Int HYPRE_PCGSetTwoNorm (
    HYPRE_Solver solver,
    HYPRE_Int two_norm )
```

(Optional) Use the two-norm in stopping criteria.

**3.7.4.167 HYPRE\_PCGSetup()**

```
HYPRE_Int HYPRE_PCGSetup (
    HYPRE_Solver solver,
    HYPRE_Matrix A,
    HYPRE_Vector b,
    HYPRE_Vector x )
```

Prepare to solve the system. The coefficient data in *b* and *x* is ignored here, but information about the layout of the data may be used.

**3.7.4.168 HYPRE\_PCGSolve()**

```
HYPRE_Int HYPRE_PCGSolve (
    HYPRE_Solver solver,
    HYPRE_Matrix A,
    HYPRE_Vector b,
    HYPRE_Vector x )
```

Solve the system.

**3.8 Eigensolvers****LOBPCG Eigensolver**

- HYPRE\_Int [HYPRE\\_LOBPCGCreate](#) (mv\_InterfaceInterpreter \*interpreter, HYPRE\_MatvecFunctions \*mvfunctions, HYPRE\_Solver \*solver)
- HYPRE\_Int [HYPRE\\_LOBPCGDestroy](#) (HYPRE\_Solver solver)
- HYPRE\_Int [HYPRE\\_LOBPCGSetPrecond](#) (HYPRE\_Solver solver, HYPRE\_PtrToSolverFcn precondition, HYPRE\_PtrToSolverFcn precondition\_setup, HYPRE\_Solver precondition\_solver)
- HYPRE\_Int [HYPRE\\_LOBPCGGetPrecond](#) (HYPRE\_Solver solver, HYPRE\_Solver \*precond\_data\_ptr)
- HYPRE\_Int [HYPRE\\_LOBPCGSetup](#) (HYPRE\_Solver solver, HYPRE\_Matrix A, HYPRE\_Vector b, HYPRE\_Vector x)
- HYPRE\_Int [HYPRE\\_LOBPCGSetupB](#) (HYPRE\_Solver solver, HYPRE\_Matrix B, HYPRE\_Vector x)
- HYPRE\_Int [HYPRE\\_LOBPCGSetupT](#) (HYPRE\_Solver solver, HYPRE\_Matrix T, HYPRE\_Vector x)
- HYPRE\_Int [HYPRE\\_LOBPCGSolve](#) (HYPRE\_Solver solver, mv\_MultiVectorPtr y, mv\_MultiVectorPtr x, HYPRE\_Real \*lambda)
- HYPRE\_Int [HYPRE\\_LOBPCGSetTol](#) (HYPRE\_Solver solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_LOBPCGSetRTol](#) (HYPRE\_Solver solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_LOBPCGSetMaxIter](#) (HYPRE\_Solver solver, HYPRE\_Int max\_iter)
- HYPRE\_Int [HYPRE\\_LOBPCGSetPrecondUsageMode](#) (HYPRE\_Solver solver, HYPRE\_Int mode)
- HYPRE\_Int [HYPRE\\_LOBPCGSetPrintLevel](#) (HYPRE\_Solver solver, HYPRE\_Int level)
- utilities\_FortranMatrix \* [HYPRE\\_LOBPCGResidualNorms](#) (HYPRE\_Solver solver)
- utilities\_FortranMatrix \* [HYPRE\\_LOBPCGResidualNormsHistory](#) (HYPRE\_Solver solver)
- utilities\_FortranMatrix \* [HYPRE\\_LOBPCGEigenvaluesHistory](#) (HYPRE\_Solver solver)
- HYPRE\_Int [HYPRE\\_LOBPCGIterations](#) (HYPRE\_Solver solver)
- void [hypre\\_LOBPCGMultiOperatorB](#) (void \*data, void \*x, void \*y)
- void [lobpcg\\_MultiVectorByMultiVector](#) (mv\_MultiVectorPtr x, mv\_MultiVectorPtr y, utilities\_FortranMatrix \*xy)

### 3.8.1 Detailed Description

These eigensolvers support many of the matrix/vector storage schemes in hypre. They should be used in conjunction with the storage-specific interfaces.

@memo A basic interface for eigensolvers

### 3.8.2 Function Documentation

#### 3.8.2.1 HYPRE\_LOBPCGCreate()

```
HYPRE_Int HYPRE_LOBPCGCreate (
    mv_InterfaceInterpreter * interpreter,
    HYPRE_MatvecFunctions * mvfunctions,
    HYPRE_Solver * solver )
```

LOBPCG constructor.

#### 3.8.2.2 HYPRE\_LOBPCGDestroy()

```
HYPRE_Int HYPRE_LOBPCGDestroy (
    HYPRE_Solver solver )
```

LOBPCG destructor.

#### 3.8.2.3 HYPRE\_LOBPCGEigenvaluesHistory()

```
utilities_FortranMatrix * HYPRE_LOBPCGEigenvaluesHistory (
    HYPRE_Solver solver )
```

#### 3.8.2.4 HYPRE\_LOBPCGGetPrecond()

```
HYPRE_Int HYPRE_LOBPCGGetPrecond (
    HYPRE_Solver solver,
    HYPRE_Solver * precondition_data_ptr )
```

#### 3.8.2.5 HYPRE\_LOBPCGIterations()

```
HYPRE_Int HYPRE_LOBPCGIterations (
    HYPRE_Solver solver )
```

#### 3.8.2.6 hypre\_LOBPCGMultiOperatorB()

```
void hypre_LOBPCGMultiOperatorB (
    void * data,
    void * x,
    void * y )
```



### 3.8.2.7 HYPRE\_LOBPCGResidualNorms()

```
utilities_FortranMatrix * HYPRE_LOBPCGResidualNorms (
    HYPRE_Solver solver )
```

### 3.8.2.8 HYPRE\_LOBPCGResidualNormsHistory()

```
utilities_FortranMatrix * HYPRE_LOBPCGResidualNormsHistory (
    HYPRE_Solver solver )
```

### 3.8.2.9 HYPRE\_LOBPCGSetMaxIter()

```
HYPRE_Int HYPRE_LOBPCGSetMaxIter (
    HYPRE_Solver solver,
    HYPRE_Int max_iter )
```

(Optional) Set maximum number of iterations.

### 3.8.2.10 HYPRE\_LOBPCGSetPrecond()

```
HYPRE_Int HYPRE_LOBPCGSetPrecond (
    HYPRE_Solver solver,
    HYPRE_PtrToSolverFcn precondition,
    HYPRE_PtrToSolverFcn precondition_setup,
    HYPRE_Solver precondition_solver )
```

(Optional) Set the preconditioner to use. If not called, preconditioning is not used.

### 3.8.2.11 HYPRE\_LOBPCGSetPrecondUsageMode()

```
HYPRE_Int HYPRE_LOBPCGSetPrecondUsageMode (
    HYPRE_Solver solver,
    HYPRE_Int mode )
```

Define which initial guess for inner PCG iterations to use: *mode* = 0: use zero initial guess, otherwise use RHS.

### 3.8.2.12 HYPRE\_LOBPCGSetPrintLevel()

```
HYPRE_Int HYPRE_LOBPCGSetPrintLevel (
    HYPRE_Solver solver,
    HYPRE_Int level )
```

(Optional) Set the amount of printing to do to the screen.

**3.8.2.13 HYPRE\_LOBPCGSetRTol()**

```
HYPRE_Int HYPRE_LOBPCGSetRTol (
    HYPRE_Solver solver,
    HYPRE_Real tol )
```

(Optional) Set the relative convergence tolerance.

**3.8.2.14 HYPRE\_LOBPCGSetTol()**

```
HYPRE_Int HYPRE_LOBPCGSetTol (
    HYPRE_Solver solver,
    HYPRE_Real tol )
```

(Optional) Set the absolute convergence tolerance.

**3.8.2.15 HYPRE\_LOBPCGSetup()**

```
HYPRE_Int HYPRE_LOBPCGSetup (
    HYPRE_Solver solver,
    HYPRE_Matrix A,
    HYPRE_Vector b,
    HYPRE_Vector x )
```

Set up  $A$  and the preconditioner (if there is one).

**3.8.2.16 HYPRE\_LOBPCGSetupB()**

```
HYPRE_Int HYPRE_LOBPCGSetupB (
    HYPRE_Solver solver,
    HYPRE_Matrix B,
    HYPRE_Vector x )
```

(Optional) Set up  $B$ . If not called,  $B = I$ .

**3.8.2.17 HYPRE\_LOBPCGSetupT()**

```
HYPRE_Int HYPRE_LOBPCGSetupT (
    HYPRE_Solver solver,
    HYPRE_Matrix T,
    HYPRE_Vector x )
```

(Optional) Set the preconditioning to be applied to  $Tx = b$ , not  $Ax = b$ .

**3.8.2.18 HYPRE\_LOBPCGSolve()**

```
HYPRE_Int HYPRE_LOBPCGSolve (
    HYPRE_Solver solver,
    mv_MultiVectorPtr y,
    mv_MultiVectorPtr x,
    HYPRE_Real * lambda )
```

Solve  $Ax = \lambda Bx$ ,  $y'x = 0$ .

#### 3.8.2.19 lobpcg\_MultiVectorByMultiVector()

```
void lobpcg_MultiVectorByMultiVector (
    mv_MultiVectorPtr x,
    mv_MultiVectorPtr y,
    utilities_FortranMatrix * xy )
```



# Chapter 4

## File Documentation

### 4.1 HYPRE\_IJ\_mv.h File Reference

#### IJ Matrices

- typedef struct hypre\_IJMatrix\_struct \* [HYPRE\\_IJMatrix](#)
- HYPRE\_Int [HYPRE\\_IJMatrixCreate](#) (MPI\_Comm comm, HYPRE\_BigInt ilower, HYPRE\_BigInt iupper, HYPRE\_BigInt jlower, HYPRE\_BigInt jupper, [HYPRE\\_IJMatrix](#) \*matrix)
- HYPRE\_Int [HYPRE\\_IJMatrixDestroy](#) ([HYPRE\\_IJMatrix](#) matrix)
- HYPRE\_Int [HYPRE\\_IJMatrixInitialize](#) ([HYPRE\\_IJMatrix](#) matrix)
- HYPRE\_Int [HYPRE\\_IJMatrixInitialize\\_v2](#) ([HYPRE\\_IJMatrix](#) matrix, HYPRE\_MemoryLocation memory\_↵ location)
- HYPRE\_Int [HYPRE\\_IJMatrixSetValues](#) ([HYPRE\\_IJMatrix](#) matrix, HYPRE\_Int nrows, HYPRE\_Int \*ncols, const HYPRE\_BigInt \*rows, const HYPRE\_BigInt \*cols, const HYPRE\_Complex \*values)
- HYPRE\_Int [HYPRE\\_IJMatrixSetConstantValues](#) ([HYPRE\\_IJMatrix](#) matrix, HYPRE\_Complex value)
- HYPRE\_Int [HYPRE\\_IJMatrixAddToValues](#) ([HYPRE\\_IJMatrix](#) matrix, HYPRE\_Int nrows, HYPRE\_Int \*ncols, const HYPRE\_BigInt \*rows, const HYPRE\_BigInt \*cols, const HYPRE\_Complex \*values)
- HYPRE\_Int [HYPRE\\_IJMatrixSetValues2](#) ([HYPRE\\_IJMatrix](#) matrix, HYPRE\_Int nrows, HYPRE\_Int \*ncols, const HYPRE\_BigInt \*rows, const HYPRE\_Int \*row\_indexes, const HYPRE\_BigInt \*cols, const HYPRE\_↵ Complex \*values)
- HYPRE\_Int [HYPRE\\_IJMatrixAddToValues2](#) ([HYPRE\\_IJMatrix](#) matrix, HYPRE\_Int nrows, HYPRE\_Int \*ncols, const HYPRE\_BigInt \*rows, const HYPRE\_Int \*row\_indexes, const HYPRE\_BigInt \*cols, const HYPRE\_↵ Complex \*values)
- HYPRE\_Int [HYPRE\\_IJMatrixAssemble](#) ([HYPRE\\_IJMatrix](#) matrix)
- HYPRE\_Int [HYPRE\\_IJMatrixGetRowCounts](#) ([HYPRE\\_IJMatrix](#) matrix, HYPRE\_Int nrows, HYPRE\_BigInt \*rows, HYPRE\_Int \*ncols)
- HYPRE\_Int [HYPRE\\_IJMatrixGetValues](#) ([HYPRE\\_IJMatrix](#) matrix, HYPRE\_Int nrows, HYPRE\_Int \*ncols, HYPRE\_BigInt \*rows, HYPRE\_BigInt \*cols, HYPRE\_Complex \*values)
- HYPRE\_Int [HYPRE\\_IJMatrixSetObjectType](#) ([HYPRE\\_IJMatrix](#) matrix, HYPRE\_Int type)
- HYPRE\_Int [HYPRE\\_IJMatrixGetObjectType](#) ([HYPRE\\_IJMatrix](#) matrix, HYPRE\_Int \*type)
- HYPRE\_Int [HYPRE\\_IJMatrixGetLocalRange](#) ([HYPRE\\_IJMatrix](#) matrix, HYPRE\_BigInt \*ilower, HYPRE\_↵ BigInt \*iupper, HYPRE\_BigInt \*jlower, HYPRE\_BigInt \*jupper)
- HYPRE\_Int [HYPRE\\_IJMatrixGetObject](#) ([HYPRE\\_IJMatrix](#) matrix, void \*\*object)
- HYPRE\_Int [HYPRE\\_IJMatrixSetRowSizes](#) ([HYPRE\\_IJMatrix](#) matrix, const HYPRE\_Int \*sizes)
- HYPRE\_Int [HYPRE\\_IJMatrixSetDiagOffdSizes](#) ([HYPRE\\_IJMatrix](#) matrix, const HYPRE\_Int \*diag\_sizes, const HYPRE\_Int \*offdiag\_sizes)
- HYPRE\_Int [HYPRE\\_IJMatrixSetMaxOffProcElmts](#) ([HYPRE\\_IJMatrix](#) matrix, HYPRE\_Int max\_off\_proc\_↵ elmts)
- HYPRE\_Int [HYPRE\\_IJMatrixSetPrintLevel](#) ([HYPRE\\_IJMatrix](#) matrix, HYPRE\_Int print\_level)
- HYPRE\_Int [HYPRE\\_IJMatrixSetOMPFlag](#) ([HYPRE\\_IJMatrix](#) matrix, HYPRE\_Int omp\_flag)
- HYPRE\_Int [HYPRE\\_IJMatrixRead](#) (const char \*filename, MPI\_Comm comm, HYPRE\_Int type, [HYPRE\\_IJMatrix](#) \*matrix)
- HYPRE\_Int [HYPRE\\_IJMatrixPrint](#) ([HYPRE\\_IJMatrix](#) matrix, const char \*filename)

## IJ Vectors

- typedef struct hypre\_IJVector\_struct \* [HYPRE\\_IJVector](#)
- HYPRE\_Int [HYPRE\\_IJVectorCreate](#) (MPI\_Comm comm, HYPRE\_BigInt jlower, HYPRE\_BigInt jupper, [HYPRE\\_IJVector](#) \*vector)
- HYPRE\_Int [HYPRE\\_IJVectorDestroy](#) ([HYPRE\\_IJVector](#) vector)
- HYPRE\_Int [HYPRE\\_IJVectorInitialize](#) ([HYPRE\\_IJVector](#) vector)
- HYPRE\_Int [HYPRE\\_IJVectorInitialize\\_v2](#) ([HYPRE\\_IJVector](#) vector, HYPRE\_MemoryLocation memory\_location)
- HYPRE\_Int [HYPRE\\_IJVectorSetMaxOffProcElmts](#) ([HYPRE\\_IJVector](#) vector, HYPRE\_Int max\_off\_proc\_elmts)
- HYPRE\_Int [HYPRE\\_IJVectorSetValues](#) ([HYPRE\\_IJVector](#) vector, HYPRE\_Int nvalues, const HYPRE\_BigInt \*indices, const HYPRE\_Complex \*values)
- HYPRE\_Int [HYPRE\\_IJVectorAddToValues](#) ([HYPRE\\_IJVector](#) vector, HYPRE\_Int nvalues, const HYPRE\_BigInt \*indices, const HYPRE\_Complex \*values)
- HYPRE\_Int [HYPRE\\_IJVectorAssemble](#) ([HYPRE\\_IJVector](#) vector)
- HYPRE\_Int [HYPRE\\_IJVectorGetValues](#) ([HYPRE\\_IJVector](#) vector, HYPRE\_Int nvalues, const HYPRE\_BigInt \*indices, HYPRE\_Complex \*values)
- HYPRE\_Int [HYPRE\\_IJVectorSetObjectType](#) ([HYPRE\\_IJVector](#) vector, HYPRE\_Int type)
- HYPRE\_Int [HYPRE\\_IJVectorGetObjectType](#) ([HYPRE\\_IJVector](#) vector, HYPRE\_Int \*type)
- HYPRE\_Int [HYPRE\\_IJVectorGetLocalRange](#) ([HYPRE\\_IJVector](#) vector, HYPRE\_BigInt \*jlower, HYPRE\_BigInt \*jupper)
- HYPRE\_Int [HYPRE\\_IJVectorGetObject](#) ([HYPRE\\_IJVector](#) vector, void \*\*object)
- HYPRE\_Int [HYPRE\\_IJVectorSetPrintLevel](#) ([HYPRE\\_IJVector](#) vector, HYPRE\_Int print\_level)
- HYPRE\_Int [HYPRE\\_IJVectorRead](#) (const char \*filename, MPI\_Comm comm, HYPRE\_Int type, [HYPRE\\_IJVector](#) \*vector)
- HYPRE\_Int [HYPRE\\_IJVectorPrint](#) ([HYPRE\\_IJVector](#) vector, const char \*filename)

## 4.2 HYPRE\_krylov.h File Reference

### Functions

#### PCG Solver

- HYPRE\_Int [HYPRE\\_PCGSetup](#) ([HYPRE\\_Solver](#) solver, [HYPRE\\_Matrix](#) A, [HYPRE\\_Vector](#) b, [HYPRE\\_Vector](#) x)
- HYPRE\_Int [HYPRE\\_PCGSolve](#) ([HYPRE\\_Solver](#) solver, [HYPRE\\_Matrix](#) A, [HYPRE\\_Vector](#) b, [HYPRE\\_Vector](#) x)
- HYPRE\_Int [HYPRE\\_PCGSetTol](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_PCGSetAbsoluteTol](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Real a\_tol)
- HYPRE\_Int [HYPRE\\_PCGSetResidualTol](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Real r\_tol)
- HYPRE\_Int [HYPRE\\_PCGSetAbsoluteTolFactor](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Real abstolf)
- HYPRE\_Int [HYPRE\\_PCGSetConvergenceFactorTol](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Real cf\_tol)
- HYPRE\_Int [HYPRE\\_PCGSetStopCrit](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int stop\_crit)
- HYPRE\_Int [HYPRE\\_PCGSetMaxIter](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int max\_iter)
- HYPRE\_Int [HYPRE\\_PCGSetTwoNorm](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int two\_norm)
- HYPRE\_Int [HYPRE\\_PCGSetRelChange](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int rel\_change)
- HYPRE\_Int [HYPRE\\_PCGSetRecomputeResidual](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int recompute\_residual)
- HYPRE\_Int [HYPRE\\_PCGSetRecomputeResidualP](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int recompute\_residual\_p)
- HYPRE\_Int [HYPRE\\_PCGSetPrecond](#) ([HYPRE\\_Solver](#) solver, [HYPRE\\_PtrToSolverFcn](#) precondition, [HYPRE\\_PtrToSolverFcn](#) precondition\_setup, [HYPRE\\_Solver](#) precondition\_solver)
- HYPRE\_Int [HYPRE\\_PCGSetLogging](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int logging)
- HYPRE\_Int [HYPRE\\_PCGSetPrintLevel](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int level)
- HYPRE\_Int [HYPRE\\_PCGGetNumIterations](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int \*num\_iterations)

- HYPRE\_Int [HYPRE\\_PCGGetFinalRelativeResidualNorm](#) (HYPRE\_Solver solver, HYPRE\_Real \*norm)
- HYPRE\_Int [HYPRE\\_PCGGetResidual](#) (HYPRE\_Solver solver, void \*residual)
- HYPRE\_Int [HYPRE\\_PCGGetTol](#) (HYPRE\_Solver solver, HYPRE\_Real \*tol)
- HYPRE\_Int [HYPRE\\_PCGGetResidualTol](#) (HYPRE\_Solver solver, HYPRE\_Real \*rtol)
- HYPRE\_Int [HYPRE\\_PCGGetAbsoluteTolFactor](#) (HYPRE\_Solver solver, HYPRE\_Real \*abstolf)
- HYPRE\_Int [HYPRE\\_PCGGetConvergenceFactorTol](#) (HYPRE\_Solver solver, HYPRE\_Real \*cf\_tol)
- HYPRE\_Int [HYPRE\\_PCGGetStopCrit](#) (HYPRE\_Solver solver, HYPRE\_Int \*stop\_crit)
- HYPRE\_Int [HYPRE\\_PCGGetMaxIter](#) (HYPRE\_Solver solver, HYPRE\_Int \*max\_iter)
- HYPRE\_Int [HYPRE\\_PCGGetTwoNorm](#) (HYPRE\_Solver solver, HYPRE\_Int \*two\_norm)
- HYPRE\_Int [HYPRE\\_PCGGetRelChange](#) (HYPRE\_Solver solver, HYPRE\_Int \*rel\_change)
- HYPRE\_Int [HYPRE\\_GMRESGetSkipRealResidualCheck](#) (HYPRE\_Solver solver, HYPRE\_Int \*skip\_real↔  
real\_r\_check)
- HYPRE\_Int [HYPRE\\_PCGGetPrecond](#) (HYPRE\_Solver solver, HYPRE\_Solver \*precond\_data\_ptr)
- HYPRE\_Int [HYPRE\\_PCGGetLogging](#) (HYPRE\_Solver solver, HYPRE\_Int \*level)
- HYPRE\_Int [HYPRE\\_PCGGetPrintLevel](#) (HYPRE\_Solver solver, HYPRE\_Int \*level)
- HYPRE\_Int [HYPRE\\_PCGGetConverged](#) (HYPRE\_Solver solver, HYPRE\_Int \*converged)

### GMRES Solver

- HYPRE\_Int [HYPRE\\_GMRESSetup](#) (HYPRE\_Solver solver, HYPRE\_Matrix A, HYPRE\_Vector b, HYPRE\_Vector x)
- HYPRE\_Int [HYPRE\\_GMRESSolve](#) (HYPRE\_Solver solver, HYPRE\_Matrix A, HYPRE\_Vector b, HYPRE\_Vector x)
- HYPRE\_Int [HYPRE\\_GMRESSetTol](#) (HYPRE\_Solver solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_GMRESSetAbsoluteTol](#) (HYPRE\_Solver solver, HYPRE\_Real a\_tol)
- HYPRE\_Int [HYPRE\\_GMRESSetConvergenceFactorTol](#) (HYPRE\_Solver solver, HYPRE\_Real cf\_tol)
- HYPRE\_Int [HYPRE\\_GMRESSetStopCrit](#) (HYPRE\_Solver solver, HYPRE\_Int stop\_crit)
- HYPRE\_Int [HYPRE\\_GMRESSetMinIter](#) (HYPRE\_Solver solver, HYPRE\_Int min\_iter)
- HYPRE\_Int [HYPRE\\_GMRESSetMaxIter](#) (HYPRE\_Solver solver, HYPRE\_Int max\_iter)
- HYPRE\_Int [HYPRE\\_GMRESSetKDim](#) (HYPRE\_Solver solver, HYPRE\_Int k\_dim)
- HYPRE\_Int [HYPRE\\_GMRESSetRelChange](#) (HYPRE\_Solver solver, HYPRE\_Int rel\_change)
- HYPRE\_Int [HYPRE\\_GMRESSetSkipRealResidualCheck](#) (HYPRE\_Solver solver, HYPRE\_Int skip\_real↔  
\_r\_check)
- HYPRE\_Int [HYPRE\\_GMRESSetPrecond](#) (HYPRE\_Solver solver, HYPRE\_PtrToSolverFcn precondition, HYPRE\_PtrToSolverFcn precondition\_setup, HYPRE\_Solver precondition\_solver)
- HYPRE\_Int [HYPRE\\_GMRESSetLogging](#) (HYPRE\_Solver solver, HYPRE\_Int logging)
- HYPRE\_Int [HYPRE\\_GMRESSetPrintLevel](#) (HYPRE\_Solver solver, HYPRE\_Int level)
- HYPRE\_Int [HYPRE\\_GMRESGetNumIterations](#) (HYPRE\_Solver solver, HYPRE\_Int \*num\_iterations)
- HYPRE\_Int [HYPRE\\_GMRESGetFinalRelativeResidualNorm](#) (HYPRE\_Solver solver, HYPRE\_Real \*norm)
- HYPRE\_Int [HYPRE\\_GMRESGetResidual](#) (HYPRE\_Solver solver, void \*residual)
- HYPRE\_Int [HYPRE\\_GMRESGetTol](#) (HYPRE\_Solver solver, HYPRE\_Real \*tol)
- HYPRE\_Int [HYPRE\\_GMRESGetAbsoluteTol](#) (HYPRE\_Solver solver, HYPRE\_Real \*tol)
- HYPRE\_Int [HYPRE\\_GMRESGetConvergenceFactorTol](#) (HYPRE\_Solver solver, HYPRE\_Real \*cf\_tol)
- HYPRE\_Int [HYPRE\\_GMRESGetStopCrit](#) (HYPRE\_Solver solver, HYPRE\_Int \*stop\_crit)
- HYPRE\_Int [HYPRE\\_GMRESGetMinIter](#) (HYPRE\_Solver solver, HYPRE\_Int \*min\_iter)
- HYPRE\_Int [HYPRE\\_GMRESGetMaxIter](#) (HYPRE\_Solver solver, HYPRE\_Int \*max\_iter)
- HYPRE\_Int [HYPRE\\_GMRESGetKDim](#) (HYPRE\_Solver solver, HYPRE\_Int \*k\_dim)
- HYPRE\_Int [HYPRE\\_GMRESGetRelChange](#) (HYPRE\_Solver solver, HYPRE\_Int \*rel\_change)
- HYPRE\_Int [HYPRE\\_GMRESGetPrecond](#) (HYPRE\_Solver solver, HYPRE\_Solver \*precond\_data\_ptr)
- HYPRE\_Int [HYPRE\\_GMRESGetLogging](#) (HYPRE\_Solver solver, HYPRE\_Int \*level)
- HYPRE\_Int [HYPRE\\_GMRESGetPrintLevel](#) (HYPRE\_Solver solver, HYPRE\_Int \*level)
- HYPRE\_Int [HYPRE\\_GMRESGetConverged](#) (HYPRE\_Solver solver, HYPRE\_Int \*converged)

### FlexGMRES Solver

- HYPRE\_Int [HYPRE\\_FlexGMRESSetup](#) (HYPRE\_Solver solver, HYPRE\_Matrix A, HYPRE\_Vector b, HYPRE\_Vector x)
- HYPRE\_Int [HYPRE\\_FlexGMRESSolve](#) (HYPRE\_Solver solver, HYPRE\_Matrix A, HYPRE\_Vector b, HYPRE\_Vector x)
- HYPRE\_Int [HYPRE\\_FlexGMRESSetTol](#) (HYPRE\_Solver solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_FlexGMRESSetAbsoluteTol](#) (HYPRE\_Solver solver, HYPRE\_Real a\_tol)

- HYPRE\_Int [HYPRE\\_FlexGMRESSetConvergenceFactorTol](#) (HYPRE\_Solver solver, HYPRE\_Real cf\_tol)
- HYPRE\_Int [HYPRE\\_FlexGMRESSetMinIter](#) (HYPRE\_Solver solver, HYPRE\_Int min\_iter)
- HYPRE\_Int [HYPRE\\_FlexGMRESSetMaxIter](#) (HYPRE\_Solver solver, HYPRE\_Int max\_iter)
- HYPRE\_Int [HYPRE\\_FlexGMRESSetKDim](#) (HYPRE\_Solver solver, HYPRE\_Int k\_dim)
- HYPRE\_Int [HYPRE\\_FlexGMRESSetPrecond](#) (HYPRE\_Solver solver, [HYPRE\\_PtrToSolverFcn](#) precondition, [HYPRE\\_PtrToSolverFcn](#) precondition\_setup, HYPRE\_Solver precondition\_solver)
- HYPRE\_Int [HYPRE\\_FlexGMRESSetLogging](#) (HYPRE\_Solver solver, HYPRE\_Int logging)
- HYPRE\_Int [HYPRE\\_FlexGMRESSetPrintLevel](#) (HYPRE\_Solver solver, HYPRE\_Int level)
- HYPRE\_Int [HYPRE\\_FlexGMRESSetNumIterations](#) (HYPRE\_Solver solver, HYPRE\_Int \*num\_iterations)
- HYPRE\_Int [HYPRE\\_FlexGMRESSetFinalRelativeResidualNorm](#) (HYPRE\_Solver solver, HYPRE\_Real \*norm)
- HYPRE\_Int [HYPRE\\_FlexGMRESSetResidual](#) (HYPRE\_Solver solver, void \*residual)
- HYPRE\_Int [HYPRE\\_FlexGMRESSetTol](#) (HYPRE\_Solver solver, HYPRE\_Real \*tol)
- HYPRE\_Int [HYPRE\\_FlexGMRESSetConvergenceFactorTol](#) (HYPRE\_Solver solver, HYPRE\_Real \*cf\_↵tol)
- HYPRE\_Int [HYPRE\\_FlexGMRESSetStopCrit](#) (HYPRE\_Solver solver, HYPRE\_Int \*stop\_crit)
- HYPRE\_Int [HYPRE\\_FlexGMRESSetMinIter](#) (HYPRE\_Solver solver, HYPRE\_Int \*min\_iter)
- HYPRE\_Int [HYPRE\\_FlexGMRESSetMaxIter](#) (HYPRE\_Solver solver, HYPRE\_Int \*max\_iter)
- HYPRE\_Int [HYPRE\\_FlexGMRESSetKDim](#) (HYPRE\_Solver solver, HYPRE\_Int \*k\_dim)
- HYPRE\_Int [HYPRE\\_FlexGMRESSetPrecond](#) (HYPRE\_Solver solver, [HYPRE\\_Solver](#) \*precond\_data\_↵ptr)
- HYPRE\_Int [HYPRE\\_FlexGMRESSetLogging](#) (HYPRE\_Solver solver, HYPRE\_Int \*level)
- HYPRE\_Int [HYPRE\\_FlexGMRESSetPrintLevel](#) (HYPRE\_Solver solver, HYPRE\_Int \*level)
- HYPRE\_Int [HYPRE\\_FlexGMRESSetConverged](#) (HYPRE\_Solver solver, HYPRE\_Int \*converged)
- HYPRE\_Int [HYPRE\\_FlexGMRESSetModifyPC](#) (HYPRE\_Solver solver, [HYPRE\\_PtrToModifyPCFcn](#) modify\_pc)

## LGMRES Solver

- HYPRE\_Int [HYPRE\\_LGMRESSetup](#) (HYPRE\_Solver solver, [HYPRE\\_Matrix](#) A, [HYPRE\\_Vector](#) b, [HYPRE\\_Vector](#) x)
- HYPRE\_Int [HYPRE\\_LGMRESSolve](#) (HYPRE\_Solver solver, [HYPRE\\_Matrix](#) A, [HYPRE\\_Vector](#) b, [HYPRE\\_Vector](#) x)
- HYPRE\_Int [HYPRE\\_LGMRESSetTol](#) (HYPRE\_Solver solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_LGMRESSetAbsoluteTol](#) (HYPRE\_Solver solver, HYPRE\_Real a\_tol)
- HYPRE\_Int [HYPRE\\_LGMRESSetConvergenceFactorTol](#) (HYPRE\_Solver solver, HYPRE\_Real cf\_tol)
- HYPRE\_Int [HYPRE\\_LGMRESSetMinIter](#) (HYPRE\_Solver solver, HYPRE\_Int min\_iter)
- HYPRE\_Int [HYPRE\\_LGMRESSetMaxIter](#) (HYPRE\_Solver solver, HYPRE\_Int max\_iter)
- HYPRE\_Int [HYPRE\\_LGMRESSetKDim](#) (HYPRE\_Solver solver, HYPRE\_Int k\_dim)
- HYPRE\_Int [HYPRE\\_LGMRESSetAugDim](#) (HYPRE\_Solver solver, HYPRE\_Int aug\_dim)
- HYPRE\_Int [HYPRE\\_LGMRESSetPrecond](#) (HYPRE\_Solver solver, [HYPRE\\_PtrToSolverFcn](#) precondition, [HYPRE\\_PtrToSolverFcn](#) precondition\_setup, HYPRE\_Solver precondition\_solver)
- HYPRE\_Int [HYPRE\\_LGMRESSetLogging](#) (HYPRE\_Solver solver, HYPRE\_Int logging)
- HYPRE\_Int [HYPRE\\_LGMRESSetPrintLevel](#) (HYPRE\_Solver solver, HYPRE\_Int level)
- HYPRE\_Int [HYPRE\\_LGMRESSetNumIterations](#) (HYPRE\_Solver solver, HYPRE\_Int \*num\_iterations)
- HYPRE\_Int [HYPRE\\_LGMRESSetFinalRelativeResidualNorm](#) (HYPRE\_Solver solver, HYPRE\_Real \*norm)
- HYPRE\_Int [HYPRE\\_LGMRESSetResidual](#) (HYPRE\_Solver solver, void \*residual)
- HYPRE\_Int [HYPRE\\_LGMRESSetTol](#) (HYPRE\_Solver solver, HYPRE\_Real \*tol)
- HYPRE\_Int [HYPRE\\_LGMRESSetConvergenceFactorTol](#) (HYPRE\_Solver solver, HYPRE\_Real \*cf\_tol)
- HYPRE\_Int [HYPRE\\_LGMRESSetStopCrit](#) (HYPRE\_Solver solver, HYPRE\_Int \*stop\_crit)
- HYPRE\_Int [HYPRE\\_LGMRESSetMinIter](#) (HYPRE\_Solver solver, HYPRE\_Int \*min\_iter)
- HYPRE\_Int [HYPRE\\_LGMRESSetMaxIter](#) (HYPRE\_Solver solver, HYPRE\_Int \*max\_iter)
- HYPRE\_Int [HYPRE\\_LGMRESSetKDim](#) (HYPRE\_Solver solver, HYPRE\_Int \*k\_dim)
- HYPRE\_Int [HYPRE\\_LGMRESSetAugDim](#) (HYPRE\_Solver solver, HYPRE\_Int \*k\_dim)
- HYPRE\_Int [HYPRE\\_LGMRESSetPrecond](#) (HYPRE\_Solver solver, [HYPRE\\_Solver](#) \*precond\_data\_ptr)
- HYPRE\_Int [HYPRE\\_LGMRESSetLogging](#) (HYPRE\_Solver solver, HYPRE\_Int \*level)
- HYPRE\_Int [HYPRE\\_LGMRESSetPrintLevel](#) (HYPRE\_Solver solver, HYPRE\_Int \*level)
- HYPRE\_Int [HYPRE\\_LGMRESSetConverged](#) (HYPRE\_Solver solver, HYPRE\_Int \*converged)

## COGMRES Solver



- HYPRE\_Int [HYPRE\\_COGMRESSetup](#) (HYPRE\_Solver solver, HYPRE\_Matrix A, HYPRE\_Vector b, HYPRE\_Vector x)
- HYPRE\_Int [HYPRE\\_COGMRESSolve](#) (HYPRE\_Solver solver, HYPRE\_Matrix A, HYPRE\_Vector b, HYPRE\_Vector x)
- HYPRE\_Int [HYPRE\\_COGMRESSetTol](#) (HYPRE\_Solver solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_COGMRESSetAbsoluteTol](#) (HYPRE\_Solver solver, HYPRE\_Real a\_tol)
- HYPRE\_Int [HYPRE\\_COGMRESSetConvergenceFactorTol](#) (HYPRE\_Solver solver, HYPRE\_Real cf\_tol)
- HYPRE\_Int [HYPRE\\_COGMRESSetMinIter](#) (HYPRE\_Solver solver, HYPRE\_Int min\_iter)
- HYPRE\_Int [HYPRE\\_COGMRESSetMaxIter](#) (HYPRE\_Solver solver, HYPRE\_Int max\_iter)
- HYPRE\_Int [HYPRE\\_COGMRESSetKDim](#) (HYPRE\_Solver solver, HYPRE\_Int k\_dim)
- HYPRE\_Int [HYPRE\\_COGMRESSetUnroll](#) (HYPRE\_Solver solver, HYPRE\_Int unroll)
- HYPRE\_Int [HYPRE\\_COGMRESSetCGS](#) (HYPRE\_Solver solver, HYPRE\_Int cgs)
- HYPRE\_Int [HYPRE\\_COGMRESSetPrecond](#) (HYPRE\_Solver solver, HYPRE\_PtrToSolverFcn precondition, HYPRE\_PtrToSolverFcn precondition\_setup, HYPRE\_Solver precondition\_solver)
- HYPRE\_Int [HYPRE\\_COGMRESSetLogging](#) (HYPRE\_Solver solver, HYPRE\_Int logging)
- HYPRE\_Int [HYPRE\\_COGMRESSetPrintLevel](#) (HYPRE\_Solver solver, HYPRE\_Int level)
- HYPRE\_Int [HYPRE\\_COGMRESGetNumIterations](#) (HYPRE\_Solver solver, HYPRE\_Int \*num\_iterations)
- HYPRE\_Int [HYPRE\\_COGMRESGetFinalRelativeResidualNorm](#) (HYPRE\_Solver solver, HYPRE\_Real \*norm)
- HYPRE\_Int [HYPRE\\_COGMRESGetResidual](#) (HYPRE\_Solver solver, void \*residual)
- HYPRE\_Int [HYPRE\\_COGMRESGetTol](#) (HYPRE\_Solver solver, HYPRE\_Real \*tol)
- HYPRE\_Int [HYPRE\\_COGMRESGetConvergenceFactorTol](#) (HYPRE\_Solver solver, HYPRE\_Real \*cf\_tol)
- HYPRE\_Int [HYPRE\\_COGMRESGetMinIter](#) (HYPRE\_Solver solver, HYPRE\_Int \*min\_iter)
- HYPRE\_Int [HYPRE\\_COGMRESGetMaxIter](#) (HYPRE\_Solver solver, HYPRE\_Int \*max\_iter)
- HYPRE\_Int [HYPRE\\_COGMRESGetKDim](#) (HYPRE\_Solver solver, HYPRE\_Int \*k\_dim)
- HYPRE\_Int [HYPRE\\_COGMRESGetUnroll](#) (HYPRE\_Solver solver, HYPRE\_Int \*unroll)
- HYPRE\_Int [HYPRE\\_COGMRESGetCGS](#) (HYPRE\_Solver solver, HYPRE\_Int \*cgs)
- HYPRE\_Int [HYPRE\\_COGMRESGetPrecond](#) (HYPRE\_Solver solver, HYPRE\_Solver \*precond\_data\_ptr)
- HYPRE\_Int [HYPRE\\_COGMRESGetLogging](#) (HYPRE\_Solver solver, HYPRE\_Int \*level)
- HYPRE\_Int [HYPRE\\_COGMRESGetPrintLevel](#) (HYPRE\_Solver solver, HYPRE\_Int \*level)
- HYPRE\_Int [HYPRE\\_COGMRESGetConverged](#) (HYPRE\_Solver solver, HYPRE\_Int \*converged)
- HYPRE\_Int [HYPRE\\_COGMRESSetModifyPC](#) (HYPRE\_Solver solver, HYPRE\_PtrToModifyPCFcn modify\_pc)

### BiCGSTAB Solver

- HYPRE\_Int [HYPRE\\_BiCGSTABDestroy](#) (HYPRE\_Solver solver)
- HYPRE\_Int [HYPRE\\_BiCGSTABSetup](#) (HYPRE\_Solver solver, HYPRE\_Matrix A, HYPRE\_Vector b, HYPRE\_Vector x)
- HYPRE\_Int [HYPRE\\_BiCGSTABSolve](#) (HYPRE\_Solver solver, HYPRE\_Matrix A, HYPRE\_Vector b, HYPRE\_Vector x)
- HYPRE\_Int [HYPRE\\_BiCGSTABSetTol](#) (HYPRE\_Solver solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_BiCGSTABSetAbsoluteTol](#) (HYPRE\_Solver solver, HYPRE\_Real a\_tol)
- HYPRE\_Int [HYPRE\\_BiCGSTABSetConvergenceFactorTol](#) (HYPRE\_Solver solver, HYPRE\_Real cf\_tol)
- HYPRE\_Int [HYPRE\\_BiCGSTABSetStopCrit](#) (HYPRE\_Solver solver, HYPRE\_Int stop\_crit)
- HYPRE\_Int [HYPRE\\_BiCGSTABSetMinIter](#) (HYPRE\_Solver solver, HYPRE\_Int min\_iter)
- HYPRE\_Int [HYPRE\\_BiCGSTABSetMaxIter](#) (HYPRE\_Solver solver, HYPRE\_Int max\_iter)
- HYPRE\_Int [HYPRE\\_BiCGSTABSetPrecond](#) (HYPRE\_Solver solver, HYPRE\_PtrToSolverFcn precondition, HYPRE\_PtrToSolverFcn precondition\_setup, HYPRE\_Solver precondition\_solver)
- HYPRE\_Int [HYPRE\\_BiCGSTABSetLogging](#) (HYPRE\_Solver solver, HYPRE\_Int logging)
- HYPRE\_Int [HYPRE\\_BiCGSTABSetPrintLevel](#) (HYPRE\_Solver solver, HYPRE\_Int level)
- HYPRE\_Int [HYPRE\\_BiCGSTABGetNumIterations](#) (HYPRE\_Solver solver, HYPRE\_Int \*num\_iterations)
- HYPRE\_Int [HYPRE\\_BiCGSTABGetFinalRelativeResidualNorm](#) (HYPRE\_Solver solver, HYPRE\_Real \*norm)
- HYPRE\_Int [HYPRE\\_BiCGSTABGetResidual](#) (HYPRE\_Solver solver, void \*residual)
- HYPRE\_Int [HYPRE\\_BiCGSTABGetPrecond](#) (HYPRE\_Solver solver, HYPRE\_Solver \*precond\_data\_ptr)

### CGNR Solver

- HYPRE\_Int [HYPRE\\_CGNRDestroy](#) (HYPRE\_Solver solver)

- `HYPRE_Int HYPRE_CGNRSetup` (`HYPRE_Solver` solver, `HYPRE_Matrix` A, `HYPRE_Vector` b, `HYPRE_Vector` x)
- `HYPRE_Int HYPRE_CGNRSolve` (`HYPRE_Solver` solver, `HYPRE_Matrix` A, `HYPRE_Vector` b, `HYPRE_Vector` x)
- `HYPRE_Int HYPRE_CGNRSetTol` (`HYPRE_Solver` solver, `HYPRE_Real` tol)
- `HYPRE_Int HYPRE_CGNRSetStopCrit` (`HYPRE_Solver` solver, `HYPRE_Int` stop\_crit)
- `HYPRE_Int HYPRE_CGNRSetMinIter` (`HYPRE_Solver` solver, `HYPRE_Int` min\_iter)
- `HYPRE_Int HYPRE_CGNRSetMaxIter` (`HYPRE_Solver` solver, `HYPRE_Int` max\_iter)
- `HYPRE_Int HYPRE_CGNRSetPrecond` (`HYPRE_Solver` solver, `HYPRE_PtrToSolverFcn` precondition, `HYPRE_PtrToSolverFcn` preconditionT, `HYPRE_PtrToSolverFcn` precondition\_setup, `HYPRE_Solver` precondition\_solver)
- `HYPRE_Int HYPRE_CGNRSetLogging` (`HYPRE_Solver` solver, `HYPRE_Int` logging)
- `HYPRE_Int HYPRE_CGNRGetNumIterations` (`HYPRE_Solver` solver, `HYPRE_Int` \*num\_iterations)
- `HYPRE_Int HYPRE_CGNRGetFinalRelativeResidualNorm` (`HYPRE_Solver` solver, `HYPRE_Real` \*norm)
- `HYPRE_Int HYPRE_CGNRGetPrecond` (`HYPRE_Solver` solver, `HYPRE_Solver` \*precond\_data\_ptr)

### Krylov Solvers

- `#define HYPRE_SOLVER_STRUCT`
- `#define HYPRE_MATRIX_STRUCT`
- `#define HYPRE_VECTOR_STRUCT`
- `#define HYPRE_MODIFYPC`
- `typedef struct hypre_Solver_struct * HYPRE_Solver`
- `typedef struct hypre_Matrix_struct * HYPRE_Matrix`
- `typedef struct hypre_Vector_struct * HYPRE_Vector`
- `typedef HYPRE_Int(* HYPRE_PtrToSolverFcn) (HYPRE_Solver, HYPRE_Matrix, HYPRE_Vector, HYPRE_Vector)`
- `typedef HYPRE_Int(* HYPRE_PtrToModifyPCFcn) (HYPRE_Solver, HYPRE_Int, HYPRE_Real)`

## 4.3 HYPRE\_lobpcg.h File Reference

### Functions

#### LOBPCG Eigensolver

- `HYPRE_Int HYPRE_LOBPCGCreate` (`mv_InterfaceInterpreter` \*interpreter, `HYPRE_MatvecFunctions` \*mvfunctions, `HYPRE_Solver` \*solver)
- `HYPRE_Int HYPRE_LOBPCGDestroy` (`HYPRE_Solver` solver)
- `HYPRE_Int HYPRE_LOBPCGSetPrecond` (`HYPRE_Solver` solver, `HYPRE_PtrToSolverFcn` precondition, `HYPRE_PtrToSolverFcn` precondition\_setup, `HYPRE_Solver` precondition\_solver)
- `HYPRE_Int HYPRE_LOBPCGGetPrecond` (`HYPRE_Solver` solver, `HYPRE_Solver` \*precond\_data\_ptr)
- `HYPRE_Int HYPRE_LOBPCGSetup` (`HYPRE_Solver` solver, `HYPRE_Matrix` A, `HYPRE_Vector` b, `HYPRE_Vector` x)
- `HYPRE_Int HYPRE_LOBPCGSetupB` (`HYPRE_Solver` solver, `HYPRE_Matrix` B, `HYPRE_Vector` x)
- `HYPRE_Int HYPRE_LOBPCGSetupT` (`HYPRE_Solver` solver, `HYPRE_Matrix` T, `HYPRE_Vector` x)
- `HYPRE_Int HYPRE_LOBPCGSolve` (`HYPRE_Solver` solver, `mv_MultiVectorPtr` y, `mv_MultiVectorPtr` x, `HYPRE_Real` \*lambda)
- `HYPRE_Int HYPRE_LOBPCGSetTol` (`HYPRE_Solver` solver, `HYPRE_Real` tol)
- `HYPRE_Int HYPRE_LOBPCGSetRTol` (`HYPRE_Solver` solver, `HYPRE_Real` tol)
- `HYPRE_Int HYPRE_LOBPCGSetMaxIter` (`HYPRE_Solver` solver, `HYPRE_Int` max\_iter)
- `HYPRE_Int HYPRE_LOBPCGSetPrecondUsageMode` (`HYPRE_Solver` solver, `HYPRE_Int` mode)
- `HYPRE_Int HYPRE_LOBPCGSetPrintLevel` (`HYPRE_Solver` solver, `HYPRE_Int` level)
- `utilities_FortranMatrix * HYPRE_LOBPCGResidualNorms` (`HYPRE_Solver` solver)
- `utilities_FortranMatrix * HYPRE_LOBPCGResidualNormsHistory` (`HYPRE_Solver` solver)
- `utilities_FortranMatrix * HYPRE_LOBPCGEigenvaluesHistory` (`HYPRE_Solver` solver)
- `HYPRE_Int HYPRE_LOBPCGIterations` (`HYPRE_Solver` solver)
- `void hypre_LOBPCGMultiOperatorB` (`void` \*data, `void` \*x, `void` \*y)
- `void lobpcg_MultiVectorByMultiVector` (`mv_MultiVectorPtr` x, `mv_MultiVectorPtr` y, `utilities_FortranMatrix` \*xy)

## 4.4 HYPRE\_parcsr\_ls.h File Reference

### Functions

- HYPRE\_Int [HYPRE\\_SchwarzCreate](#) (HYPRE\_Solver \*solver)
- HYPRE\_Int [HYPRE\\_SchwarzDestroy](#) (HYPRE\_Solver solver)
- HYPRE\_Int [HYPRE\\_SchwarzSetup](#) (HYPRE\_Solver solver, HYPRE\_ParCSRMatrix A, HYPRE\_ParVector b, HYPRE\_ParVector x)
- HYPRE\_Int [HYPRE\\_SchwarzSolve](#) (HYPRE\_Solver solver, HYPRE\_ParCSRMatrix A, HYPRE\_ParVector b, HYPRE\_ParVector x)
- HYPRE\_Int [HYPRE\\_SchwarzSetVariant](#) (HYPRE\_Solver solver, HYPRE\_Int variant)
- HYPRE\_Int [HYPRE\\_SchwarzSetOverlap](#) (HYPRE\_Solver solver, HYPRE\_Int overlap)
- HYPRE\_Int [HYPRE\\_SchwarzSetDomainType](#) (HYPRE\_Solver solver, HYPRE\_Int domain\_type)
- HYPRE\_Int [HYPRE\\_SchwarzSetRelaxWeight](#) (HYPRE\_Solver solver, HYPRE\_Real relax\_weight)
- HYPRE\_Int [HYPRE\\_SchwarzSetDomainStructure](#) (HYPRE\_Solver solver, HYPRE\_CSRMatrix domain\_↵ structure)
- HYPRE\_Int [HYPRE\\_SchwarzSetNumFunctions](#) (HYPRE\_Solver solver, HYPRE\_Int num\_functions)
- HYPRE\_Int [HYPRE\\_SchwarzSetDofFunc](#) (HYPRE\_Solver solver, HYPRE\_Int \*dof\_func)
- HYPRE\_Int [HYPRE\\_SchwarzSetNonSymm](#) (HYPRE\_Solver solver, HYPRE\_Int use\_nonsymm)
- HYPRE\_Int [HYPRE\\_ParCSRCreate](#) (MPI\_Comm comm, HYPRE\_Solver \*solver)
- HYPRE\_Int [HYPRE\\_ParCSRDestroy](#) (HYPRE\_Solver solver)
- HYPRE\_Int [HYPRE\\_ParCSRSetup](#) (HYPRE\_Solver solver, HYPRE\_ParCSRMatrix A, HYPRE\_Par↵ Vector b, HYPRE\_ParVector x)
- HYPRE\_Int [HYPRE\\_ParCSRSolve](#) (HYPRE\_Solver solver, HYPRE\_ParCSRMatrix A, HYPRE\_Par↵ Vector b, HYPRE\_ParVector x)
- HYPRE\_Int [HYPRE\\_ParCSRSetTol](#) (HYPRE\_Solver solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_ParCSRSetMinIter](#) (HYPRE\_Solver solver, HYPRE\_Int min\_iter)
- HYPRE\_Int [HYPRE\\_ParCSRSetMaxIter](#) (HYPRE\_Solver solver, HYPRE\_Int max\_iter)
- HYPRE\_Int [HYPRE\\_ParCSRSetStopCrit](#) (HYPRE\_Solver solver, HYPRE\_Int stop\_crit)
- HYPRE\_Int [HYPRE\\_ParCSRSetPrecond](#) (HYPRE\_Solver solver, HYPRE\_PtrToParSolverFcn pre↵ cond, HYPRE\_PtrToParSolverFcn preconditionT, HYPRE\_PtrToParSolverFcn precondition\_setup, HYPRE\_Solver precondition\_solver)
- HYPRE\_Int [HYPRE\\_ParCSRGetPrecond](#) (HYPRE\_Solver solver, HYPRE\_Solver \*precond\_data)
- HYPRE\_Int [HYPRE\\_ParCSRSetLogging](#) (HYPRE\_Solver solver, HYPRE\_Int logging)
- HYPRE\_Int [HYPRE\\_ParCSRGetNumIterations](#) (HYPRE\_Solver solver, HYPRE\_Int \*num\_iterations)
- HYPRE\_Int [HYPRE\\_ParCSRGetFinalRelativeResidualNorm](#) (HYPRE\_Solver solver, HYPRE\_Real \*norm)

### ParCSR BoomerAMG Solver and Preconditioner

*Parallel unstructured algebraic multigrid solver and preconditioner*

- HYPRE\_Int [HYPRE\\_BoomerAMGCreate](#) (HYPRE\_Solver \*solver)
- HYPRE\_Int [HYPRE\\_BoomerAMGDestroy](#) (HYPRE\_Solver solver)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetup](#) (HYPRE\_Solver solver, HYPRE\_ParCSRMatrix A, HYPRE\_↵ ParVector b, HYPRE\_ParVector x)
- HYPRE\_Int [HYPRE\\_BoomerAMGSolve](#) (HYPRE\_Solver solver, HYPRE\_ParCSRMatrix A, HYPRE\_Par↵ Vector b, HYPRE\_ParVector x)
- HYPRE\_Int [HYPRE\\_BoomerAMGSolveT](#) (HYPRE\_Solver solver, HYPRE\_ParCSRMatrix A, HYPRE\_↵ ParVector b, HYPRE\_ParVector x)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetOldDefault](#) (HYPRE\_Solver solver)
- HYPRE\_Int [HYPRE\\_BoomerAMGGetResidual](#) (HYPRE\_Solver solver, HYPRE\_ParVector \*residual)
- HYPRE\_Int [HYPRE\\_BoomerAMGGetNumIterations](#) (HYPRE\_Solver solver, HYPRE\_Int \*num\_iterations)
- HYPRE\_Int [HYPRE\\_BoomerAMGGetFinalRelativeResidualNorm](#) (HYPRE\_Solver solver, HYPRE\_Real \*rel\_resid\_norm)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetNumFunctions](#) (HYPRE\_Solver solver, HYPRE\_Int num\_functions)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetDofFunc](#) (HYPRE\_Solver solver, HYPRE\_Int \*dof\_func)

- HYPRE\_Int [HYPRE\\_BoomerAMGSetConvergeType](#) (HYPRE\_Solver solver, HYPRE\_Int type)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetTol](#) (HYPRE\_Solver solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetMaxIter](#) (HYPRE\_Solver solver, HYPRE\_Int max\_iter)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetMinIter](#) (HYPRE\_Solver solver, HYPRE\_Int min\_iter)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetMaxCoarseSize](#) (HYPRE\_Solver solver, HYPRE\_Int max\_coarse\_↵  
size)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetMinCoarseSize](#) (HYPRE\_Solver solver, HYPRE\_Int min\_coarse\_↵  
size)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetMaxLevels](#) (HYPRE\_Solver solver, HYPRE\_Int max\_levels)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetCoarsenCutFactor](#) (HYPRE\_Solver solver, HYPRE\_Int coarsen\_↵  
cut\_factor)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetStrongThreshold](#) (HYPRE\_Solver solver, HYPRE\_Real strong\_↵  
threshold)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetStrongThresholdR](#) (HYPRE\_Solver solver, HYPRE\_Real strong\_↵  
threshold)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetFilterThresholdR](#) (HYPRE\_Solver solver, HYPRE\_Real filter\_↵  
threshold)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetSCommPkgSwitch](#) (HYPRE\_Solver solver, HYPRE\_Real S\_↵  
commpkg\_switch)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetMaxRowSum](#) (HYPRE\_Solver solver, HYPRE\_Real max\_row\_sum)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetCoarsenType](#) (HYPRE\_Solver solver, HYPRE\_Int coarsen\_type)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetNonGalerkinTol](#) (HYPRE\_Solver solver, HYPRE\_Real nongalerkin\_↵  
tol)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetLevelNonGalerkinTol](#) (HYPRE\_Solver solver, HYPRE\_Real  
nongalerkin\_tol, HYPRE\_Int level)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetNonGalerkTol](#) (HYPRE\_Solver solver, HYPRE\_Int nongalerk\_num\_↵  
tol, HYPRE\_Real \*nongalerk\_tol)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetMeasureType](#) (HYPRE\_Solver solver, HYPRE\_Int measure\_type)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetAggNumLevels](#) (HYPRE\_Solver solver, HYPRE\_Int agg\_num\_↵  
levels)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetNumPaths](#) (HYPRE\_Solver solver, HYPRE\_Int num\_paths)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetCGCIts](#) (HYPRE\_Solver solver, HYPRE\_Int its)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetNodal](#) (HYPRE\_Solver solver, HYPRE\_Int nodal)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetNodalDiag](#) (HYPRE\_Solver solver, HYPRE\_Int nodal\_diag)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetKeepSameSign](#) (HYPRE\_Solver solver, HYPRE\_Int keep\_same\_↵  
sign)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetInterpType](#) (HYPRE\_Solver solver, HYPRE\_Int interp\_type)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetTruncFactor](#) (HYPRE\_Solver solver, HYPRE\_Real trunc\_factor)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetPMaxElmts](#) (HYPRE\_Solver solver, HYPRE\_Int P\_max\_elmts)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetSepWeight](#) (HYPRE\_Solver solver, HYPRE\_Int sep\_weight)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetAggInterpType](#) (HYPRE\_Solver solver, HYPRE\_Int agg\_interp\_↵  
type)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetAggTruncFactor](#) (HYPRE\_Solver solver, HYPRE\_Real agg\_trunc\_↵  
factor)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetAggP12TruncFactor](#) (HYPRE\_Solver solver, HYPRE\_Real agg\_↵  
P12\_trunc\_factor)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetAggPMaxElmts](#) (HYPRE\_Solver solver, HYPRE\_Int agg\_P\_max\_↵  
elmts)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetAggP12MaxElmts](#) (HYPRE\_Solver solver, HYPRE\_Int agg\_P12\_↵  
max\_elmts)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetInterpVectors](#) (HYPRE\_Solver solver, HYPRE\_Int num\_vectors,  
HYPRE\_ParVector \*interp\_vectors)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetInterpVecVariant](#) (HYPRE\_Solver solver, HYPRE\_Int var)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetInterpVecQMax](#) (HYPRE\_Solver solver, HYPRE\_Int q\_max)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetInterpVecAbsQTrunc](#) (HYPRE\_Solver solver, HYPRE\_Real q\_trunc)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetGSMG](#) (HYPRE\_Solver solver, HYPRE\_Int gsmg)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetNumSamples](#) (HYPRE\_Solver solver, HYPRE\_Int num\_samples)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetCycleType](#) (HYPRE\_Solver solver, HYPRE\_Int cycle\_type)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetFCycle](#) (HYPRE\_Solver solver, HYPRE\_Int fcycle)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetAdditive](#) (HYPRE\_Solver solver, HYPRE\_Int addlvl)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetMultAdditive](#) (HYPRE\_Solver solver, HYPRE\_Int addlvl)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetSimple](#) (HYPRE\_Solver solver, HYPRE\_Int addlvl)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetAddLastLvl](#) (HYPRE\_Solver solver, HYPRE\_Int add\_last\_lvl)

- HYPRE\_Int [HYPRE\\_BoomerAMGSetMultAddTruncFactor](#) (HYPRE\_Solver solver, HYPRE\_Real add\_↵  
trunc\_factor)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetMultAddPMaxElmts](#) (HYPRE\_Solver solver, HYPRE\_Int add\_P\_↵  
max\_elmts)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetAddRelaxType](#) (HYPRE\_Solver solver, HYPRE\_Int add\_rlx\_type)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetAddRelaxWt](#) (HYPRE\_Solver solver, HYPRE\_Real add\_rlx\_wt)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetSeqThreshold](#) (HYPRE\_Solver solver, HYPRE\_Int seq\_threshold)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetRedundant](#) (HYPRE\_Solver solver, HYPRE\_Int redundant)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetNumGridSweeps](#) (HYPRE\_Solver solver, HYPRE\_Int \*num\_grid\_↵  
sweeps)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetNumSweeps](#) (HYPRE\_Solver solver, HYPRE\_Int num\_sweeps)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetCycleNumSweeps](#) (HYPRE\_Solver solver, HYPRE\_Int num\_↵  
sweeps, HYPRE\_Int k)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetGridRelaxType](#) (HYPRE\_Solver solver, HYPRE\_Int \*grid\_relax\_↵  
type)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetRelaxType](#) (HYPRE\_Solver solver, HYPRE\_Int relax\_type)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetCycleRelaxType](#) (HYPRE\_Solver solver, HYPRE\_Int relax\_type,  
HYPRE\_Int k)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetRelaxOrder](#) (HYPRE\_Solver solver, HYPRE\_Int relax\_order)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetGridRelaxPoints](#) (HYPRE\_Solver solver, HYPRE\_Int \*\*grid\_relax\_↵  
points)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetRelaxWeight](#) (HYPRE\_Solver solver, HYPRE\_Real \*relax\_weight)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetRelaxWt](#) (HYPRE\_Solver solver, HYPRE\_Real relax\_weight)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetLevelRelaxWt](#) (HYPRE\_Solver solver, HYPRE\_Real relax\_weight,  
HYPRE\_Int level)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetOmega](#) (HYPRE\_Solver solver, HYPRE\_Real \*omega)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetOuterWt](#) (HYPRE\_Solver solver, HYPRE\_Real omega)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetLevelOuterWt](#) (HYPRE\_Solver solver, HYPRE\_Real omega,  
HYPRE\_Int level)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetChebyOrder](#) (HYPRE\_Solver solver, HYPRE\_Int order)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetChebyFraction](#) (HYPRE\_Solver solver, HYPRE\_Real ratio)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetChebyScale](#) (HYPRE\_Solver solver, HYPRE\_Int scale)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetChebyVariant](#) (HYPRE\_Solver solver, HYPRE\_Int variant)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetChebyEigEst](#) (HYPRE\_Solver solver, HYPRE\_Int eig\_est)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetSmoothType](#) (HYPRE\_Solver solver, HYPRE\_Int smooth\_type)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetSmoothNumLevels](#) (HYPRE\_Solver solver, HYPRE\_Int smooth\_↵  
num\_levels)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetSmoothNumSweeps](#) (HYPRE\_Solver solver, HYPRE\_Int smooth\_↵  
num\_sweeps)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetVariant](#) (HYPRE\_Solver solver, HYPRE\_Int variant)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetOverlap](#) (HYPRE\_Solver solver, HYPRE\_Int overlap)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetDomainType](#) (HYPRE\_Solver solver, HYPRE\_Int domain\_type)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetSchwarzRlxWeight](#) (HYPRE\_Solver solver, HYPRE\_Real schwarz\_↵  
rlx\_weight)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetSchwarzUseNonSymm](#) (HYPRE\_Solver solver, HYPRE\_Int use\_↵  
nonsymm)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetSym](#) (HYPRE\_Solver solver, HYPRE\_Int sym)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetLevel](#) (HYPRE\_Solver solver, HYPRE\_Int level)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetThreshold](#) (HYPRE\_Solver solver, HYPRE\_Real threshold)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetFilter](#) (HYPRE\_Solver solver, HYPRE\_Real filter)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetDropTol](#) (HYPRE\_Solver solver, HYPRE\_Real drop\_tol)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetMaxNzPerRow](#) (HYPRE\_Solver solver, HYPRE\_Int max\_nz\_per\_↵  
row)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetEuclidFile](#) (HYPRE\_Solver solver, char \*euclidfile)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetEuLevel](#) (HYPRE\_Solver solver, HYPRE\_Int eu\_level)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetEuSparseA](#) (HYPRE\_Solver solver, HYPRE\_Real eu\_sparse\_A)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetEuBJ](#) (HYPRE\_Solver solver, HYPRE\_Int eu\_bj)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetILUType](#) (HYPRE\_Solver solver, HYPRE\_Int ilu\_type)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetILULevel](#) (HYPRE\_Solver solver, HYPRE\_Int ilu\_lfil)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetILUMaxRowNnz](#) (HYPRE\_Solver solver, HYPRE\_Int ilu\_max\_row\_↵  
nnz)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetILUMaxIter](#) (HYPRE\_Solver solver, HYPRE\_Int ilu\_max\_iter)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetILUDroptol](#) (HYPRE\_Solver solver, HYPRE\_Real ilu\_droptol)



- HYPRE\_Int [HYPRE\\_BoomerAMGSetRestriction](#) (HYPRE\_Solver solver, HYPRE\_Int restr\_par)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetIsTriangular](#) (HYPRE\_Solver solver, HYPRE\_Int is\_triangular)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetGMRESSwitchR](#) (HYPRE\_Solver solver, HYPRE\_Int gmres\_switch)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetADropTol](#) (HYPRE\_Solver solver, HYPRE\_Real A\_drop\_tol)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetADropType](#) (HYPRE\_Solver solver, HYPRE\_Int A\_drop\_type)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetPrintFileName](#) (HYPRE\_Solver solver, const char \*print\_file\_name)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetPrintLevel](#) (HYPRE\_Solver solver, HYPRE\_Int print\_level)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetLogging](#) (HYPRE\_Solver solver, HYPRE\_Int logging)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetDebugFlag](#) (HYPRE\_Solver solver, HYPRE\_Int debug\_flag)
- HYPRE\_Int [HYPRE\\_BoomerAMGInitGridRelaxation](#) (HYPRE\_Int \*\*num\_grid\_sweeps\_ptr, HYPRE\_↵  
Int \*\*grid\_relax\_type\_ptr, HYPRE\_Int \*\*\*grid\_relax\_points\_ptr, HYPRE\_Int coarsen\_type, HYPRE\_Real  
\*\*relax\_weights\_ptr, HYPRE\_Int max\_levels)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetRAP2](#) (HYPRE\_Solver solver, HYPRE\_Int rap2)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetModuleRAP2](#) (HYPRE\_Solver solver, HYPRE\_Int mod\_rap2)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetKeepTranspose](#) (HYPRE\_Solver solver, HYPRE\_Int keepTranspose)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetPlotGrids](#) (HYPRE\_Solver solver, HYPRE\_Int plotgrids)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetPlotFileName](#) (HYPRE\_Solver solver, const char \*plotfilename)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetCoordDim](#) (HYPRE\_Solver solver, HYPRE\_Int coorddim)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetCoordinates](#) (HYPRE\_Solver solver, float \*coordinates)
- HYPRE\_Int [HYPRE\\_BoomerAMGGetGridHierarchy](#) (HYPRE\_Solver solver, HYPRE\_Int \*cgrid)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetCPoints](#) (HYPRE\_Solver solver, HYPRE\_Int cpt\_coarse\_level,  
HYPRE\_Int num\_cpt\_coarse, HYPRE\_BigInt \*cpt\_coarse\_index)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetCPointsToKeep](#) (HYPRE\_Solver solver, HYPRE\_Int cpt\_coarse\_↵  
level, HYPRE\_Int num\_cpt\_coarse, HYPRE\_BigInt \*cpt\_coarse\_index)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetFPoints](#) (HYPRE\_Solver solver, HYPRE\_Int num\_fpt, HYPRE\_Big↵  
Int \*fpt\_index)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetIsolatedFPoints](#) (HYPRE\_Solver solver, HYPRE\_Int num\_isolated\_↵  
\_fpt, HYPRE\_BigInt \*isolated\_fpt\_index)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetSabs](#) (HYPRE\_Solver solver, HYPRE\_Int Sabs)

### ParCSR BoomerAMGDD Solver and Preconditioner

*Communication reducing solver and preconditioner built on top of algebraic multigrid*

- HYPRE\_Int [HYPRE\\_BoomerAMGDDCreate](#) (HYPRE\_Solver \*solver)
- HYPRE\_Int [HYPRE\\_BoomerAMGDDDestroy](#) (HYPRE\_Solver solver)
- HYPRE\_Int [HYPRE\\_BoomerAMGDDSetup](#) (HYPRE\_Solver solver, HYPRE\_ParCSRMatrix A, HYPRE\_↵  
\_ParVector b, HYPRE\_ParVector x)
- HYPRE\_Int [HYPRE\\_BoomerAMGDDSolve](#) (HYPRE\_Solver solver, HYPRE\_ParCSRMatrix A, HYPRE\_↵  
\_ParVector b, HYPRE\_ParVector x)
- HYPRE\_Int [HYPRE\\_BoomerAMGDDSetFACNumRelax](#) (HYPRE\_Solver solver, HYPRE\_Int amgdd\_fac\_↵  
\_num\_relax)
- HYPRE\_Int [HYPRE\\_BoomerAMGDDSetFACNumCycles](#) (HYPRE\_Solver solver, HYPRE\_Int amgdd\_↵  
fac\_num\_cycles)
- HYPRE\_Int [HYPRE\\_BoomerAMGDDSetFACCycleType](#) (HYPRE\_Solver solver, HYPRE\_Int amgdd\_fac\_↵  
\_cycle\_type)
- HYPRE\_Int [HYPRE\\_BoomerAMGDDSetFACRelaxType](#) (HYPRE\_Solver solver, HYPRE\_Int amgdd\_fac\_↵  
\_relax\_type)
- HYPRE\_Int [HYPRE\\_BoomerAMGDDSetFACRelaxWeight](#) (HYPRE\_Solver solver, HYPRE\_Real  
amgdd\_fac\_relax\_weight)
- HYPRE\_Int [HYPRE\\_BoomerAMGDDSetStartLevel](#) (HYPRE\_Solver solver, HYPRE\_Int start\_level)
- HYPRE\_Int [HYPRE\\_BoomerAMGDDSetPadding](#) (HYPRE\_Solver solver, HYPRE\_Int padding)
- HYPRE\_Int [HYPRE\\_BoomerAMGDDSetNumGhostLayers](#) (HYPRE\_Solver solver, HYPRE\_Int num\_↵  
ghost\_layers)
- HYPRE\_Int [HYPRE\\_BoomerAMGDDSetUserFACRelaxation](#) (HYPRE\_Solver solver, HYPRE\_Int(\*user\_↵  
FACRelaxation)(void \*amgdd\_vdata, HYPRE\_Int level, HYPRE\_Int cycle\_param))
- HYPRE\_Int [HYPRE\\_BoomerAMGDDGetAMG](#) (HYPRE\_Solver solver, HYPRE\_Solver \*amg\_solver)
- HYPRE\_Int [HYPRE\\_BoomerAMGDDGetFinalRelativeResidualNorm](#) (HYPRE\_Solver solver, HYPRE\_↵  
Real \*rel\_resid\_norm)
- HYPRE\_Int [HYPRE\\_BoomerAMGDDGetNumIterations](#) (HYPRE\_Solver solver, HYPRE\_Int \*num\_↵  
iterations)

**ParCSR ParaSails Preconditioner**

*Parallel sparse approximate inverse preconditioner for the ParCSR matrix format.*

- HYPRE\_Int [HYPRE\\_ParaSailsCreate](#) (MPI\_Comm comm, [HYPRE\\_Solver](#) \*solver)
- HYPRE\_Int [HYPRE\\_ParaSailsDestroy](#) ([HYPRE\\_Solver](#) solver)
- HYPRE\_Int [HYPRE\\_ParaSailsSetup](#) ([HYPRE\\_Solver](#) solver, HYPRE\_ParCSRMatrix A, HYPRE\_ParVector b, HYPRE\_ParVector x)
- HYPRE\_Int [HYPRE\\_ParaSailsSolve](#) ([HYPRE\\_Solver](#) solver, HYPRE\_ParCSRMatrix A, HYPRE\_ParVector b, HYPRE\_ParVector x)
- HYPRE\_Int [HYPRE\\_ParaSailsSetParams](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Real thresh, HYPRE\_Int nlevels)
- HYPRE\_Int [HYPRE\\_ParaSailsSetFilter](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Real filter)
- HYPRE\_Int [HYPRE\\_ParaSailsSetSym](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int sym)
- HYPRE\_Int [HYPRE\\_ParaSailsSetLoadbal](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Real loadbal)
- HYPRE\_Int [HYPRE\\_ParaSailsSetReuse](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int reuse)
- HYPRE\_Int [HYPRE\\_ParaSailsSetLogging](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int logging)
- HYPRE\_Int [HYPRE\\_ParaSailsBuildIJMatrix](#) ([HYPRE\\_Solver](#) solver, [HYPRE\\_IJMatrix](#) \*pij\_A)
- HYPRE\_Int [HYPRE\\_ParCSRParaSailsCreate](#) (MPI\_Comm comm, [HYPRE\\_Solver](#) \*solver)
- HYPRE\_Int [HYPRE\\_ParCSRParaSailsDestroy](#) ([HYPRE\\_Solver](#) solver)
- HYPRE\_Int [HYPRE\\_ParCSRParaSailsSetup](#) ([HYPRE\\_Solver](#) solver, HYPRE\_ParCSRMatrix A, HYPRE\_ParVector b, HYPRE\_ParVector x)
- HYPRE\_Int [HYPRE\\_ParCSRParaSailsSolve](#) ([HYPRE\\_Solver](#) solver, HYPRE\_ParCSRMatrix A, HYPRE\_ParVector b, HYPRE\_ParVector x)
- HYPRE\_Int [HYPRE\\_ParCSRParaSailsSetParams](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Real thresh, HYPRE\_Int nlevels)
- HYPRE\_Int [HYPRE\\_ParCSRParaSailsSetFilter](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Real filter)
- HYPRE\_Int [HYPRE\\_ParCSRParaSailsSetSym](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int sym)
- HYPRE\_Int [HYPRE\\_ParCSRParaSailsSetLoadbal](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Real loadbal)
- HYPRE\_Int [HYPRE\\_ParCSRParaSailsSetReuse](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int reuse)
- HYPRE\_Int [HYPRE\\_ParCSRParaSailsSetLogging](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int logging)

**ParCSR Euclid Preconditioner**

*MPI Parallel ILU preconditioner*

*Options summary:*

Option	Default	Synopsis
-level	1	ILU(k) factorization level
-bj	0 (false)	Use Block Jacobi ILU instead of PILU
-eu_stats	0 (false)	Print internal timing and statistics
-eu_mem	0 (false)	Print internal memory usage

- HYPRE\_Int [HYPRE\\_EuclidCreate](#) (MPI\_Comm comm, [HYPRE\\_Solver](#) \*solver)
- HYPRE\_Int [HYPRE\\_EuclidDestroy](#) ([HYPRE\\_Solver](#) solver)
- HYPRE\_Int [HYPRE\\_EuclidSetup](#) ([HYPRE\\_Solver](#) solver, HYPRE\_ParCSRMatrix A, HYPRE\_ParVector b, HYPRE\_ParVector x)
- HYPRE\_Int [HYPRE\\_EuclidSolve](#) ([HYPRE\\_Solver](#) solver, HYPRE\_ParCSRMatrix A, HYPRE\_ParVector b, HYPRE\_ParVector x)
- HYPRE\_Int [HYPRE\\_EuclidSetParams](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int argc, char \*argv[])
- HYPRE\_Int [HYPRE\\_EuclidSetParamsFromFile](#) ([HYPRE\\_Solver](#) solver, char \*filename)
- HYPRE\_Int [HYPRE\\_EuclidSetLevel](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int level)
- HYPRE\_Int [HYPRE\\_EuclidSetBJ](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int bj)
- HYPRE\_Int [HYPRE\\_EuclidSetStats](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int eu\_stats)
- HYPRE\_Int [HYPRE\\_EuclidSetMem](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int eu\_mem)
- HYPRE\_Int [HYPRE\\_EuclidSetSparseA](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Real sparse\_A)
- HYPRE\_Int [HYPRE\\_EuclidSetRowScale](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int row\_scale)
- HYPRE\_Int [HYPRE\\_EuclidSetILUT](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Real drop\_tol)

**ParCSR Pilut Preconditioner**

- HYPRE\_Int [HYPRE\\_ParCSRPIlutCreate](#) (MPI\_Comm comm, [HYPRE\\_Solver](#) \*solver)
- HYPRE\_Int [HYPRE\\_ParCSRPIlutDestroy](#) ([HYPRE\\_Solver](#) solver)
- HYPRE\_Int [HYPRE\\_ParCSRPIlutSetup](#) ([HYPRE\\_Solver](#) solver, HYPRE\_ParCSRMatrix A, HYPRE\_ParVector b, HYPRE\_ParVector x)
- HYPRE\_Int [HYPRE\\_ParCSRPIlutSolve](#) ([HYPRE\\_Solver](#) solver, HYPRE\_ParCSRMatrix A, HYPRE\_ParVector b, HYPRE\_ParVector x)
- HYPRE\_Int [HYPRE\\_ParCSRPIlutSetMaxIter](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int max\_iter)
- HYPRE\_Int [HYPRE\\_ParCSRPIlutSetDropTolerance](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_ParCSRPIlutSetFactorRowSize](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int size)
- HYPRE\_Int [HYPRE\\_ParCSRPIlutSetLogging](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int logging)

### ParCSR AMS Solver and Preconditioner

*Parallel auxiliary space Maxwell solver and preconditioner*

- HYPRE\_Int [HYPRE\\_AMSCreate](#) ([HYPRE\\_Solver](#) \*solver)
- HYPRE\_Int [HYPRE\\_AMSDestroy](#) ([HYPRE\\_Solver](#) solver)
- HYPRE\_Int [HYPRE\\_AMSSetup](#) ([HYPRE\\_Solver](#) solver, HYPRE\_ParCSRMatrix A, HYPRE\_ParVector b, HYPRE\_ParVector x)
- HYPRE\_Int [HYPRE\\_AMSolve](#) ([HYPRE\\_Solver](#) solver, HYPRE\_ParCSRMatrix A, HYPRE\_ParVector b, HYPRE\_ParVector x)
- HYPRE\_Int [HYPRE\\_AMSSetDimension](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int dim)
- HYPRE\_Int [HYPRE\\_AMSSetDiscreteGradient](#) ([HYPRE\\_Solver](#) solver, HYPRE\_ParCSRMatrix G)
- HYPRE\_Int [HYPRE\\_AMSSetCoordinateVectors](#) ([HYPRE\\_Solver](#) solver, HYPRE\_ParVector x, HYPRE\_ParVector y, HYPRE\_ParVector z)
- HYPRE\_Int [HYPRE\\_AMSSetEdgeConstantVectors](#) ([HYPRE\\_Solver](#) solver, HYPRE\_ParVector Gx, HYPRE\_ParVector Gy, HYPRE\_ParVector Gz)
- HYPRE\_Int [HYPRE\\_AMSSetInterpolations](#) ([HYPRE\\_Solver](#) solver, HYPRE\_ParCSRMatrix Pi, HYPRE\_ParCSRMatrix Pix, HYPRE\_ParCSRMatrix Piy, HYPRE\_ParCSRMatrix Piz)
- HYPRE\_Int [HYPRE\\_AMSSetAlphaPoissonMatrix](#) ([HYPRE\\_Solver](#) solver, HYPRE\_ParCSRMatrix A, HYPRE\_Int alpha)
- HYPRE\_Int [HYPRE\\_AMSSetBetaPoissonMatrix](#) ([HYPRE\\_Solver](#) solver, HYPRE\_ParCSRMatrix A, HYPRE\_Int beta)
- HYPRE\_Int [HYPRE\\_AMSSetInteriorNodes](#) ([HYPRE\\_Solver](#) solver, HYPRE\_ParVector interior\_nodes)
- HYPRE\_Int [HYPRE\\_AMSSetProjectionFrequency](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int projection\_frequency)
- HYPRE\_Int [HYPRE\\_AMSSetMaxIter](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int maxit)
- HYPRE\_Int [HYPRE\\_AMSSetTol](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_AMSSetCycleType](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int cycle\_type)
- HYPRE\_Int [HYPRE\\_AMSSetPrintLevel](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int print\_level)
- HYPRE\_Int [HYPRE\\_AMSSetSmoothingOptions](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int relax\_type, HYPRE\_Int relax\_times, HYPRE\_Real relax\_weight, HYPRE\_Real omega)
- HYPRE\_Int [HYPRE\\_AMSSetAlphaAMGOptions](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int alpha\_coarsen\_type, HYPRE\_Int alpha\_agg\_levels, HYPRE\_Int alpha\_relax\_type, HYPRE\_Real alpha\_strength\_threshold, HYPRE\_Int alpha\_interp\_type, HYPRE\_Int alpha\_Pmax)
- HYPRE\_Int [HYPRE\\_AMSSetAlphaAMGCoarseRelaxType](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int alpha\_coarse\_relax\_type)
- HYPRE\_Int [HYPRE\\_AMSSetBetaAMGOptions](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int beta\_coarsen\_type, HYPRE\_Int beta\_agg\_levels, HYPRE\_Int beta\_relax\_type, HYPRE\_Real beta\_strength\_threshold, HYPRE\_Int beta\_interp\_type, HYPRE\_Int beta\_Pmax)
- HYPRE\_Int [HYPRE\\_AMSSetBetaAMGCoarseRelaxType](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int beta\_coarse\_relax\_type)
- HYPRE\_Int [HYPRE\\_AMSGetNumIterations](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int \*num\_iterations)
- HYPRE\_Int [HYPRE\\_AMSGetFinalRelativeResidualNorm](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Real \*rel\_resid\_norm)
- HYPRE\_Int [HYPRE\\_AMSProjectOutGradients](#) ([HYPRE\\_Solver](#) solver, HYPRE\_ParVector x)
- HYPRE\_Int [HYPRE\\_AMSConstructDiscreteGradient](#) (HYPRE\_ParCSRMatrix A, HYPRE\_ParVector x, HYPRE\_BigInt \*edge\_vertex, HYPRE\_Int edge\_orientation, HYPRE\_ParCSRMatrix \*G)

### ParCSR ADS Solver and Preconditioner

*Parallel auxiliary space divergence solver and preconditioner*



- HYPRE\_Int [HYPRE\\_ADSCreate](#) (HYPRE\_Solver \*solver)
- HYPRE\_Int [HYPRE\\_ADSDestroy](#) (HYPRE\_Solver solver)
- HYPRE\_Int [HYPRE\\_ADSSetup](#) (HYPRE\_Solver solver, HYPRE\_ParCSRMatrix A, HYPRE\_ParVector b, HYPRE\_ParVector x)
- HYPRE\_Int [HYPRE\\_ADSSolve](#) (HYPRE\_Solver solver, HYPRE\_ParCSRMatrix A, HYPRE\_ParVector b, HYPRE\_ParVector x)
- HYPRE\_Int [HYPRE\\_ADSSetDiscreteCurl](#) (HYPRE\_Solver solver, HYPRE\_ParCSRMatrix C)
- HYPRE\_Int [HYPRE\\_ADSSetDiscreteGradient](#) (HYPRE\_Solver solver, HYPRE\_ParCSRMatrix G)
- HYPRE\_Int [HYPRE\\_ADSSetCoordinateVectors](#) (HYPRE\_Solver solver, HYPRE\_ParVector x, HYPRE\_ParVector y, HYPRE\_ParVector z)
- HYPRE\_Int [HYPRE\\_ADSSetInterpolations](#) (HYPRE\_Solver solver, HYPRE\_ParCSRMatrix RT\_Pi, HYPRE\_ParCSRMatrix RT\_Pix, HYPRE\_ParCSRMatrix RT\_Piy, HYPRE\_ParCSRMatrix RT\_Piz, HYPRE\_ParCSRMatrix ND\_Pi, HYPRE\_ParCSRMatrix ND\_Pix, HYPRE\_ParCSRMatrix ND\_Piy, HYPRE\_ParCSRMatrix ND\_Piz)
- HYPRE\_Int [HYPRE\\_ADSSetMaxIter](#) (HYPRE\_Solver solver, HYPRE\_Int maxit)
- HYPRE\_Int [HYPRE\\_ADSSetTol](#) (HYPRE\_Solver solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_ADSSetCycleType](#) (HYPRE\_Solver solver, HYPRE\_Int cycle\_type)
- HYPRE\_Int [HYPRE\\_ADSSetPrintLevel](#) (HYPRE\_Solver solver, HYPRE\_Int print\_level)
- HYPRE\_Int [HYPRE\\_ADSSetSmoothingOptions](#) (HYPRE\_Solver solver, HYPRE\_Int relax\_type, HYPRE\_Int relax\_times, HYPRE\_Real relax\_weight, HYPRE\_Real omega)
- HYPRE\_Int [HYPRE\\_ADSSetChebySmoothingOptions](#) (HYPRE\_Solver solver, HYPRE\_Int cheby\_order, HYPRE\_Int cheby\_fraction)
- HYPRE\_Int [HYPRE\\_ADSSetAMSOOptions](#) (HYPRE\_Solver solver, HYPRE\_Int cycle\_type, HYPRE\_Int coarsen\_type, HYPRE\_Int agg\_levels, HYPRE\_Int relax\_type, HYPRE\_Real strength\_threshold, HYPRE\_Int interp\_type, HYPRE\_Int Pmax)
- HYPRE\_Int [HYPRE\\_ADSSetAMGOptions](#) (HYPRE\_Solver solver, HYPRE\_Int coarsen\_type, HYPRE\_Int agg\_levels, HYPRE\_Int relax\_type, HYPRE\_Real strength\_threshold, HYPRE\_Int interp\_type, HYPRE\_Int Pmax)
- HYPRE\_Int [HYPRE\\_ADSSetNumIterations](#) (HYPRE\_Solver solver, HYPRE\_Int \*num\_iterations)
- HYPRE\_Int [HYPRE\\_ADSSetFinalRelativeResidualNorm](#) (HYPRE\_Solver solver, HYPRE\_Real \*rel\_resid\_norm)

### ParCSR PCG Solver

These routines should be used in conjunction with the generic interface in [Krylov Solvers](#).

- HYPRE\_Int [HYPRE\\_ParCSRPCGCreate](#) (MPI\_Comm comm, HYPRE\_Solver \*solver)
- HYPRE\_Int [HYPRE\\_ParCSRPCGDestroy](#) (HYPRE\_Solver solver)
- HYPRE\_Int [HYPRE\\_ParCSRPCGSetup](#) (HYPRE\_Solver solver, HYPRE\_ParCSRMatrix A, HYPRE\_ParVector b, HYPRE\_ParVector x)
- HYPRE\_Int [HYPRE\\_ParCSRPCGSolve](#) (HYPRE\_Solver solver, HYPRE\_ParCSRMatrix A, HYPRE\_ParVector b, HYPRE\_ParVector x)
- HYPRE\_Int [HYPRE\\_ParCSRPCGSetTol](#) (HYPRE\_Solver solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_ParCSRPCGSetAbsoluteTol](#) (HYPRE\_Solver solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_ParCSRPCGSetMaxIter](#) (HYPRE\_Solver solver, HYPRE\_Int max\_iter)
- HYPRE\_Int [HYPRE\\_ParCSRPCGSetStopCrit](#) (HYPRE\_Solver solver, HYPRE\_Int stop\_crit)
- HYPRE\_Int [HYPRE\\_ParCSRPCGSetTwoNorm](#) (HYPRE\_Solver solver, HYPRE\_Int two\_norm)
- HYPRE\_Int [HYPRE\\_ParCSRPCGSetRelChange](#) (HYPRE\_Solver solver, HYPRE\_Int rel\_change)
- HYPRE\_Int [HYPRE\\_ParCSRPCGSetPrecond](#) (HYPRE\_Solver solver, HYPRE\_PtrToParSolverFcn precond, HYPRE\_PtrToParSolverFcn precond\_setup, HYPRE\_Solver precond\_solver)
- HYPRE\_Int [HYPRE\\_ParCSRPCGGetPrecond](#) (HYPRE\_Solver solver, HYPRE\_Solver \*precond\_data)
- HYPRE\_Int [HYPRE\\_ParCSRPCGSetLogging](#) (HYPRE\_Solver solver, HYPRE\_Int logging)
- HYPRE\_Int [HYPRE\\_ParCSRPCGSetPrintLevel](#) (HYPRE\_Solver solver, HYPRE\_Int print\_level)
- HYPRE\_Int [HYPRE\\_ParCSRPCGGetNumIterations](#) (HYPRE\_Solver solver, HYPRE\_Int \*num\_iterations)
- HYPRE\_Int [HYPRE\\_ParCSRPCGGetFinalRelativeResidualNorm](#) (HYPRE\_Solver solver, HYPRE\_Real \*norm)
- HYPRE\_Int [HYPRE\\_ParCSRPCGGetResidual](#) (HYPRE\_Solver solver, HYPRE\_ParVector \*residual)
- HYPRE\_Int [HYPRE\\_ParCSRDiagScaleSetup](#) (HYPRE\_Solver solver, HYPRE\_ParCSRMatrix A, HYPRE\_ParVector y, HYPRE\_ParVector x)
- HYPRE\_Int [HYPRE\\_ParCSRDiagScale](#) (HYPRE\_Solver solver, HYPRE\_ParCSRMatrix HA, HYPRE\_ParVector Hy, HYPRE\_ParVector Hx)

- HYPRE\_Int [HYPRE\\_ParCSROnProcTriSetup](#) (HYPRE\_Solver solver, HYPRE\_ParCSRMatrix HA, HYPRE\_ParVector Hy, HYPRE\_ParVector Hx)
- HYPRE\_Int [HYPRE\\_ParCSROnProcTriSolve](#) (HYPRE\_Solver solver, HYPRE\_ParCSRMatrix HA, HYPRE\_ParVector Hy, HYPRE\_ParVector Hx)

### ParCSR GMRES Solver

These routines should be used in conjunction with the generic interface in [Krylov Solvers](#).

- HYPRE\_Int [HYPRE\\_ParCSRGMRESCreate](#) (MPI\_Comm comm, HYPRE\_Solver \*solver)
- HYPRE\_Int [HYPRE\\_ParCSRGMRESDestroy](#) (HYPRE\_Solver solver)
- HYPRE\_Int [HYPRE\\_ParCSRGMRESSetup](#) (HYPRE\_Solver solver, HYPRE\_ParCSRMatrix A, HYPRE\_ParVector b, HYPRE\_ParVector x)
- HYPRE\_Int [HYPRE\\_ParCSRGMRESSolve](#) (HYPRE\_Solver solver, HYPRE\_ParCSRMatrix A, HYPRE\_ParVector b, HYPRE\_ParVector x)
- HYPRE\_Int [HYPRE\\_ParCSRGMRESSetKDim](#) (HYPRE\_Solver solver, HYPRE\_Int k\_dim)
- HYPRE\_Int [HYPRE\\_ParCSRGMRESSetTol](#) (HYPRE\_Solver solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_ParCSRGMRESSetAbsoluteTol](#) (HYPRE\_Solver solver, HYPRE\_Real a\_tol)
- HYPRE\_Int [HYPRE\\_ParCSRGMRESSetMinIter](#) (HYPRE\_Solver solver, HYPRE\_Int min\_iter)
- HYPRE\_Int [HYPRE\\_ParCSRGMRESSetMaxIter](#) (HYPRE\_Solver solver, HYPRE\_Int max\_iter)
- HYPRE\_Int [HYPRE\\_ParCSRGMRESSetStopCrit](#) (HYPRE\_Solver solver, HYPRE\_Int stop\_crit)
- HYPRE\_Int [HYPRE\\_ParCSRGMRESSetPrecond](#) (HYPRE\_Solver solver, HYPRE\_PtrToParSolverFcn precondition, HYPRE\_PtrToParSolverFcn precondition\_setup, HYPRE\_Solver precondition\_solver)
- HYPRE\_Int [HYPRE\\_ParCSRGMRESGetPrecond](#) (HYPRE\_Solver solver, HYPRE\_Solver \*precond\_data)
- HYPRE\_Int [HYPRE\\_ParCSRGMRESSetLogging](#) (HYPRE\_Solver solver, HYPRE\_Int logging)
- HYPRE\_Int [HYPRE\\_ParCSRGMRESSetPrintLevel](#) (HYPRE\_Solver solver, HYPRE\_Int print\_level)
- HYPRE\_Int [HYPRE\\_ParCSRGMRESGetNumIterations](#) (HYPRE\_Solver solver, HYPRE\_Int \*num\_iterations)
- HYPRE\_Int [HYPRE\\_ParCSRGMRESGetFinalRelativeResidualNorm](#) (HYPRE\_Solver solver, HYPRE\_Real \*norm)
- HYPRE\_Int [HYPRE\\_ParCSRGMRESGetResidual](#) (HYPRE\_Solver solver, HYPRE\_ParVector \*residual)
- HYPRE\_Int [HYPRE\\_ParCSRCOGMRESCreate](#) (MPI\_Comm comm, HYPRE\_Solver \*solver)
- HYPRE\_Int [HYPRE\\_ParCSRCOGMRESDestroy](#) (HYPRE\_Solver solver)
- HYPRE\_Int [HYPRE\\_ParCSRCOGMRESSetup](#) (HYPRE\_Solver solver, HYPRE\_ParCSRMatrix A, HYPRE\_ParVector b, HYPRE\_ParVector x)
- HYPRE\_Int [HYPRE\\_ParCSRCOGMRESSolve](#) (HYPRE\_Solver solver, HYPRE\_ParCSRMatrix A, HYPRE\_ParVector b, HYPRE\_ParVector x)
- HYPRE\_Int [HYPRE\\_ParCSRCOGMRESSetKDim](#) (HYPRE\_Solver solver, HYPRE\_Int k\_dim)
- HYPRE\_Int [HYPRE\\_ParCSRCOGMRESSetUnroll](#) (HYPRE\_Solver solver, HYPRE\_Int unroll)
- HYPRE\_Int [HYPRE\\_ParCSRCOGMRESSetCGS](#) (HYPRE\_Solver solver, HYPRE\_Int cgs)
- HYPRE\_Int [HYPRE\\_ParCSRCOGMRESSetTol](#) (HYPRE\_Solver solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_ParCSRCOGMRESSetAbsoluteTol](#) (HYPRE\_Solver solver, HYPRE\_Real a\_tol)
- HYPRE\_Int [HYPRE\\_ParCSRCOGMRESSetMinIter](#) (HYPRE\_Solver solver, HYPRE\_Int min\_iter)
- HYPRE\_Int [HYPRE\\_ParCSRCOGMRESSetMaxIter](#) (HYPRE\_Solver solver, HYPRE\_Int max\_iter)
- HYPRE\_Int [HYPRE\\_ParCSRCOGMRESSetPrecond](#) (HYPRE\_Solver solver, HYPRE\_PtrToParSolverFcn precondition, HYPRE\_PtrToParSolverFcn precondition\_setup, HYPRE\_Solver precondition\_solver)
- HYPRE\_Int [HYPRE\\_ParCSRCOGMRESGetPrecond](#) (HYPRE\_Solver solver, HYPRE\_Solver \*precond\_data)
- HYPRE\_Int [HYPRE\\_ParCSRCOGMRESSetLogging](#) (HYPRE\_Solver solver, HYPRE\_Int logging)
- HYPRE\_Int [HYPRE\\_ParCSRCOGMRESSetPrintLevel](#) (HYPRE\_Solver solver, HYPRE\_Int print\_level)
- HYPRE\_Int [HYPRE\\_ParCSRCOGMRESGetNumIterations](#) (HYPRE\_Solver solver, HYPRE\_Int \*num\_iterations)
- HYPRE\_Int [HYPRE\\_ParCSRCOGMRESGetFinalRelativeResidualNorm](#) (HYPRE\_Solver solver, HYPRE\_Real \*norm)
- HYPRE\_Int [HYPRE\\_ParCSRCOGMRESGetResidual](#) (HYPRE\_Solver solver, HYPRE\_ParVector \*residual)

### ParCSR FlexGMRES Solver

These routines should be used in conjunction with the generic interface in [Krylov Solvers](#).

- HYPRE\_Int [HYPRE\\_ParCSRFlexGMRESCreate](#) (MPI\_Comm comm, [HYPRE\\_Solver](#) \*solver)
- HYPRE\_Int [HYPRE\\_ParCSRFlexGMRESDestroy](#) ([HYPRE\\_Solver](#) solver)
- HYPRE\_Int [HYPRE\\_ParCSRFlexGMRESSetup](#) ([HYPRE\\_Solver](#) solver, HYPRE\_ParCSRMatrix A, HYPRE\_ParVector b, HYPRE\_ParVector x)
- HYPRE\_Int [HYPRE\\_ParCSRFlexGMRESSolve](#) ([HYPRE\\_Solver](#) solver, HYPRE\_ParCSRMatrix A, HYPRE\_ParVector b, HYPRE\_ParVector x)
- HYPRE\_Int [HYPRE\\_ParCSRFlexGMRESSetKDim](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int k\_dim)
- HYPRE\_Int [HYPRE\\_ParCSRFlexGMRESSetTol](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_ParCSRFlexGMRESSetAbsoluteTol](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Real a\_tol)
- HYPRE\_Int [HYPRE\\_ParCSRFlexGMRESSetMinIter](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int min\_iter)
- HYPRE\_Int [HYPRE\\_ParCSRFlexGMRESSetMaxIter](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int max\_iter)
- HYPRE\_Int [HYPRE\\_ParCSRFlexGMRESSetPrecond](#) ([HYPRE\\_Solver](#) solver, [HYPRE\\_PtrToParSolverFcn](#) precondition, [HYPRE\\_PtrToParSolverFcn](#) precondition\_setup, [HYPRE\\_Solver](#) precondition\_solver)
- HYPRE\_Int [HYPRE\\_ParCSRFlexGMRESGetPrecond](#) ([HYPRE\\_Solver](#) solver, [HYPRE\\_Solver](#) \*precond\_data)
- HYPRE\_Int [HYPRE\\_ParCSRFlexGMRESSetLogging](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int logging)
- HYPRE\_Int [HYPRE\\_ParCSRFlexGMRESSetPrintLevel](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int print\_level)
- HYPRE\_Int [HYPRE\\_ParCSRFlexGMRESGetNumIterations](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int \*num\_ iterations)
- HYPRE\_Int [HYPRE\\_ParCSRFlexGMRESGetFinalRelativeResidualNorm](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Real \*norm)
- HYPRE\_Int [HYPRE\\_ParCSRFlexGMRESGetResidual](#) ([HYPRE\\_Solver](#) solver, HYPRE\_ParVector \*residual)
- HYPRE\_Int [HYPRE\\_ParCSRFlexGMRESSetModifyPC](#) ([HYPRE\\_Solver](#) solver, [HYPRE\\_PtrToModifyPCFcn](#) modify\_pc)

### ParCSR LGMRES Solver

These routines should be used in conjunction with the generic interface in [Krylov Solvers](#).

- HYPRE\_Int [HYPRE\\_ParCSRLGMRESCreate](#) (MPI\_Comm comm, [HYPRE\\_Solver](#) \*solver)
- HYPRE\_Int [HYPRE\\_ParCSRLGMRESDestroy](#) ([HYPRE\\_Solver](#) solver)
- HYPRE\_Int [HYPRE\\_ParCSRLGMRESSetup](#) ([HYPRE\\_Solver](#) solver, HYPRE\_ParCSRMatrix A, HYPRE\_ParVector b, HYPRE\_ParVector x)
- HYPRE\_Int [HYPRE\\_ParCSRLGMRESSolve](#) ([HYPRE\\_Solver](#) solver, HYPRE\_ParCSRMatrix A, HYPRE\_ ParVector b, HYPRE\_ParVector x)
- HYPRE\_Int [HYPRE\\_ParCSRLGMRESSetKDim](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int k\_dim)
- HYPRE\_Int [HYPRE\\_ParCSRLGMRESSetAugDim](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int aug\_dim)
- HYPRE\_Int [HYPRE\\_ParCSRLGMRESSetTol](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_ParCSRLGMRESSetAbsoluteTol](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Real a\_tol)
- HYPRE\_Int [HYPRE\\_ParCSRLGMRESSetMinIter](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int min\_iter)
- HYPRE\_Int [HYPRE\\_ParCSRLGMRESSetMaxIter](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int max\_iter)
- HYPRE\_Int [HYPRE\\_ParCSRLGMRESSetPrecond](#) ([HYPRE\\_Solver](#) solver, [HYPRE\\_PtrToParSolverFcn](#) precondition, [HYPRE\\_PtrToParSolverFcn](#) precondition\_setup, [HYPRE\\_Solver](#) precondition\_solver)
- HYPRE\_Int [HYPRE\\_ParCSRLGMRESGetPrecond](#) ([HYPRE\\_Solver](#) solver, [HYPRE\\_Solver](#) \*precond\_data)
- HYPRE\_Int [HYPRE\\_ParCSRLGMRESSetLogging](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int logging)
- HYPRE\_Int [HYPRE\\_ParCSRLGMRESSetPrintLevel](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int print\_level)
- HYPRE\_Int [HYPRE\\_ParCSRLGMRESGetNumIterations](#) ([HYPRE\\_Solver](#) solver, HYPRE\_Int \*num\_ iterations)
- HYPRE\_Int [HYPRE\\_ParCSRLGMRESGetFinalRelativeResidualNorm](#) ([HYPRE\\_Solver](#) solver, HYPRE\_ Real \*norm)
- HYPRE\_Int [HYPRE\\_ParCSRLGMRESGetResidual](#) ([HYPRE\\_Solver](#) solver, HYPRE\_ParVector \*residual)

### ParCSR BiCGSTAB Solver

These routines should be used in conjunction with the generic interface in [Krylov Solvers](#).

- HYPRE\_Int [HYPRE\\_ParCSRBICGSTABCreate](#) (MPI\_Comm comm, [HYPRE\\_Solver](#) \*solver)
- HYPRE\_Int [HYPRE\\_ParCSRBICGSTABDestroy](#) ([HYPRE\\_Solver](#) solver)
- HYPRE\_Int [HYPRE\\_ParCSRBICGSTABSetup](#) ([HYPRE\\_Solver](#) solver, HYPRE\_ParCSRMatrix A, HYPRE\_ParVector b, HYPRE\_ParVector x)

- HYPRE\_Int [HYPRE\\_ParCSRBiCGSTABsolve](#) (HYPRE\_Solver solver, HYPRE\_ParCSRMatrix A, HYPRE\_ParVector b, HYPRE\_ParVector x)
- HYPRE\_Int [HYPRE\\_ParCSRBiCGSTABSetTol](#) (HYPRE\_Solver solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_ParCSRBiCGSTABSetAbsoluteTol](#) (HYPRE\_Solver solver, HYPRE\_Real a\_tol)
- HYPRE\_Int [HYPRE\\_ParCSRBiCGSTABSetMinIter](#) (HYPRE\_Solver solver, HYPRE\_Int min\_iter)
- HYPRE\_Int [HYPRE\\_ParCSRBiCGSTABSetMaxIter](#) (HYPRE\_Solver solver, HYPRE\_Int max\_iter)
- HYPRE\_Int [HYPRE\\_ParCSRBiCGSTABSetStopCrit](#) (HYPRE\_Solver solver, HYPRE\_Int stop\_crit)
- HYPRE\_Int [HYPRE\\_ParCSRBiCGSTABSetPrecond](#) (HYPRE\_Solver solver, HYPRE\_PtrToParSolverFcn precondition, HYPRE\_PtrToParSolverFcn precondition\_setup, HYPRE\_Solver precondition\_solver)
- HYPRE\_Int [HYPRE\\_ParCSRBiCGSTABGetPrecond](#) (HYPRE\_Solver solver, HYPRE\_Solver \*precondition\_data)
- HYPRE\_Int [HYPRE\\_ParCSRBiCGSTABSetLogging](#) (HYPRE\_Solver solver, HYPRE\_Int logging)
- HYPRE\_Int [HYPRE\\_ParCSRBiCGSTABSetPrintLevel](#) (HYPRE\_Solver solver, HYPRE\_Int print\_level)
- HYPRE\_Int [HYPRE\\_ParCSRBiCGSTABGetNumIterations](#) (HYPRE\_Solver solver, HYPRE\_Int \*num\_iterations)
- HYPRE\_Int [HYPRE\\_ParCSRBiCGSTABGetFinalRelativeResidualNorm](#) (HYPRE\_Solver solver, HYPRE\_Real \*norm)
- HYPRE\_Int [HYPRE\\_ParCSRBiCGSTABGetResidual](#) (HYPRE\_Solver solver, HYPRE\_ParVector \*residual)

### ParCSR Hybrid Solver

- HYPRE\_Int [HYPRE\\_ParCSRHybridCreate](#) (HYPRE\_Solver \*solver)
- HYPRE\_Int [HYPRE\\_ParCSRHybridDestroy](#) (HYPRE\_Solver solver)
- HYPRE\_Int [HYPRE\\_ParCSRHybridSetup](#) (HYPRE\_Solver solver, HYPRE\_ParCSRMatrix A, HYPRE\_ParVector b, HYPRE\_ParVector x)
- HYPRE\_Int [HYPRE\\_ParCSRHybridSolve](#) (HYPRE\_Solver solver, HYPRE\_ParCSRMatrix A, HYPRE\_ParVector b, HYPRE\_ParVector x)
- HYPRE\_Int [HYPRE\\_ParCSRHybridSetTol](#) (HYPRE\_Solver solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_ParCSRHybridSetAbsoluteTol](#) (HYPRE\_Solver solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_ParCSRHybridSetConvergenceTol](#) (HYPRE\_Solver solver, HYPRE\_Real cf\_tol)
- HYPRE\_Int [HYPRE\\_ParCSRHybridSetDSCGMaxIter](#) (HYPRE\_Solver solver, HYPRE\_Int dscg\_max\_its)
- HYPRE\_Int [HYPRE\\_ParCSRHybridSetPCGMaxIter](#) (HYPRE\_Solver solver, HYPRE\_Int pcg\_max\_its)
- HYPRE\_Int [HYPRE\\_ParCSRHybridSetSetupType](#) (HYPRE\_Solver solver, HYPRE\_Int setup\_type)
- HYPRE\_Int [HYPRE\\_ParCSRHybridSetSolverType](#) (HYPRE\_Solver solver, HYPRE\_Int solver\_type)
- HYPRE\_Int [HYPRE\\_ParCSRHybridSetRecomputeResidual](#) (HYPRE\_Solver solver, HYPRE\_Int recompute\_residual)
- HYPRE\_Int [HYPRE\\_ParCSRHybridGetRecomputeResidual](#) (HYPRE\_Solver solver, HYPRE\_Int \*recompute\_residual)
- HYPRE\_Int [HYPRE\\_ParCSRHybridSetRecomputeResidualP](#) (HYPRE\_Solver solver, HYPRE\_Int recompute\_residual\_p)
- HYPRE\_Int [HYPRE\\_ParCSRHybridGetRecomputeResidualP](#) (HYPRE\_Solver solver, HYPRE\_Int \*recompute\_residual\_p)
- HYPRE\_Int [HYPRE\\_ParCSRHybridSetKDim](#) (HYPRE\_Solver solver, HYPRE\_Int k\_dim)
- HYPRE\_Int [HYPRE\\_ParCSRHybridSetTwoNorm](#) (HYPRE\_Solver solver, HYPRE\_Int two\_norm)
- HYPRE\_Int [HYPRE\\_ParCSRHybridSetStopCrit](#) (HYPRE\_Solver solver, HYPRE\_Int stop\_crit)
- HYPRE\_Int [HYPRE\\_ParCSRHybridSetRelChange](#) (HYPRE\_Solver solver, HYPRE\_Int rel\_change)
- HYPRE\_Int [HYPRE\\_ParCSRHybridSetPrecond](#) (HYPRE\_Solver solver, HYPRE\_PtrToParSolverFcn precondition, HYPRE\_PtrToParSolverFcn precondition\_setup, HYPRE\_Solver precondition\_solver)
- HYPRE\_Int [HYPRE\\_ParCSRHybridSetLogging](#) (HYPRE\_Solver solver, HYPRE\_Int logging)
- HYPRE\_Int [HYPRE\\_ParCSRHybridSetPrintLevel](#) (HYPRE\_Solver solver, HYPRE\_Int print\_level)
- HYPRE\_Int [HYPRE\\_ParCSRHybridSetStrongThreshold](#) (HYPRE\_Solver solver, HYPRE\_Real strong\_threshold)
- HYPRE\_Int [HYPRE\\_ParCSRHybridSetMaxRowSum](#) (HYPRE\_Solver solver, HYPRE\_Real max\_row\_sum)
- HYPRE\_Int [HYPRE\\_ParCSRHybridSetTruncFactor](#) (HYPRE\_Solver solver, HYPRE\_Real trunc\_factor)
- HYPRE\_Int [HYPRE\\_ParCSRHybridSetPMaxElmts](#) (HYPRE\_Solver solver, HYPRE\_Int P\_max\_elmts)
- HYPRE\_Int [HYPRE\\_ParCSRHybridSetMaxLevels](#) (HYPRE\_Solver solver, HYPRE\_Int max\_levels)
- HYPRE\_Int [HYPRE\\_ParCSRHybridSetMeasureType](#) (HYPRE\_Solver solver, HYPRE\_Int measure\_type)
- HYPRE\_Int [HYPRE\\_ParCSRHybridSetCoarsenType](#) (HYPRE\_Solver solver, HYPRE\_Int coarsen\_type)
- HYPRE\_Int [HYPRE\\_ParCSRHybridSetInterpType](#) (HYPRE\_Solver solver, HYPRE\_Int interp\_type)
- HYPRE\_Int [HYPRE\\_ParCSRHybridSetCycleType](#) (HYPRE\_Solver solver, HYPRE\_Int cycle\_type)

- HYPRE\_Int [HYPRE\\_ParCSRHybridSetGridRelaxType](#) (HYPRE\_Solver solver, HYPRE\_Int \*grid\_relax\_↵\_type)
- HYPRE\_Int [HYPRE\\_ParCSRHybridSetGridRelaxPoints](#) (HYPRE\_Solver solver, HYPRE\_Int \*\*grid\_↵relax\_points)
- HYPRE\_Int [HYPRE\\_ParCSRHybridSetNumSweeps](#) (HYPRE\_Solver solver, HYPRE\_Int num\_sweeps)
- HYPRE\_Int [HYPRE\\_ParCSRHybridSetCycleNumSweeps](#) (HYPRE\_Solver solver, HYPRE\_Int num\_↵sweeps, HYPRE\_Int k)
- HYPRE\_Int [HYPRE\\_ParCSRHybridSetRelaxType](#) (HYPRE\_Solver solver, HYPRE\_Int relax\_type)
- HYPRE\_Int [HYPRE\\_ParCSRHybridSetCycleRelaxType](#) (HYPRE\_Solver solver, HYPRE\_Int relax\_type, HYPRE\_Int k)
- HYPRE\_Int [HYPRE\\_ParCSRHybridSetRelaxOrder](#) (HYPRE\_Solver solver, HYPRE\_Int relax\_order)
- HYPRE\_Int [HYPRE\\_ParCSRHybridSetRelaxWt](#) (HYPRE\_Solver solver, HYPRE\_Real relax\_wt)
- HYPRE\_Int [HYPRE\\_ParCSRHybridSetLevelRelaxWt](#) (HYPRE\_Solver solver, HYPRE\_Real relax\_wt, HYPRE\_Int level)
- HYPRE\_Int [HYPRE\\_ParCSRHybridSetOuterWt](#) (HYPRE\_Solver solver, HYPRE\_Real outer\_wt)
- HYPRE\_Int [HYPRE\\_ParCSRHybridSetLevelOuterWt](#) (HYPRE\_Solver solver, HYPRE\_Real outer\_wt, HYPRE\_Int level)
- HYPRE\_Int [HYPRE\\_ParCSRHybridSetMaxCoarseSize](#) (HYPRE\_Solver solver, HYPRE\_Int max\_↵coarse\_size)
- HYPRE\_Int [HYPRE\\_ParCSRHybridSetMinCoarseSize](#) (HYPRE\_Solver solver, HYPRE\_Int min\_coarse\_↵size)
- HYPRE\_Int [HYPRE\\_ParCSRHybridSetSeqThreshold](#) (HYPRE\_Solver solver, HYPRE\_Int seq\_threshold)
- HYPRE\_Int [HYPRE\\_ParCSRHybridSetRelaxWeight](#) (HYPRE\_Solver solver, HYPRE\_Real \*relax\_weight)
- HYPRE\_Int [HYPRE\\_ParCSRHybridSetOmega](#) (HYPRE\_Solver solver, HYPRE\_Real \*omega)
- HYPRE\_Int [HYPRE\\_ParCSRHybridSetAggNumLevels](#) (HYPRE\_Solver solver, HYPRE\_Int agg\_num\_↵levels)
- HYPRE\_Int [HYPRE\\_ParCSRHybridSetAggInterpType](#) (HYPRE\_Solver solver, HYPRE\_Int agg\_interp\_↵type)
- HYPRE\_Int [HYPRE\\_ParCSRHybridSetNumPaths](#) (HYPRE\_Solver solver, HYPRE\_Int num\_paths)
- HYPRE\_Int [HYPRE\\_ParCSRHybridSetNumFunctions](#) (HYPRE\_Solver solver, HYPRE\_Int num\_↵functions)
- HYPRE\_Int [HYPRE\\_ParCSRHybridSetDofFunc](#) (HYPRE\_Solver solver, HYPRE\_Int \*dof\_func)
- HYPRE\_Int [HYPRE\\_ParCSRHybridSetNodal](#) (HYPRE\_Solver solver, HYPRE\_Int nodal)
- HYPRE\_Int [HYPRE\\_ParCSRHybridSetKeepTranspose](#) (HYPRE\_Solver solver, HYPRE\_Int keepT)
- HYPRE\_Int [HYPRE\\_ParCSRHybridSetNonGalerkinTol](#) (HYPRE\_Solver solver, HYPRE\_Int num\_levels, HYPRE\_Real \*nongalerkin\_tol)
- HYPRE\_Int [HYPRE\\_ParCSRHybridGetNumIterations](#) (HYPRE\_Solver solver, HYPRE\_Int \*num\_its)
- HYPRE\_Int [HYPRE\\_ParCSRHybridGetDSCGNumIterations](#) (HYPRE\_Solver solver, HYPRE\_Int \*dscg\_↵num\_its)
- HYPRE\_Int [HYPRE\\_ParCSRHybridGetPCGNumIterations](#) (HYPRE\_Solver solver, HYPRE\_Int \*pcg\_↵num\_its)
- HYPRE\_Int [HYPRE\\_ParCSRHybridGetFinalRelativeResidualNorm](#) (HYPRE\_Solver solver, HYPRE\_Real \*norm)
- HYPRE\_Int [HYPRE\\_ParCSRHybridSetNumGridSweeps](#) (HYPRE\_Solver solver, HYPRE\_Int \*num\_↵grid\_sweeps)
- HYPRE\_Int [HYPRE\\_ParCSRHybridGetSetupSolveTime](#) (HYPRE\_Solver solver, HYPRE\_Real \*time)

### ParCSR MGR Solver

*Parallel multigrid reduction solver and preconditioner. This solver or preconditioner is designed with systems of PDEs in mind. However, it can also be used for scalar linear systems, particularly for problems where the user can exploit information from the physics of the problem. In this way, the MGR solver could potentially be used as a foundation for a physics-based preconditioner.*

- HYPRE\_Int [HYPRE\\_MGRCreate](#) (HYPRE\_Solver \*solver)
- HYPRE\_Int [HYPRE\\_MGRDestroy](#) (HYPRE\_Solver solver)
- HYPRE\_Int [HYPRE\\_MGRSetup](#) (HYPRE\_Solver solver, HYPRE\_ParCSRMatrix A, HYPRE\_ParVector b, HYPRE\_ParVector x)
- HYPRE\_Int [HYPRE\\_MGRSolve](#) (HYPRE\_Solver solver, HYPRE\_ParCSRMatrix A, HYPRE\_ParVector b, HYPRE\_ParVector x)
- HYPRE\_Int [HYPRE\\_MGRSetCpointsByContiguousBlock](#) (HYPRE\_Solver solver, HYPRE\_Int block\_↵size, HYPRE\_Int max\_num\_levels, HYPRE\_BigInt \*idx\_array, HYPRE\_Int \*num\_block\_coarse\_points, HYPRE\_Int \*\*block\_coarse\_indexes)



- HYPRE\_Int [HYPRE\\_MGRSetCpointsByBlock](#) (HYPRE\_Solver solver, HYPRE\_Int block\_size, HYPRE\_Int max\_num\_levels, HYPRE\_Int \*num\_block\_coarse\_points, HYPRE\_Int \*\*block\_coarse\_indexes)
- HYPRE\_Int [HYPRE\\_MGRSetCpointsByPointMarkerArray](#) (HYPRE\_Solver solver, HYPRE\_Int block\_size, HYPRE\_Int max\_num\_levels, HYPRE\_Int \*num\_block\_coarse\_points, HYPRE\_Int \*\*lvl\_block\_coarse\_indexes, HYPRE\_Int \*point\_marker\_array)
- HYPRE\_Int [HYPRE\\_MGRSetNonCpointsToFpoints](#) (HYPRE\_Solver solver, HYPRE\_Int nonCptToFptFlag)
- HYPRE\_Int [HYPRE\\_MGRSetMaxCoarseLevels](#) (HYPRE\_Solver solver, HYPRE\_Int maxlev)
- HYPRE\_Int [HYPRE\\_MGRSetBlockSize](#) (HYPRE\_Solver solver, HYPRE\_Int bsize)
- HYPRE\_Int [HYPRE\\_MGRSetReservedCoarseNodes](#) (HYPRE\_Solver solver, HYPRE\_Int reserved\_coarse\_size, HYPRE\_BigInt \*reserved\_coarse\_nodes)
- HYPRE\_Int [HYPRE\\_MGRSetReservedCpointsLevelToKeep](#) (HYPRE\_Solver solver, HYPRE\_Int level)
- HYPRE\_Int [HYPRE\\_MGRSetRelaxType](#) (HYPRE\_Solver solver, HYPRE\_Int relax\_type)
- HYPRE\_Int [HYPRE\\_MGRSetFRelaxMethod](#) (HYPRE\_Solver solver, HYPRE\_Int relax\_method)
- HYPRE\_Int [HYPRE\\_MGRSetLevelFRelaxMethod](#) (HYPRE\_Solver solver, HYPRE\_Int \*relax\_method)
- HYPRE\_Int [HYPRE\\_MGRSetCoarseGridMethod](#) (HYPRE\_Solver solver, HYPRE\_Int \*cg\_method)
- HYPRE\_Int [HYPRE\\_MGRSetLevelFRelaxNumFunctions](#) (HYPRE\_Solver solver, HYPRE\_Int \*num\_functions)
- HYPRE\_Int [HYPRE\\_MGRSetRestrictType](#) (HYPRE\_Solver solver, HYPRE\_Int restrict\_type)
- HYPRE\_Int [HYPRE\\_MGRSetLevelRestrictType](#) (HYPRE\_Solver solver, HYPRE\_Int \*restrict\_type)
- HYPRE\_Int [HYPRE\\_MGRSetNumRestrictSweeps](#) (HYPRE\_Solver solver, HYPRE\_Int nsweeps)
- HYPRE\_Int [HYPRE\\_MGRSetInterpType](#) (HYPRE\_Solver solver, HYPRE\_Int interp\_type)
- HYPRE\_Int [HYPRE\\_MGRSetLevelInterpType](#) (HYPRE\_Solver solver, HYPRE\_Int \*interp\_type)
- HYPRE\_Int [HYPRE\\_MGRSetNumRelaxSweeps](#) (HYPRE\_Solver solver, HYPRE\_Int nsweeps)
- HYPRE\_Int [HYPRE\\_MGRSetNumInterpSweeps](#) (HYPRE\_Solver solver, HYPRE\_Int nsweeps)
- HYPRE\_Int [HYPRE\\_MGRSetFSolver](#) (HYPRE\_Solver solver, HYPRE\_PtrToParSolverFcn fine\_grid\_solver\_solve, HYPRE\_PtrToParSolverFcn fine\_grid\_solver\_setup, HYPRE\_Solver fsolver)
- HYPRE\_Int [HYPRE\\_MGRBuildAif](#) (HYPRE\_ParCSRMatrix A, HYPRE\_Int \*CF\_marker, HYPRE\_Int debug\_flag, HYPRE\_ParCSRMatrix \*A\_ff)
- HYPRE\_Int [HYPRE\\_MGRSetCoarseSolver](#) (HYPRE\_Solver solver, HYPRE\_PtrToParSolverFcn coarse\_grid\_solver\_solve, HYPRE\_PtrToParSolverFcn coarse\_grid\_solver\_setup, HYPRE\_Solver coarse\_grid\_solver)
- HYPRE\_Int [HYPRE\\_MGRSetPrintLevel](#) (HYPRE\_Solver solver, HYPRE\_Int print\_level)
- HYPRE\_Int [HYPRE\\_MGRSetFrelaxPrintLevel](#) (HYPRE\_Solver solver, HYPRE\_Int print\_level)
- HYPRE\_Int [HYPRE\\_MGRSetCoarseGridPrintLevel](#) (HYPRE\_Solver solver, HYPRE\_Int print\_level)
- HYPRE\_Int [HYPRE\\_MGRSetTruncateCoarseGridThreshold](#) (HYPRE\_Solver solver, HYPRE\_Real threshold)
- HYPRE\_Int [HYPRE\\_MGRSetLogging](#) (HYPRE\_Solver solver, HYPRE\_Int logging)
- HYPRE\_Int [HYPRE\\_MGRSetMaxIter](#) (HYPRE\_Solver solver, HYPRE\_Int max\_iter)
- HYPRE\_Int [HYPRE\\_MGRSetTol](#) (HYPRE\_Solver solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_MGRSetMaxGlobalSmoothIters](#) (HYPRE\_Solver solver, HYPRE\_Int smooth\_iter)
- HYPRE\_Int [HYPRE\\_MGRSetGlobalSmoothType](#) (HYPRE\_Solver solver, HYPRE\_Int smooth\_type)
- HYPRE\_Int [HYPRE\\_MGRGetNumIterations](#) (HYPRE\_Solver solver, HYPRE\_Int \*num\_iterations)
- HYPRE\_Int [HYPRE\\_MGRGetCoarseGridConvergenceFactor](#) (HYPRE\_Solver solver, HYPRE\_Real \*conv\_factor)
- HYPRE\_Int [HYPRE\\_MGRSetPMaxElmts](#) (HYPRE\_Solver solver, HYPRE\_Int P\_max\_elmts)
- HYPRE\_Int [HYPRE\\_MGRGetFinalRelativeResidualNorm](#) (HYPRE\_Solver solver, HYPRE\_Real \*res\_norm)

### ParCSR ILU Solver

(Parallel) ILU smoother

- HYPRE\_Int [HYPRE\\_ILUCreate](#) (HYPRE\_Solver \*solver)
- HYPRE\_Int [HYPRE\\_ILUDestroy](#) (HYPRE\_Solver solver)
- HYPRE\_Int [HYPRE\\_ILUSetup](#) (HYPRE\_Solver solver, HYPRE\_ParCSRMatrix A, HYPRE\_ParVector b, HYPRE\_ParVector x)
- HYPRE\_Int [HYPRE\\_ILUSolve](#) (HYPRE\_Solver solver, HYPRE\_ParCSRMatrix A, HYPRE\_ParVector b, HYPRE\_ParVector x)
- HYPRE\_Int [HYPRE\\_ILUSetMaxIter](#) (HYPRE\_Solver solver, HYPRE\_Int max\_iter)
- HYPRE\_Int [HYPRE\\_ILUSetTol](#) (HYPRE\_Solver solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_ILUSetLevelOfFill](#) (HYPRE\_Solver solver, HYPRE\_Int lfil)
- HYPRE\_Int [HYPRE\\_ILUSetMaxNnzPerRow](#) (HYPRE\_Solver solver, HYPRE\_Int nzmax)

- HYPRE\_Int [HYPRE\\_ILUSetDropThreshold](#) (HYPRE\_Solver solver, HYPRE\_Real threshold)
- HYPRE\_Int [HYPRE\\_ILUSetDropThresholdArray](#) (HYPRE\_Solver solver, HYPRE\_Real \*threshold)
- HYPRE\_Int [HYPRE\\_ILUSetNSHDropThreshold](#) (HYPRE\_Solver solver, HYPRE\_Real threshold)
- HYPRE\_Int [HYPRE\\_ILUSetNSHDropThresholdArray](#) (HYPRE\_Solver solver, HYPRE\_Real \*threshold)
- HYPRE\_Int [HYPRE\\_ILUSetSchurMaxIter](#) (HYPRE\_Solver solver, HYPRE\_Int ss\_max\_iter)
- HYPRE\_Int [HYPRE\\_ILUSetType](#) (HYPRE\_Solver solver, HYPRE\_Int ilu\_type)
- HYPRE\_Int [HYPRE\\_ILUSetLocalReordering](#) (HYPRE\_Solver solver, HYPRE\_Int reordering\_type)
- HYPRE\_Int [HYPRE\\_ILUSetPrintLevel](#) (HYPRE\_Solver solver, HYPRE\_Int print\_level)
- HYPRE\_Int [HYPRE\\_ILUSetLogging](#) (HYPRE\_Solver solver, HYPRE\_Int logging)
- HYPRE\_Int [HYPRE\\_ILUGetNumIterations](#) (HYPRE\_Solver solver, HYPRE\_Int \*num\_iterations)
- HYPRE\_Int [HYPRE\\_ILUGetFinalRelativeResidualNorm](#) (HYPRE\_Solver solver, HYPRE\_Real \*res\_↵ norm)
- HYPRE\_ParCSRMatrix [GenerateLaplacian](#) (MPI\_Comm comm, HYPRE\_BigInt nx, HYPRE\_BigInt ny, HYPRE\_BigInt nz, HYPRE\_Int P, HYPRE\_Int Q, HYPRE\_Int R, HYPRE\_Int p, HYPRE\_Int q, HYPRE\_Int r, HYPRE\_Real \*value)
- HYPRE\_ParCSRMatrix [GenerateLaplacian27pt](#) (MPI\_Comm comm, HYPRE\_BigInt nx, HYPRE\_BigInt ny, HYPRE\_BigInt nz, HYPRE\_Int P, HYPRE\_Int Q, HYPRE\_Int R, HYPRE\_Int p, HYPRE\_Int q, HYPRE\_Int r, HYPRE\_Real \*value)
- HYPRE\_ParCSRMatrix [GenerateLaplacian9pt](#) (MPI\_Comm comm, HYPRE\_BigInt nx, HYPRE\_BigInt ny, HYPRE\_Int P, HYPRE\_Int Q, HYPRE\_Int p, HYPRE\_Int q, HYPRE\_Real \*value)
- HYPRE\_ParCSRMatrix [GenerateDifConv](#) (MPI\_Comm comm, HYPRE\_BigInt nx, HYPRE\_BigInt ny, HYPRE\_BigInt nz, HYPRE\_Int P, HYPRE\_Int Q, HYPRE\_Int R, HYPRE\_Int p, HYPRE\_Int q, HYPRE\_Int r, HYPRE\_Real \*value)
- HYPRE\_ParCSRMatrix [GenerateRotate7pt](#) (MPI\_Comm comm, HYPRE\_BigInt nx, HYPRE\_BigInt ny, HYPRE\_Int P, HYPRE\_Int Q, HYPRE\_Int p, HYPRE\_Int q, HYPRE\_Real alpha, HYPRE\_Real eps)
- HYPRE\_ParCSRMatrix [GenerateVarDifConv](#) (MPI\_Comm comm, HYPRE\_BigInt nx, HYPRE\_BigInt ny, HYPRE\_BigInt nz, HYPRE\_Int P, HYPRE\_Int Q, HYPRE\_Int R, HYPRE\_Int p, HYPRE\_Int q, HYPRE\_Int r, HYPRE\_Real eps, HYPRE\_ParVector \*rhs\_ptr)
- HYPRE\_ParCSRMatrix [GenerateRSVarDifConv](#) (MPI\_Comm comm, HYPRE\_BigInt nx, HYPRE\_BigInt ny, HYPRE\_BigInt nz, HYPRE\_Int P, HYPRE\_Int Q, HYPRE\_Int R, HYPRE\_Int p, HYPRE\_Int q, HYPRE\_↵\_Int r, HYPRE\_Real eps, HYPRE\_ParVector \*rhs\_ptr, HYPRE\_Int type)
- float \* [GenerateCoordinates](#) (MPI\_Comm comm, HYPRE\_BigInt nx, HYPRE\_BigInt ny, HYPRE\_BigInt nz, HYPRE\_Int P, HYPRE\_Int Q, HYPRE\_Int R, HYPRE\_Int p, HYPRE\_Int q, HYPRE\_Int r, HYPRE\_Int coorddim)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetPostInterpType](#) (HYPRE\_Solver solver, HYPRE\_Int post\_interp\_↵ type)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetJacobiTruncThreshold](#) (HYPRE\_Solver solver, HYPRE\_Real jacobi\_trunc\_threshold)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetNumCRRRelaxSteps](#) (HYPRE\_Solver solver, HYPRE\_Int num\_CR\_↵\_relax\_steps)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetCRRate](#) (HYPRE\_Solver solver, HYPRE\_Real CR\_rate)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetCRStrongTh](#) (HYPRE\_Solver solver, HYPRE\_Real CR\_strong\_th)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetCRUseCG](#) (HYPRE\_Solver solver, HYPRE\_Int CR\_use\_CG)
- HYPRE\_Int [HYPRE\\_BoomerAMGSetISType](#) (HYPRE\_Solver solver, HYPRE\_Int IS\_type)

### ParCSR LOBPCG Eigensolver

These routines should be used in conjunction with the generic interface in [Eigensolvers](#).

- HYPRE\_Int [HYPRE\\_ParCSRSetupInterpreter](#) (mv\_InterfaceInterpreter \*i)
- HYPRE\_Int [HYPRE\\_ParCSRSetupMatvec](#) (HYPRE\_MatvecFunctions \*mv)
- HYPRE\_Int [HYPRE\\_ParCSRMultiVectorPrint](#) (void \*x\_, const char \*fileName)
- void \* [HYPRE\\_ParCSRMultiVectorRead](#) (MPI\_Comm comm, void \*ii\_, const char \*fileName)

### ParCSR Solvers

- #define [HYPRE\\_SOLVER\\_STRUCT](#)
- #define [HYPRE\\_MODIFYPC](#)
- typedef struct hypre\_Solver\_struct \* [HYPRE\\_Solver](#)
- typedef HYPRE\_Int(\* [HYPRE\\_PtrToParSolverFcn](#)) (HYPRE\_Solver, HYPRE\_ParCSRMatrix, HYPRE\_Par\_↵ Vector, HYPRE\_ParVector)
- typedef HYPRE\_Int(\* [HYPRE\\_PtrToModifyPCFcn](#)) (HYPRE\_Solver, HYPRE\_Int, HYPRE\_Real)

## 4.5 HYPRE\_sstruct\_Is.h File Reference

### Functions

#### SStruct SysPFMG Solver

*SysPFMG is a semicoarsening multigrid solver similar to PFMG, but for systems of PDEs. For periodic problems, users should try to set the grid size in periodic dimensions to be as close to a power-of-two as possible (for more details, see Struct PFMG Solver).*

- HYPRE\_Int [HYPRE\\_SStructSysPFMGCreate](#) (MPI\_Comm comm, [HYPRE\\_SStructSolver](#) \*solver)
- HYPRE\_Int [HYPRE\\_SStructSysPFMGDestroy](#) ([HYPRE\\_SStructSolver](#) solver)
- HYPRE\_Int [HYPRE\\_SStructSysPFMGSetup](#) ([HYPRE\\_SStructSolver](#) solver, [HYPRE\\_SStructMatrix](#) A, [HYPRE\\_SStructVector](#) b, [HYPRE\\_SStructVector](#) x)
- HYPRE\_Int [HYPRE\\_SStructSysPFMGsolve](#) ([HYPRE\\_SStructSolver](#) solver, [HYPRE\\_SStructMatrix](#) A, [HYPRE\\_SStructVector](#) b, [HYPRE\\_SStructVector](#) x)
- HYPRE\_Int [HYPRE\\_SStructSysPFMGSetTol](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_SStructSysPFMGSetMaxIter](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Int max\_iter)
- HYPRE\_Int [HYPRE\\_SStructSysPFMGSetRelChange](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Int rel\_↵ change)
- HYPRE\_Int [HYPRE\\_SStructSysPFMGSetZeroGuess](#) ([HYPRE\\_SStructSolver](#) solver)
- HYPRE\_Int [HYPRE\\_SStructSysPFMGSetNonZeroGuess](#) ([HYPRE\\_SStructSolver](#) solver)
- HYPRE\_Int [HYPRE\\_SStructSysPFMGSetRelaxType](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Int relax\_↵ type)
- HYPRE\_Int [HYPRE\\_SStructSysPFMGSetJacobiWeight](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Real weight)
- HYPRE\_Int [HYPRE\\_SStructSysPFMGSetNumPreRelax](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Int num\_pre\_relax)
- HYPRE\_Int [HYPRE\\_SStructSysPFMGSetNumPostRelax](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Int num\_post\_relax)
- HYPRE\_Int [HYPRE\\_SStructSysPFMGSetSkipRelax](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Int skip\_↵ relax)
- HYPRE\_Int [HYPRE\\_SStructSysPFMGSetDxyz](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Real \*dxyz)
- HYPRE\_Int [HYPRE\\_SStructSysPFMGSetLogging](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Int logging)
- HYPRE\_Int [HYPRE\\_SStructSysPFMGSetPrintLevel](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Int print\_↵ level)
- HYPRE\_Int [HYPRE\\_SStructSysPFMGGetNumIterations](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Int \*num\_iterations)
- HYPRE\_Int [HYPRE\\_SStructSysPFMGGetFinalRelativeResidualNorm](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Real \*norm)

#### SStruct FAC Solver

- HYPRE\_Int [HYPRE\\_SStructFACCreate](#) (MPI\_Comm comm, [HYPRE\\_SStructSolver](#) \*solver)
- HYPRE\_Int [HYPRE\\_SStructFACDestroy2](#) ([HYPRE\\_SStructSolver](#) solver)
- HYPRE\_Int [HYPRE\\_SStructFACAMR\\_RAP](#) ([HYPRE\\_SStructMatrix](#) A, HYPRE\_Int(\*rfactors)[HYPRE\_↵ MAXDIM], [HYPRE\\_SStructMatrix](#) \*fac\_A)
- HYPRE\_Int [HYPRE\\_SStructFACSetup2](#) ([HYPRE\\_SStructSolver](#) solver, [HYPRE\\_SStructMatrix](#) A, [HYPRE\\_SStructVector](#) b, [HYPRE\\_SStructVector](#) x)
- HYPRE\_Int [HYPRE\\_SStructFACsolve3](#) ([HYPRE\\_SStructSolver](#) solver, [HYPRE\\_SStructMatrix](#) A, [HYPRE\\_SStructVector](#) b, [HYPRE\\_SStructVector](#) x)
- HYPRE\_Int [HYPRE\\_SStructFACSetPLevels](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Int nparts, HYPRE\_↵ \_Int \*plevels)
- HYPRE\_Int [HYPRE\\_SStructFACSetPRefinements](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Int nparts, HYPRE\_Int(\*rfactors)[HYPRE\_MAXDIM])
- HYPRE\_Int [HYPRE\\_SStructFACZeroCFSten](#) ([HYPRE\\_SStructMatrix](#) A, [HYPRE\\_SStructGrid](#) grid, HYPRE\_Int part, HYPRE\_Int rfactors[HYPRE\_MAXDIM])
- HYPRE\_Int [HYPRE\\_SStructFACZeroFCSten](#) ([HYPRE\\_SStructMatrix](#) A, [HYPRE\\_SStructGrid](#) grid, HYPRE\_Int part)
- HYPRE\_Int [HYPRE\\_SStructFACZeroAMRMatrixData](#) ([HYPRE\\_SStructMatrix](#) A, HYPRE\_Int part\_crse, HYPRE\_Int rfactors[HYPRE\_MAXDIM])



- HYPRE\_Int [HYPRE\\_SStructFACZeroAMRVectorData](#) (HYPRE\_SStructVector b, HYPRE\_Int \*plevels, HYPRE\_Int(\*rfactors)[HYPRE\_MAXDIM])
- HYPRE\_Int [HYPRE\\_SStructFACSetMaxLevels](#) (HYPRE\_SStructSolver solver, HYPRE\_Int max\_levels)
- HYPRE\_Int [HYPRE\\_SStructFACSetTol](#) (HYPRE\_SStructSolver solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_SStructFACSetMaxIter](#) (HYPRE\_SStructSolver solver, HYPRE\_Int max\_iter)
- HYPRE\_Int [HYPRE\\_SStructFACSetRelChange](#) (HYPRE\_SStructSolver solver, HYPRE\_Int rel\_change)
- HYPRE\_Int [HYPRE\\_SStructFACSetZeroGuess](#) (HYPRE\_SStructSolver solver)
- HYPRE\_Int [HYPRE\\_SStructFACSetNonZeroGuess](#) (HYPRE\_SStructSolver solver)
- HYPRE\_Int [HYPRE\\_SStructFACSetRelaxType](#) (HYPRE\_SStructSolver solver, HYPRE\_Int relax\_type)
- HYPRE\_Int [HYPRE\\_SStructFACSetJacobiWeight](#) (HYPRE\_SStructSolver solver, HYPRE\_Real weight)
- HYPRE\_Int [HYPRE\\_SStructFACSetNumPreRelax](#) (HYPRE\_SStructSolver solver, HYPRE\_Int num\_pre↵\_relax)
- HYPRE\_Int [HYPRE\\_SStructFACSetNumPostRelax](#) (HYPRE\_SStructSolver solver, HYPRE\_Int num\_↵post\_relax)
- HYPRE\_Int [HYPRE\\_SStructFACSetCoarseSolverType](#) (HYPRE\_SStructSolver solver, HYPRE\_Int csolver\_type)
- HYPRE\_Int [HYPRE\\_SStructFACSetLogging](#) (HYPRE\_SStructSolver solver, HYPRE\_Int logging)
- HYPRE\_Int [HYPRE\\_SStructFACGetNumIterations](#) (HYPRE\_SStructSolver solver, HYPRE\_Int \*num\_↵iterations)
- HYPRE\_Int [HYPRE\\_SStructFACGetFinalRelativeResidualNorm](#) (HYPRE\_SStructSolver solver, HYPRE\_↵Real \*norm)

### SStruct Maxwell Solver

- HYPRE\_Int [HYPRE\\_SStructMaxwellCreate](#) (MPI\_Comm comm, HYPRE\_SStructSolver \*solver)
- HYPRE\_Int [HYPRE\\_SStructMaxwellDestroy](#) (HYPRE\_SStructSolver solver)
- HYPRE\_Int [HYPRE\\_SStructMaxwellSetup](#) (HYPRE\_SStructSolver solver, HYPRE\_SStructMatrix A, HYPRE\_SStructVector b, HYPRE\_SStructVector x)
- HYPRE\_Int [HYPRE\\_SStructMaxwellSolve](#) (HYPRE\_SStructSolver solver, HYPRE\_SStructMatrix A, HYPRE\_SStructVector b, HYPRE\_SStructVector x)
- HYPRE\_Int [HYPRE\\_SStructMaxwellSolve2](#) (HYPRE\_SStructSolver solver, HYPRE\_SStructMatrix A, HYPRE\_SStructVector b, HYPRE\_SStructVector x)
- HYPRE\_Int [HYPRE\\_SStructMaxwellSetGrad](#) (HYPRE\_SStructSolver solver, HYPRE\_ParCSRMatrix T)
- HYPRE\_Int [HYPRE\\_SStructMaxwellSetRfactors](#) (HYPRE\_SStructSolver solver, HYPRE\_Int rfactors[HYPRE\_↵\_MAXDIM])
- HYPRE\_Int [HYPRE\\_SStructMaxwellPhysBdy](#) (HYPRE\_SStructGrid \*grid\_I, HYPRE\_Int num\_levels, HYPRE\_Int rfactors[HYPRE\_MAXDIM], HYPRE\_Int \*\*\*BdryRanks\_ptr, HYPRE\_Int \*\*BdryRanksCnt\_↵ptr)
- HYPRE\_Int [HYPRE\\_SStructMaxwellEliminateRowsCols](#) (HYPRE\_ParCSRMatrix parA, HYPRE\_Int nrows, HYPRE\_Int \*rows)
- HYPRE\_Int [HYPRE\\_SStructMaxwellZeroVector](#) (HYPRE\_ParVector b, HYPRE\_Int \*rows, HYPRE\_Int nrows)
- HYPRE\_Int [HYPRE\\_SStructMaxwellSetSetConstantCoef](#) (HYPRE\_SStructSolver solver, HYPRE\_Int flag)
- HYPRE\_Int [HYPRE\\_SStructMaxwellGrad](#) (HYPRE\_SStructGrid grid, HYPRE\_ParCSRMatrix \*T)
- HYPRE\_Int [HYPRE\\_SStructMaxwellSetTol](#) (HYPRE\_SStructSolver solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_SStructMaxwellSetMaxIter](#) (HYPRE\_SStructSolver solver, HYPRE\_Int max\_iter)
- HYPRE\_Int [HYPRE\\_SStructMaxwellSetRelChange](#) (HYPRE\_SStructSolver solver, HYPRE\_Int rel\_↵change)
- HYPRE\_Int [HYPRE\\_SStructMaxwellSetNumPreRelax](#) (HYPRE\_SStructSolver solver, HYPRE\_Int num\_↵pre\_relax)
- HYPRE\_Int [HYPRE\\_SStructMaxwellSetNumPostRelax](#) (HYPRE\_SStructSolver solver, HYPRE\_Int num\_↵post\_relax)
- HYPRE\_Int [HYPRE\\_SStructMaxwellSetLogging](#) (HYPRE\_SStructSolver solver, HYPRE\_Int logging)
- HYPRE\_Int [HYPRE\\_SStructMaxwellGetNumIterations](#) (HYPRE\_SStructSolver solver, HYPRE\_Int \*num\_↵iterations)
- HYPRE\_Int [HYPRE\\_SStructMaxwellGetFinalRelativeResidualNorm](#) (HYPRE\_SStructSolver solver, HYPRE\_Real \*norm)

### SStruct PCG Solver

*These routines should be used in conjunction with the generic interface in [Krylov Solvers](#).*

- HYPRE\_Int HYPRE\_SStructPCGCreate (MPI\_Comm comm, HYPRE\_SStructSolver \*solver)
- HYPRE\_Int HYPRE\_SStructPCGDestroy (HYPRE\_SStructSolver solver)
- HYPRE\_Int HYPRE\_SStructPCGSetup (HYPRE\_SStructSolver solver, HYPRE\_SStructMatrix A, HYPRE\_SStructVector b, HYPRE\_SStructVector x)
- HYPRE\_Int HYPRE\_SStructPCGSolve (HYPRE\_SStructSolver solver, HYPRE\_SStructMatrix A, HYPRE\_SStructVector b, HYPRE\_SStructVector x)
- HYPRE\_Int HYPRE\_SStructPCGSetTol (HYPRE\_SStructSolver solver, HYPRE\_Real tol)
- HYPRE\_Int HYPRE\_SStructPCGSetAbsoluteTol (HYPRE\_SStructSolver solver, HYPRE\_Real tol)
- HYPRE\_Int HYPRE\_SStructPCGSetMaxIter (HYPRE\_SStructSolver solver, HYPRE\_Int max\_iter)
- HYPRE\_Int HYPRE\_SStructPCGSetTwoNorm (HYPRE\_SStructSolver solver, HYPRE\_Int two\_norm)
- HYPRE\_Int HYPRE\_SStructPCGSetRelChange (HYPRE\_SStructSolver solver, HYPRE\_Int rel\_change)
- HYPRE\_Int HYPRE\_SStructPCGSetPrecond (HYPRE\_SStructSolver solver, HYPRE\_PtrToSStructSolverFcn precondition, HYPRE\_PtrToSStructSolverFcn precondition\_setup, void \*precond\_solver)
- HYPRE\_Int HYPRE\_SStructPCGSetLogging (HYPRE\_SStructSolver solver, HYPRE\_Int logging)
- HYPRE\_Int HYPRE\_SStructPCGSetPrintLevel (HYPRE\_SStructSolver solver, HYPRE\_Int level)
- HYPRE\_Int HYPRE\_SStructPCGGetNumIterations (HYPRE\_SStructSolver solver, HYPRE\_Int \*num\_↵ iterations)
- HYPRE\_Int HYPRE\_SStructPCGGetFinalRelativeResidualNorm (HYPRE\_SStructSolver solver, HYPRE\_Real \*norm)
- HYPRE\_Int HYPRE\_SStructPCGGetResidual (HYPRE\_SStructSolver solver, void \*\*residual)
- HYPRE\_Int HYPRE\_SStructDiagScaleSetup (HYPRE\_SStructSolver solver, HYPRE\_SStructMatrix A, HYPRE\_SStructVector y, HYPRE\_SStructVector x)
- HYPRE\_Int HYPRE\_SStructDiagScale (HYPRE\_SStructSolver solver, HYPRE\_SStructMatrix A, HYPRE\_SStructVector y, HYPRE\_SStructVector x)

### SStruct GMRES Solver

These routines should be used in conjunction with the generic interface in [Krylov Solvers](#).

- HYPRE\_Int HYPRE\_SStructGMRESCreate (MPI\_Comm comm, HYPRE\_SStructSolver \*solver)
- HYPRE\_Int HYPRE\_SStructGMRESDestroy (HYPRE\_SStructSolver solver)
- HYPRE\_Int HYPRE\_SStructGMRESSetup (HYPRE\_SStructSolver solver, HYPRE\_SStructMatrix A, HYPRE\_SStructVector b, HYPRE\_SStructVector x)
- HYPRE\_Int HYPRE\_SStructGMRESSolve (HYPRE\_SStructSolver solver, HYPRE\_SStructMatrix A, HYPRE\_SStructVector b, HYPRE\_SStructVector x)
- HYPRE\_Int HYPRE\_SStructGMRESSetTol (HYPRE\_SStructSolver solver, HYPRE\_Real tol)
- HYPRE\_Int HYPRE\_SStructGMRESSetAbsoluteTol (HYPRE\_SStructSolver solver, HYPRE\_Real tol)
- HYPRE\_Int HYPRE\_SStructGMRESSetMinIter (HYPRE\_SStructSolver solver, HYPRE\_Int min\_iter)
- HYPRE\_Int HYPRE\_SStructGMRESSetMaxIter (HYPRE\_SStructSolver solver, HYPRE\_Int max\_iter)
- HYPRE\_Int HYPRE\_SStructGMRESSetKDim (HYPRE\_SStructSolver solver, HYPRE\_Int k\_dim)
- HYPRE\_Int HYPRE\_SStructGMRESSetStopCrit (HYPRE\_SStructSolver solver, HYPRE\_Int stop\_crit)
- HYPRE\_Int HYPRE\_SStructGMRESSetPrecond (HYPRE\_SStructSolver solver, HYPRE\_PtrToSStructSolverFcn precondition, HYPRE\_PtrToSStructSolverFcn precondition\_setup, void \*precond\_solver)
- HYPRE\_Int HYPRE\_SStructGMRESSetLogging (HYPRE\_SStructSolver solver, HYPRE\_Int logging)
- HYPRE\_Int HYPRE\_SStructGMRESSetPrintLevel (HYPRE\_SStructSolver solver, HYPRE\_Int print\_level)
- HYPRE\_Int HYPRE\_SStructGMRESGetNumIterations (HYPRE\_SStructSolver solver, HYPRE\_Int \*num\_↵ iterations)
- HYPRE\_Int HYPRE\_SStructGMRESGetFinalRelativeResidualNorm (HYPRE\_SStructSolver solver, HYPRE\_Real \*norm)
- HYPRE\_Int HYPRE\_SStructGMRESGetResidual (HYPRE\_SStructSolver solver, void \*\*residual)

### SStruct FlexGMRES Solver

These routines should be used in conjunction with the generic interface in [Krylov Solvers](#).

- HYPRE\_Int HYPRE\_SStructFlexGMRESCreate (MPI\_Comm comm, HYPRE\_SStructSolver \*solver)
- HYPRE\_Int HYPRE\_SStructFlexGMRESDestroy (HYPRE\_SStructSolver solver)
- HYPRE\_Int HYPRE\_SStructFlexGMRESSetup (HYPRE\_SStructSolver solver, HYPRE\_SStructMatrix A, HYPRE\_SStructVector b, HYPRE\_SStructVector x)
- HYPRE\_Int HYPRE\_SStructFlexGMRESSolve (HYPRE\_SStructSolver solver, HYPRE\_SStructMatrix A, HYPRE\_SStructVector b, HYPRE\_SStructVector x)
- HYPRE\_Int HYPRE\_SStructFlexGMRESSetTol (HYPRE\_SStructSolver solver, HYPRE\_Real tol)

- HYPRE\_Int [HYPRE\\_SStructFlexGMRESSetAbsoluteTol](#) (HYPRE\_SStructSolver solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_SStructFlexGMRESSetMinIter](#) (HYPRE\_SStructSolver solver, HYPRE\_Int min\_iter)
- HYPRE\_Int [HYPRE\\_SStructFlexGMRESSetMaxIter](#) (HYPRE\_SStructSolver solver, HYPRE\_Int max\_iter)
- HYPRE\_Int [HYPRE\\_SStructFlexGMRESSetKDim](#) (HYPRE\_SStructSolver solver, HYPRE\_Int k\_dim)
- HYPRE\_Int [HYPRE\\_SStructFlexGMRESSetPrecond](#) (HYPRE\_SStructSolver solver, HYPRE\_PtrToSStructSolverFcn precondition, HYPRE\_PtrToSStructSolverFcn precondition\_setup, void \*precond\_solver)
- HYPRE\_Int [HYPRE\\_SStructFlexGMRESSetLogging](#) (HYPRE\_SStructSolver solver, HYPRE\_Int logging)
- HYPRE\_Int [HYPRE\\_SStructFlexGMRESSetPrintLevel](#) (HYPRE\_SStructSolver solver, HYPRE\_Int print\_level)
- HYPRE\_Int [HYPRE\\_SStructFlexGMRESGetNumIterations](#) (HYPRE\_SStructSolver solver, HYPRE\_Int \*num\_iterations)
- HYPRE\_Int [HYPRE\\_SStructFlexGMRESGetFinalRelativeResidualNorm](#) (HYPRE\_SStructSolver solver, HYPRE\_Real \*norm)
- HYPRE\_Int [HYPRE\\_SStructFlexGMRESGetResidual](#) (HYPRE\_SStructSolver solver, void \*\*residual)
- HYPRE\_Int [HYPRE\\_SStructFlexGMRESSetModifyPC](#) (HYPRE\_SStructSolver solver, HYPRE\_PtrToModifyPCFcn modify\_pc)

### SStruct LGMRES Solver

*These routines should be used in conjunction with the generic interface in [Krylov Solvers](#).*

- HYPRE\_Int [HYPRE\\_SStructLGMRESCreate](#) (MPI\_Comm comm, HYPRE\_SStructSolver \*solver)
- HYPRE\_Int [HYPRE\\_SStructLGMRESDestroy](#) (HYPRE\_SStructSolver solver)
- HYPRE\_Int [HYPRE\\_SStructLGMRESSetup](#) (HYPRE\_SStructSolver solver, HYPRE\_SStructMatrix A, HYPRE\_SStructVector b, HYPRE\_SStructVector x)
- HYPRE\_Int [HYPRE\\_SStructLGMRESSolve](#) (HYPRE\_SStructSolver solver, HYPRE\_SStructMatrix A, HYPRE\_SStructVector b, HYPRE\_SStructVector x)
- HYPRE\_Int [HYPRE\\_SStructLGMRESSetTol](#) (HYPRE\_SStructSolver solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_SStructLGMRESSetAbsoluteTol](#) (HYPRE\_SStructSolver solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_SStructLGMRESSetMinIter](#) (HYPRE\_SStructSolver solver, HYPRE\_Int min\_iter)
- HYPRE\_Int [HYPRE\\_SStructLGMRESSetMaxIter](#) (HYPRE\_SStructSolver solver, HYPRE\_Int max\_iter)
- HYPRE\_Int [HYPRE\\_SStructLGMRESSetKDim](#) (HYPRE\_SStructSolver solver, HYPRE\_Int k\_dim)
- HYPRE\_Int [HYPRE\\_SStructLGMRESSetAugDim](#) (HYPRE\_SStructSolver solver, HYPRE\_Int aug\_dim)
- HYPRE\_Int [HYPRE\\_SStructLGMRESSetPrecond](#) (HYPRE\_SStructSolver solver, HYPRE\_PtrToSStructSolverFcn precondition, HYPRE\_PtrToSStructSolverFcn precondition\_setup, void \*precond\_solver)
- HYPRE\_Int [HYPRE\\_SStructLGMRESSetLogging](#) (HYPRE\_SStructSolver solver, HYPRE\_Int logging)
- HYPRE\_Int [HYPRE\\_SStructLGMRESSetPrintLevel](#) (HYPRE\_SStructSolver solver, HYPRE\_Int print\_level)
- HYPRE\_Int [HYPRE\\_SStructLGMRESGetNumIterations](#) (HYPRE\_SStructSolver solver, HYPRE\_Int \*num\_iterations)
- HYPRE\_Int [HYPRE\\_SStructLGMRESGetFinalRelativeResidualNorm](#) (HYPRE\_SStructSolver solver, HYPRE\_Real \*norm)
- HYPRE\_Int [HYPRE\\_SStructLGMRESGetResidual](#) (HYPRE\_SStructSolver solver, void \*\*residual)

### SStruct BiCGSTAB Solver

*These routines should be used in conjunction with the generic interface in [Krylov Solvers](#).*

- HYPRE\_Int [HYPRE\\_SStructBiCGSTABCreate](#) (MPI\_Comm comm, HYPRE\_SStructSolver \*solver)
- HYPRE\_Int [HYPRE\\_SStructBiCGSTABDestroy](#) (HYPRE\_SStructSolver solver)
- HYPRE\_Int [HYPRE\\_SStructBiCGSTABSetup](#) (HYPRE\_SStructSolver solver, HYPRE\_SStructMatrix A, HYPRE\_SStructVector b, HYPRE\_SStructVector x)
- HYPRE\_Int [HYPRE\\_SStructBiCGSTABSolve](#) (HYPRE\_SStructSolver solver, HYPRE\_SStructMatrix A, HYPRE\_SStructVector b, HYPRE\_SStructVector x)
- HYPRE\_Int [HYPRE\\_SStructBiCGSTABSetTol](#) (HYPRE\_SStructSolver solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_SStructBiCGSTABSetAbsoluteTol](#) (HYPRE\_SStructSolver solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_SStructBiCGSTABSetMinIter](#) (HYPRE\_SStructSolver solver, HYPRE\_Int min\_iter)
- HYPRE\_Int [HYPRE\\_SStructBiCGSTABSetMaxIter](#) (HYPRE\_SStructSolver solver, HYPRE\_Int max\_iter)
- HYPRE\_Int [HYPRE\\_SStructBiCGSTABSetStopCrit](#) (HYPRE\_SStructSolver solver, HYPRE\_Int stop\_crit)
- HYPRE\_Int [HYPRE\\_SStructBiCGSTABSetPrecond](#) (HYPRE\_SStructSolver solver, HYPRE\_PtrToSStructSolverFcn precondition, HYPRE\_PtrToSStructSolverFcn precondition\_setup, void \*precond\_solver)
- HYPRE\_Int [HYPRE\\_SStructBiCGSTABSetLogging](#) (HYPRE\_SStructSolver solver, HYPRE\_Int logging)

- HYPRE\_Int [HYPRE\\_SStructBiCGSTABSetPrintLevel](#) (HYPRE\_SStructSolver solver, HYPRE\_Int level)
- HYPRE\_Int [HYPRE\\_SStructBiCGSTABGetNumIterations](#) (HYPRE\_SStructSolver solver, HYPRE\_Int \*num\_iterations)
- HYPRE\_Int [HYPRE\\_SStructBiCGSTABGetFinalRelativeResidualNorm](#) (HYPRE\_SStructSolver solver, HYPRE\_Real \*norm)
- HYPRE\_Int [HYPRE\\_SStructBiCGSTABGetResidual](#) (HYPRE\_SStructSolver solver, void \*\*residual)

### SStruct LOBPCG Eigensolver

*These routines should be used in conjunction with the generic interface in [Eigensolvers](#).*

- HYPRE\_Int [HYPRE\\_SStructSetupInterpreter](#) (mv\_InterfaceInterpreter \*i)
- HYPRE\_Int [HYPRE\\_SStructSetupMatvec](#) (HYPRE\_MatvecFunctions \*mv)

### SStruct Solvers

- #define [HYPRE\\_MODIFYPC](#)
- #define [HYPRE\\_SOLVER\\_STRUCT](#)
- typedef struct hypre\_SStructSolver\_struct \* [HYPRE\\_SStructSolver](#)
- typedef HYPRE\_Int(\* [HYPRE\\_PtrToSStructSolverFcn](#)) (HYPRE\_SStructSolver, [HYPRE\\_SStructMatrix](#), [HYPRE\\_SStructVector](#), [HYPRE\\_SStructVector](#))
- typedef struct hypre\_Solver\_struct \* [HYPRE\\_Solver](#)
- typedef HYPRE\_Int(\* [HYPRE\\_PtrToModifyPCFcn](#)) (HYPRE\_Solver, HYPRE\_Int, HYPRE\_Real)

### SStruct Split Solver

- #define [HYPRE\\_PFMG](#) 10
- #define [HYPRE\\_SMG](#) 11
- #define [HYPRE\\_Jacobi](#) 17
- HYPRE\_Int [HYPRE\\_SStructSplitCreate](#) (MPI\_Comm comm, [HYPRE\\_SStructSolver](#) \*solver)
- HYPRE\_Int [HYPRE\\_SStructSplitDestroy](#) ([HYPRE\\_SStructSolver](#) solver)
- HYPRE\_Int [HYPRE\\_SStructSplitSetup](#) ([HYPRE\\_SStructSolver](#) solver, [HYPRE\\_SStructMatrix](#) A, [HYPRE\\_SStructVector](#) b, [HYPRE\\_SStructVector](#) x)
- HYPRE\_Int [HYPRE\\_SStructSplitSolve](#) ([HYPRE\\_SStructSolver](#) solver, [HYPRE\\_SStructMatrix](#) A, [HYPRE\\_SStructVector](#) b, [HYPRE\\_SStructVector](#) x)
- HYPRE\_Int [HYPRE\\_SStructSplitSetTol](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_SStructSplitSetMaxIter](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Int max\_iter)
- HYPRE\_Int [HYPRE\\_SStructSplitSetZeroGuess](#) ([HYPRE\\_SStructSolver](#) solver)
- HYPRE\_Int [HYPRE\\_SStructSplitSetNonZeroGuess](#) ([HYPRE\\_SStructSolver](#) solver)
- HYPRE\_Int [HYPRE\\_SStructSplitSetStructSolver](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Int ssolver)
- HYPRE\_Int [HYPRE\\_SStructSplitGetNumIterations](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_Int \*num\_↵ iterations)
- HYPRE\_Int [HYPRE\\_SStructSplitGetFinalRelativeResidualNorm](#) ([HYPRE\\_SStructSolver](#) solver, HYPRE\_↵ Real \*norm)

## 4.6 HYPRE\_sstruct\_mv.h File Reference

### SStruct Grids

- #define [HYPRE\\_SSTRUCT\\_VARIABLE\\_UNDEFINED](#) -1
- #define [HYPRE\\_SSTRUCT\\_VARIABLE\\_CELL](#) 0
- #define [HYPRE\\_SSTRUCT\\_VARIABLE\\_NODE](#) 1
- #define [HYPRE\\_SSTRUCT\\_VARIABLE\\_XFACE](#) 2
- #define [HYPRE\\_SSTRUCT\\_VARIABLE\\_YFACE](#) 3
- #define [HYPRE\\_SSTRUCT\\_VARIABLE\\_ZFACE](#) 4
- #define [HYPRE\\_SSTRUCT\\_VARIABLE\\_XEDGE](#) 5
- #define [HYPRE\\_SSTRUCT\\_VARIABLE\\_YEDGE](#) 6
- #define [HYPRE\\_SSTRUCT\\_VARIABLE\\_ZEDGE](#) 7
- typedef struct hypre\_SStructGrid\_struct \* [HYPRE\\_SStructGrid](#)
- typedef HYPRE\_Int [HYPRE\\_SStructVariable](#)
- HYPRE\_Int [HYPRE\\_SStructGridCreate](#) (MPI\_Comm comm, HYPRE\_Int ndim, HYPRE\_Int nparts, [HYPRE\\_SStructGrid](#) \*grid)
- HYPRE\_Int [HYPRE\\_SStructGridDestroy](#) ([HYPRE\\_SStructGrid](#) grid)
- HYPRE\_Int [HYPRE\\_SStructGridSetExtents](#) ([HYPRE\\_SStructGrid](#) grid, HYPRE\_Int part, HYPRE\_Int \*ilower, HYPRE\_Int \*iupper)
- HYPRE\_Int [HYPRE\\_SStructGridSetVariables](#) ([HYPRE\\_SStructGrid](#) grid, HYPRE\_Int part, HYPRE\_Int nvars, [HYPRE\\_SStructVariable](#) \*vartypes)
- HYPRE\_Int [HYPRE\\_SStructGridAddVariables](#) ([HYPRE\\_SStructGrid](#) grid, HYPRE\_Int part, HYPRE\_Int \*index, HYPRE\_Int nvars, [HYPRE\\_SStructVariable](#) \*vartypes)
- HYPRE\_Int [HYPRE\\_SStructGridSetFEMOrdering](#) ([HYPRE\\_SStructGrid](#) grid, HYPRE\_Int part, HYPRE\_Int \*ordering)
- HYPRE\_Int [HYPRE\\_SStructGridSetNeighborPart](#) ([HYPRE\\_SStructGrid](#) grid, HYPRE\_Int part, HYPRE\_Int \*ilower, HYPRE\_Int \*iupper, HYPRE\_Int nbor\_part, HYPRE\_Int \*nbor\_ilower, HYPRE\_Int \*nbor\_iupper, HYPRE\_Int \*index\_map, HYPRE\_Int \*index\_dir)
- HYPRE\_Int [HYPRE\\_SStructGridSetSharedPart](#) ([HYPRE\\_SStructGrid](#) grid, HYPRE\_Int part, HYPRE\_Int \*ilower, HYPRE\_Int \*iupper, HYPRE\_Int \*offset, HYPRE\_Int shared\_part, HYPRE\_Int \*shared\_ilower, HYPRE\_Int \*shared\_iupper, HYPRE\_Int \*shared\_offset, HYPRE\_Int \*index\_map, HYPRE\_Int \*index\_dir)
- HYPRE\_Int [HYPRE\\_SStructGridAddUnstructuredPart](#) ([HYPRE\\_SStructGrid](#) grid, HYPRE\_Int ilower, HYPRE\_Int iupper)
- HYPRE\_Int [HYPRE\\_SStructGridAssemble](#) ([HYPRE\\_SStructGrid](#) grid)
- HYPRE\_Int [HYPRE\\_SStructGridSetPeriodic](#) ([HYPRE\\_SStructGrid](#) grid, HYPRE\_Int part, HYPRE\_Int \*periodic)
- HYPRE\_Int [HYPRE\\_SStructGridSetNumGhost](#) ([HYPRE\\_SStructGrid](#) grid, HYPRE\_Int \*num\_ghost)

### SStruct Stencils

- typedef struct hypre\_SStructStencil\_struct \* [HYPRE\\_SStructStencil](#)
- HYPRE\_Int [HYPRE\\_SStructStencilCreate](#) (HYPRE\_Int ndim, HYPRE\_Int size, [HYPRE\\_SStructStencil](#) \*stencil)
- HYPRE\_Int [HYPRE\\_SStructStencilDestroy](#) ([HYPRE\\_SStructStencil](#) stencil)
- HYPRE\_Int [HYPRE\\_SStructStencilSetEntry](#) ([HYPRE\\_SStructStencil](#) stencil, HYPRE\_Int entry, HYPRE\_Int \*offset, HYPRE\_Int var)

## SStruct Graphs

- typedef struct hypre\_SStructGraph\_struct \* [HYPRE\\_SStructGraph](#)
- HYPRE\_Int [HYPRE\\_SStructGraphCreate](#) (MPI\_Comm comm, [HYPRE\\_SStructGrid](#) grid, [HYPRE\\_SStructGraph](#) \*graph)
- HYPRE\_Int [HYPRE\\_SStructGraphDestroy](#) ([HYPRE\\_SStructGraph](#) graph)
- HYPRE\_Int [HYPRE\\_SStructGraphSetDomainGrid](#) ([HYPRE\\_SStructGraph](#) graph, [HYPRE\\_SStructGrid](#) domain\_grid)
- HYPRE\_Int [HYPRE\\_SStructGraphSetStencil](#) ([HYPRE\\_SStructGraph](#) graph, HYPRE\_Int part, HYPRE\_Int var, [HYPRE\\_SStructStencil](#) stencil)
- HYPRE\_Int [HYPRE\\_SStructGraphSetFEM](#) ([HYPRE\\_SStructGraph](#) graph, HYPRE\_Int part)
- HYPRE\_Int [HYPRE\\_SStructGraphSetFEMSparsity](#) ([HYPRE\\_SStructGraph](#) graph, HYPRE\_Int part, HYPRE\_Int nsparse, HYPRE\_Int \*sparsity)
- HYPRE\_Int [HYPRE\\_SStructGraphAddEntries](#) ([HYPRE\\_SStructGraph](#) graph, HYPRE\_Int part, HYPRE\_Int \*index, HYPRE\_Int var, HYPRE\_Int to\_part, HYPRE\_Int \*to\_index, HYPRE\_Int to\_var)
- HYPRE\_Int [HYPRE\\_SStructGraphAssemble](#) ([HYPRE\\_SStructGraph](#) graph)
- HYPRE\_Int [HYPRE\\_SStructGraphSetObjectType](#) ([HYPRE\\_SStructGraph](#) graph, HYPRE\_Int type)

## SStruct Matrices

- typedef struct hypre\_SStructMatrix\_struct \* [HYPRE\\_SStructMatrix](#)
- HYPRE\_Int [HYPRE\\_SStructMatrixCreate](#) (MPI\_Comm comm, [HYPRE\\_SStructGraph](#) graph, [HYPRE\\_SStructMatrix](#) \*matrix)
- HYPRE\_Int [HYPRE\\_SStructMatrixDestroy](#) ([HYPRE\\_SStructMatrix](#) matrix)
- HYPRE\_Int [HYPRE\\_SStructMatrixInitialize](#) ([HYPRE\\_SStructMatrix](#) matrix)
- HYPRE\_Int [HYPRE\\_SStructMatrixSetValues](#) ([HYPRE\\_SStructMatrix](#) matrix, HYPRE\_Int part, HYPRE\_Int \*index, HYPRE\_Int var, HYPRE\_Int nentries, HYPRE\_Int \*entries, HYPRE\_Complex \*values)
- HYPRE\_Int [HYPRE\\_SStructMatrixAddToValues](#) ([HYPRE\\_SStructMatrix](#) matrix, HYPRE\_Int part, HYPRE\_Int \*index, HYPRE\_Int var, HYPRE\_Int nentries, HYPRE\_Int \*entries, HYPRE\_Complex \*values)
- HYPRE\_Int [HYPRE\\_SStructMatrixAddFEMValues](#) ([HYPRE\\_SStructMatrix](#) matrix, HYPRE\_Int part, HYPRE\_Int \*index, HYPRE\_Complex \*values)
- HYPRE\_Int [HYPRE\\_SStructMatrixGetValues](#) ([HYPRE\\_SStructMatrix](#) matrix, HYPRE\_Int part, HYPRE\_Int \*index, HYPRE\_Int var, HYPRE\_Int nentries, HYPRE\_Int \*entries, HYPRE\_Complex \*values)
- HYPRE\_Int [HYPRE\\_SStructMatrixGetFEMValues](#) ([HYPRE\\_SStructMatrix](#) matrix, HYPRE\_Int part, HYPRE\_Int \*index, HYPRE\_Complex \*values)
- HYPRE\_Int [HYPRE\\_SStructMatrixSetBoxValues](#) ([HYPRE\\_SStructMatrix](#) matrix, HYPRE\_Int part, HYPRE\_Int \*ilower, HYPRE\_Int \*iupper, HYPRE\_Int var, HYPRE\_Int nentries, HYPRE\_Int \*entries, HYPRE\_Complex \*values)
- HYPRE\_Int [HYPRE\\_SStructMatrixAddToBoxValues](#) ([HYPRE\\_SStructMatrix](#) matrix, HYPRE\_Int part, HYPRE\_Int \*ilower, HYPRE\_Int \*iupper, HYPRE\_Int var, HYPRE\_Int nentries, HYPRE\_Int \*entries, HYPRE\_Complex \*values)
- HYPRE\_Int [HYPRE\\_SStructMatrixSetBoxValues2](#) ([HYPRE\\_SStructMatrix](#) matrix, HYPRE\_Int part, HYPRE\_Int \*ilower, HYPRE\_Int \*iupper, HYPRE\_Int var, HYPRE\_Int nentries, HYPRE\_Int \*entries, HYPRE\_Int \*vilower, HYPRE\_Int \*viupper, HYPRE\_Complex \*values)
- HYPRE\_Int [HYPRE\\_SStructMatrixAddToBoxValues2](#) ([HYPRE\\_SStructMatrix](#) matrix, HYPRE\_Int part, HYPRE\_Int \*ilower, HYPRE\_Int \*iupper, HYPRE\_Int var, HYPRE\_Int nentries, HYPRE\_Int \*entries, HYPRE\_Int \*vilower, HYPRE\_Int \*viupper, HYPRE\_Complex \*values)
- HYPRE\_Int [HYPRE\\_SStructMatrixAssemble](#) ([HYPRE\\_SStructMatrix](#) matrix)
- HYPRE\_Int [HYPRE\\_SStructMatrixGetBoxValues](#) ([HYPRE\\_SStructMatrix](#) matrix, HYPRE\_Int part, HYPRE\_Int \*ilower, HYPRE\_Int \*iupper, HYPRE\_Int var, HYPRE\_Int nentries, HYPRE\_Int \*entries, HYPRE\_Complex \*values)
- HYPRE\_Int [HYPRE\\_SStructMatrixGetBoxValues2](#) ([HYPRE\\_SStructMatrix](#) matrix, HYPRE\_Int part, HYPRE\_Int \*ilower, HYPRE\_Int \*iupper, HYPRE\_Int var, HYPRE\_Int nentries, HYPRE\_Int \*entries, HYPRE\_Int \*vilower, HYPRE\_Int \*viupper, HYPRE\_Complex \*values)
- HYPRE\_Int [HYPRE\\_SStructMatrixSetSymmetric](#) ([HYPRE\\_SStructMatrix](#) matrix, HYPRE\_Int part, HYPRE\_Int var, HYPRE\_Int to\_var, HYPRE\_Int symmetric)



- HYPRE\_Int [HYPRE\\_SStructMatrixSetNSSymmetric](#) (HYPRE\_SStructMatrix matrix, HYPRE\_Int symmetric)
- HYPRE\_Int [HYPRE\\_SStructMatrixSetObjectType](#) (HYPRE\_SStructMatrix matrix, HYPRE\_Int type)
- HYPRE\_Int [HYPRE\\_SStructMatrixGetObject](#) (HYPRE\_SStructMatrix matrix, void \*\*object)
- HYPRE\_Int [HYPRE\\_SStructMatrixPrint](#) (const char \*filename, HYPRE\_SStructMatrix matrix, HYPRE\_Int all)

## SStruct Vectors

- typedef struct hypre\_SStructVector\_struct \* [HYPRE\\_SStructVector](#)
- HYPRE\_Int [HYPRE\\_SStructVectorCreate](#) (MPI\_Comm comm, HYPRE\_SStructGrid grid, HYPRE\_SStructVector \*vector)
- HYPRE\_Int [HYPRE\\_SStructVectorDestroy](#) (HYPRE\_SStructVector vector)
- HYPRE\_Int [HYPRE\\_SStructVectorInitialize](#) (HYPRE\_SStructVector vector)
- HYPRE\_Int [HYPRE\\_SStructVectorSetValues](#) (HYPRE\_SStructVector vector, HYPRE\_Int part, HYPRE\_Int \*index, HYPRE\_Int var, HYPRE\_Complex \*value)
- HYPRE\_Int [HYPRE\\_SStructVectorAddToValues](#) (HYPRE\_SStructVector vector, HYPRE\_Int part, HYPRE\_Int \*index, HYPRE\_Int var, HYPRE\_Complex \*value)
- HYPRE\_Int [HYPRE\\_SStructVectorAddFEMValues](#) (HYPRE\_SStructVector vector, HYPRE\_Int part, HYPRE\_Int \*index, HYPRE\_Complex \*values)
- HYPRE\_Int [HYPRE\\_SStructVectorGetValues](#) (HYPRE\_SStructVector vector, HYPRE\_Int part, HYPRE\_Int \*index, HYPRE\_Int var, HYPRE\_Complex \*value)
- HYPRE\_Int [HYPRE\\_SStructVectorGetFEMValues](#) (HYPRE\_SStructVector vector, HYPRE\_Int part, HYPRE\_Int \*index, HYPRE\_Complex \*values)
- HYPRE\_Int [HYPRE\\_SStructVectorSetBoxValues](#) (HYPRE\_SStructVector vector, HYPRE\_Int part, HYPRE\_Int \*ilower, HYPRE\_Int \*iupper, HYPRE\_Int var, HYPRE\_Complex \*values)
- HYPRE\_Int [HYPRE\\_SStructVectorAddToBoxValues](#) (HYPRE\_SStructVector vector, HYPRE\_Int part, HYPRE\_Int \*ilower, HYPRE\_Int \*iupper, HYPRE\_Int var, HYPRE\_Complex \*values)
- HYPRE\_Int [HYPRE\\_SStructVectorSetBoxValues2](#) (HYPRE\_SStructVector vector, HYPRE\_Int part, HYPRE\_Int \*ilower, HYPRE\_Int \*iupper, HYPRE\_Int var, HYPRE\_Int \*vilower, HYPRE\_Int \*viupper, HYPRE\_Complex \*values)
- HYPRE\_Int [HYPRE\\_SStructVectorAddToBoxValues2](#) (HYPRE\_SStructVector vector, HYPRE\_Int part, HYPRE\_Int \*ilower, HYPRE\_Int \*iupper, HYPRE\_Int var, HYPRE\_Int \*vilower, HYPRE\_Int \*viupper, HYPRE\_Complex \*values)
- HYPRE\_Int [HYPRE\\_SStructVectorAssemble](#) (HYPRE\_SStructVector vector)
- HYPRE\_Int [HYPRE\\_SStructVectorGetBoxValues](#) (HYPRE\_SStructVector vector, HYPRE\_Int part, HYPRE\_Int \*ilower, HYPRE\_Int \*iupper, HYPRE\_Int var, HYPRE\_Complex \*values)
- HYPRE\_Int [HYPRE\\_SStructVectorGetBoxValues2](#) (HYPRE\_SStructVector vector, HYPRE\_Int part, HYPRE\_Int \*ilower, HYPRE\_Int \*iupper, HYPRE\_Int var, HYPRE\_Int \*vilower, HYPRE\_Int \*viupper, HYPRE\_Complex \*values)
- HYPRE\_Int [HYPRE\\_SStructVectorGather](#) (HYPRE\_SStructVector vector)
- HYPRE\_Int [HYPRE\\_SStructVectorSetObjectType](#) (HYPRE\_SStructVector vector, HYPRE\_Int type)
- HYPRE\_Int [HYPRE\\_SStructVectorGetObject](#) (HYPRE\_SStructVector vector, void \*\*object)
- HYPRE\_Int [HYPRE\\_SStructVectorPrint](#) (const char \*filename, HYPRE\_SStructVector vector, HYPRE\_Int all)

## 4.7 HYPRE\_struct\_ls.h File Reference

### Functions

- HYPRE\_Int [HYPRE\\_StructSparseMSGCreate](#) (MPI\_Comm comm, HYPRE\_StructSolver \*solver)
- HYPRE\_Int [HYPRE\\_StructSparseMSGDestroy](#) (HYPRE\_StructSolver solver)
- HYPRE\_Int [HYPRE\\_StructSparseMSGSetup](#) (HYPRE\_StructSolver solver, HYPRE\_StructMatrix A, HYPRE\_StructVector b, HYPRE\_StructVector x)
- HYPRE\_Int [HYPRE\\_StructSparseMSGSolve](#) (HYPRE\_StructSolver solver, HYPRE\_StructMatrix A, HYPRE\_StructVector b, HYPRE\_StructVector x)

- HYPRE\_Int [HYPRE\\_StructSparseMSGSetTol](#) (HYPRE\_StructSolver solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_StructSparseMSGSetMaxIter](#) (HYPRE\_StructSolver solver, HYPRE\_Int max\_iter)
- HYPRE\_Int [HYPRE\\_StructSparseMSGSetJump](#) (HYPRE\_StructSolver solver, HYPRE\_Int jump)
- HYPRE\_Int [HYPRE\\_StructSparseMSGSetRelChange](#) (HYPRE\_StructSolver solver, HYPRE\_Int rel\_change)
- HYPRE\_Int [HYPRE\\_StructSparseMSGSetZeroGuess](#) (HYPRE\_StructSolver solver)
- HYPRE\_Int [HYPRE\\_StructSparseMSGSetNonZeroGuess](#) (HYPRE\_StructSolver solver)
- HYPRE\_Int [HYPRE\\_StructSparseMSGSetRelaxType](#) (HYPRE\_StructSolver solver, HYPRE\_Int relax\_type)
- HYPRE\_Int [HYPRE\\_StructSparseMSGSetJacobiWeight](#) (HYPRE\_StructSolver solver, HYPRE\_Real weight)
- HYPRE\_Int [HYPRE\\_StructSparseMSGSetNumPreRelax](#) (HYPRE\_StructSolver solver, HYPRE\_Int num\_↵  
pre\_relax)
- HYPRE\_Int [HYPRE\\_StructSparseMSGSetNumPostRelax](#) (HYPRE\_StructSolver solver, HYPRE\_Int num\_↵  
post\_relax)
- HYPRE\_Int [HYPRE\\_StructSparseMSGSetNumFineRelax](#) (HYPRE\_StructSolver solver, HYPRE\_Int num\_↵  
fine\_relax)
- HYPRE\_Int [HYPRE\\_StructSparseMSGSetLogging](#) (HYPRE\_StructSolver solver, HYPRE\_Int logging)
- HYPRE\_Int [HYPRE\\_StructSparseMSGSetPrintLevel](#) (HYPRE\_StructSolver solver, HYPRE\_Int print\_level)
- HYPRE\_Int [HYPRE\\_StructSparseMSGGetNumIterations](#) (HYPRE\_StructSolver solver, HYPRE\_Int \*num\_↵  
\_iterations)
- HYPRE\_Int [HYPRE\\_StructSparseMSGGetFinalRelativeResidualNorm](#) (HYPRE\_StructSolver solver,  
HYPRE\_Real \*norm)

### Struct Jacobi Solver

- HYPRE\_Int [HYPRE\\_StructJacobiCreate](#) (MPI\_Comm comm, HYPRE\_StructSolver \*solver)
- HYPRE\_Int [HYPRE\\_StructJacobiDestroy](#) (HYPRE\_StructSolver solver)
- HYPRE\_Int [HYPRE\\_StructJacobiSetup](#) (HYPRE\_StructSolver solver, HYPRE\_StructMatrix A, HYPRE\_StructVector  
b, HYPRE\_StructVector x)
- HYPRE\_Int [HYPRE\\_StructJacobiSolve](#) (HYPRE\_StructSolver solver, HYPRE\_StructMatrix A, HYPRE\_StructVector  
b, HYPRE\_StructVector x)
- HYPRE\_Int [HYPRE\\_StructJacobiSetTol](#) (HYPRE\_StructSolver solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_StructJacobiGetTol](#) (HYPRE\_StructSolver solver, HYPRE\_Real \*tol)
- HYPRE\_Int [HYPRE\\_StructJacobiSetMaxIter](#) (HYPRE\_StructSolver solver, HYPRE\_Int max\_iter)
- HYPRE\_Int [HYPRE\\_StructJacobiGetMaxIter](#) (HYPRE\_StructSolver solver, HYPRE\_Int \*max\_iter)
- HYPRE\_Int [HYPRE\\_StructJacobiSetZeroGuess](#) (HYPRE\_StructSolver solver)
- HYPRE\_Int [HYPRE\\_StructJacobiGetZeroGuess](#) (HYPRE\_StructSolver solver, HYPRE\_Int \*zeroguess)
- HYPRE\_Int [HYPRE\\_StructJacobiSetNonZeroGuess](#) (HYPRE\_StructSolver solver)
- HYPRE\_Int [HYPRE\\_StructJacobiGetNumIterations](#) (HYPRE\_StructSolver solver, HYPRE\_Int \*num\_↵  
iterations)
- HYPRE\_Int [HYPRE\\_StructJacobiGetFinalRelativeResidualNorm](#) (HYPRE\_StructSolver solver, HYPRE\_↵  
\_Real \*norm)

### Struct PFMG Solver

PFMG is a semicoarsening multigrid solver that uses pointwise relaxation. For periodic problems, users should try to set the grid size in periodic dimensions to be as close to a power-of-two as possible. That is, if the grid size in a periodic dimension is given by  $N = 2^m * M$  where  $M$  is not a power-of-two, then  $M$  should be as small as possible. Large values of  $M$  will generally result in slower convergence rates.

- HYPRE\_Int [HYPRE\\_StructPFMGCreate](#) (MPI\_Comm comm, HYPRE\_StructSolver \*solver)
- HYPRE\_Int [HYPRE\\_StructPFMGDestroy](#) (HYPRE\_StructSolver solver)
- HYPRE\_Int [HYPRE\\_StructPFMGSetup](#) (HYPRE\_StructSolver solver, HYPRE\_StructMatrix A, HYPRE\_StructVector  
b, HYPRE\_StructVector x)
- HYPRE\_Int [HYPRE\\_StructPFMGsolve](#) (HYPRE\_StructSolver solver, HYPRE\_StructMatrix A, HYPRE\_StructVector  
b, HYPRE\_StructVector x)
- HYPRE\_Int [HYPRE\\_StructPFMGSetTol](#) (HYPRE\_StructSolver solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_StructPFMGGetTol](#) (HYPRE\_StructSolver solver, HYPRE\_Real \*tol)
- HYPRE\_Int [HYPRE\\_StructPFMGSetMaxIter](#) (HYPRE\_StructSolver solver, HYPRE\_Int max\_iter)
- HYPRE\_Int [HYPRE\\_StructPFMGGetMaxIter](#) (HYPRE\_StructSolver solver, HYPRE\_Int \*max\_iter)
- HYPRE\_Int [HYPRE\\_StructPFMGSetMaxLevels](#) (HYPRE\_StructSolver solver, HYPRE\_Int max\_levels)



- HYPRE\_Int HYPRE\_StructPFMGGetMaxLevels (HYPRE\_StructSolver solver, HYPRE\_Int \*max\_levels)
- HYPRE\_Int HYPRE\_StructPFMGSetRelChange (HYPRE\_StructSolver solver, HYPRE\_Int rel\_change)
- HYPRE\_Int HYPRE\_StructPFMGGetRelChange (HYPRE\_StructSolver solver, HYPRE\_Int \*rel\_change)
- HYPRE\_Int HYPRE\_StructPFMGSetZeroGuess (HYPRE\_StructSolver solver)
- HYPRE\_Int HYPRE\_StructPFMGGetZeroGuess (HYPRE\_StructSolver solver, HYPRE\_Int \*zeroguess)
- HYPRE\_Int HYPRE\_StructPFMGSetNonZeroGuess (HYPRE\_StructSolver solver)
- HYPRE\_Int HYPRE\_StructPFMGSetRelaxType (HYPRE\_StructSolver solver, HYPRE\_Int relax\_type)
- HYPRE\_Int HYPRE\_StructPFMGGetRelaxType (HYPRE\_StructSolver solver, HYPRE\_Int \*relax\_type)
- HYPRE\_Int HYPRE\_StructPFMGSetJacobiWeight (HYPRE\_StructSolver solver, HYPRE\_Real weight)
- HYPRE\_Int HYPRE\_StructPFMGGetJacobiWeight (HYPRE\_StructSolver solver, HYPRE\_Real \*weight)
- HYPRE\_Int HYPRE\_StructPFMGSetRAPType (HYPRE\_StructSolver solver, HYPRE\_Int rap\_type)
- HYPRE\_Int HYPRE\_StructPFMGGetRAPType (HYPRE\_StructSolver solver, HYPRE\_Int \*rap\_type)
- HYPRE\_Int HYPRE\_StructPFMGSetNumPreRelax (HYPRE\_StructSolver solver, HYPRE\_Int num\_pre↵\_relax)
- HYPRE\_Int HYPRE\_StructPFMGGetNumPreRelax (HYPRE\_StructSolver solver, HYPRE\_Int \*num\_↵pre\_relax)
- HYPRE\_Int HYPRE\_StructPFMGSetNumPostRelax (HYPRE\_StructSolver solver, HYPRE\_Int num\_↵post\_relax)
- HYPRE\_Int HYPRE\_StructPFMGGetNumPostRelax (HYPRE\_StructSolver solver, HYPRE\_Int \*num\_↵post\_relax)
- HYPRE\_Int HYPRE\_StructPFMGSetSkipRelax (HYPRE\_StructSolver solver, HYPRE\_Int skip\_relax)
- HYPRE\_Int HYPRE\_StructPFMGGetSkipRelax (HYPRE\_StructSolver solver, HYPRE\_Int \*skip\_relax)
- HYPRE\_Int HYPRE\_StructPFMGSetDxyz (HYPRE\_StructSolver solver, HYPRE\_Real \*dxyz)
- HYPRE\_Int HYPRE\_StructPFMGSetLogging (HYPRE\_StructSolver solver, HYPRE\_Int logging)
- HYPRE\_Int HYPRE\_StructPFMGGetLogging (HYPRE\_StructSolver solver, HYPRE\_Int \*logging)
- HYPRE\_Int HYPRE\_StructPFMGSetPrintLevel (HYPRE\_StructSolver solver, HYPRE\_Int print\_level)
- HYPRE\_Int HYPRE\_StructPFMGGetPrintLevel (HYPRE\_StructSolver solver, HYPRE\_Int \*print\_level)
- HYPRE\_Int HYPRE\_StructPFMGGetNumIterations (HYPRE\_StructSolver solver, HYPRE\_Int \*num\_↵iterations)
- HYPRE\_Int HYPRE\_StructPFMGGetFinalRelativeResidualNorm (HYPRE\_StructSolver solver, HYPRE\_↵Real \*norm)

### Struct SMG Solver

SMG is a semicoarsening multigrid solver that uses plane smoothing (in 3D). The plane smoother calls a 2D SMG algorithm with line smoothing, and the line smoother is cyclic reduction (1D SMG). For periodic problems, the grid size in periodic dimensions currently must be a power-of-two.

- HYPRE\_Int HYPRE\_StructSMGCreate (MPI\_Comm comm, HYPRE\_StructSolver \*solver)
- HYPRE\_Int HYPRE\_StructSMGDestroy (HYPRE\_StructSolver solver)
- HYPRE\_Int HYPRE\_StructSMGSetup (HYPRE\_StructSolver solver, HYPRE\_StructMatrix A, HYPRE\_StructVector b, HYPRE\_StructVector x)
- HYPRE\_Int HYPRE\_StructSMGSolve (HYPRE\_StructSolver solver, HYPRE\_StructMatrix A, HYPRE\_StructVector b, HYPRE\_StructVector x)
- HYPRE\_Int HYPRE\_StructSMGSetMemoryUse (HYPRE\_StructSolver solver, HYPRE\_Int memory\_use)
- HYPRE\_Int HYPRE\_StructSMGGetMemoryUse (HYPRE\_StructSolver solver, HYPRE\_Int \*memory\_↵use)
- HYPRE\_Int HYPRE\_StructSMGSetTol (HYPRE\_StructSolver solver, HYPRE\_Real tol)
- HYPRE\_Int HYPRE\_StructSMGGetTol (HYPRE\_StructSolver solver, HYPRE\_Real \*tol)
- HYPRE\_Int HYPRE\_StructSMGSetMaxIter (HYPRE\_StructSolver solver, HYPRE\_Int max\_iter)
- HYPRE\_Int HYPRE\_StructSMGGetMaxIter (HYPRE\_StructSolver solver, HYPRE\_Int \*max\_iter)
- HYPRE\_Int HYPRE\_StructSMGSetRelChange (HYPRE\_StructSolver solver, HYPRE\_Int rel\_change)
- HYPRE\_Int HYPRE\_StructSMGGetRelChange (HYPRE\_StructSolver solver, HYPRE\_Int \*rel\_change)
- HYPRE\_Int HYPRE\_StructSMGSetZeroGuess (HYPRE\_StructSolver solver)
- HYPRE\_Int HYPRE\_StructSMGGetZeroGuess (HYPRE\_StructSolver solver, HYPRE\_Int \*zeroguess)
- HYPRE\_Int HYPRE\_StructSMGSetNonZeroGuess (HYPRE\_StructSolver solver)
- HYPRE\_Int HYPRE\_StructSMGSetNumPreRelax (HYPRE\_StructSolver solver, HYPRE\_Int num\_pre↵relax)
- HYPRE\_Int HYPRE\_StructSMGGetNumPreRelax (HYPRE\_StructSolver solver, HYPRE\_Int \*num\_pre↵\_relax)
- HYPRE\_Int HYPRE\_StructSMGSetNumPostRelax (HYPRE\_StructSolver solver, HYPRE\_Int num\_post↵\_relax)

- HYPRE\_Int [HYPRE\\_StructSMGGetNumPostRelax](#) (HYPRE\_StructSolver solver, HYPRE\_Int \*num\_↵ post\_relax)
- HYPRE\_Int [HYPRE\\_StructSMGSetLogging](#) (HYPRE\_StructSolver solver, HYPRE\_Int logging)
- HYPRE\_Int [HYPRE\\_StructSMGGetLogging](#) (HYPRE\_StructSolver solver, HYPRE\_Int \*logging)
- HYPRE\_Int [HYPRE\\_StructSMGSetPrintLevel](#) (HYPRE\_StructSolver solver, HYPRE\_Int print\_level)
- HYPRE\_Int [HYPRE\\_StructSMGGetPrintLevel](#) (HYPRE\_StructSolver solver, HYPRE\_Int \*print\_level)
- HYPRE\_Int [HYPRE\\_StructSMGGetNumIterations](#) (HYPRE\_StructSolver solver, HYPRE\_Int \*num\_↵ iterations)
- HYPRE\_Int [HYPRE\\_StructSMGGetFinalRelativeResidualNorm](#) (HYPRE\_StructSolver solver, HYPRE\_↵ Real \*norm)

### Struct CycRed Solver

*CycRed is a cyclic reduction solver that simultaneously solves a collection of 1D tridiagonal systems embedded in a d-dimensional grid.*

- HYPRE\_Int [HYPRE\\_StructCycRedCreate](#) (MPI\_Comm comm, HYPRE\_StructSolver \*solver)
- HYPRE\_Int [HYPRE\\_StructCycRedDestroy](#) (HYPRE\_StructSolver solver)
- HYPRE\_Int [HYPRE\\_StructCycRedSetup](#) (HYPRE\_StructSolver solver, HYPRE\_StructMatrix A, HYPRE\_StructVector b, HYPRE\_StructVector x)
- HYPRE\_Int [HYPRE\\_StructCycRedSolve](#) (HYPRE\_StructSolver solver, HYPRE\_StructMatrix A, HYPRE\_StructVector b, HYPRE\_StructVector x)
- HYPRE\_Int [HYPRE\\_StructCycRedSetTDim](#) (HYPRE\_StructSolver solver, HYPRE\_Int tdim)
- HYPRE\_Int [HYPRE\\_StructCycRedSetBase](#) (HYPRE\_StructSolver solver, HYPRE\_Int ndim, HYPRE\_Int \*base\_index, HYPRE\_Int \*base\_stride)

### Struct PCG Solver

*These routines should be used in conjunction with the generic interface in [Krylov Solvers](#).*

- HYPRE\_Int [HYPRE\\_StructPCGCreate](#) (MPI\_Comm comm, HYPRE\_StructSolver \*solver)
- HYPRE\_Int [HYPRE\\_StructPCGDestroy](#) (HYPRE\_StructSolver solver)
- HYPRE\_Int [HYPRE\\_StructPCGSetup](#) (HYPRE\_StructSolver solver, HYPRE\_StructMatrix A, HYPRE\_StructVector b, HYPRE\_StructVector x)
- HYPRE\_Int [HYPRE\\_StructPCGSolve](#) (HYPRE\_StructSolver solver, HYPRE\_StructMatrix A, HYPRE\_StructVector b, HYPRE\_StructVector x)
- HYPRE\_Int [HYPRE\\_StructPCGSetTol](#) (HYPRE\_StructSolver solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_StructPCGSetAbsoluteTol](#) (HYPRE\_StructSolver solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_StructPCGSetMaxIter](#) (HYPRE\_StructSolver solver, HYPRE\_Int max\_iter)
- HYPRE\_Int [HYPRE\\_StructPCGSetTwoNorm](#) (HYPRE\_StructSolver solver, HYPRE\_Int two\_norm)
- HYPRE\_Int [HYPRE\\_StructPCGSetRelChange](#) (HYPRE\_StructSolver solver, HYPRE\_Int rel\_change)
- HYPRE\_Int [HYPRE\\_StructPCGSetPrecond](#) (HYPRE\_StructSolver solver, HYPRE\_PtrToStructSolverFcn precondition, HYPRE\_PtrToStructSolverFcn precondition\_setup, HYPRE\_StructSolver precondition\_solver)
- HYPRE\_Int [HYPRE\\_StructPCGSetLogging](#) (HYPRE\_StructSolver solver, HYPRE\_Int logging)
- HYPRE\_Int [HYPRE\\_StructPCGSetPrintLevel](#) (HYPRE\_StructSolver solver, HYPRE\_Int level)
- HYPRE\_Int [HYPRE\\_StructPCGGetNumIterations](#) (HYPRE\_StructSolver solver, HYPRE\_Int \*num\_↵ iterations)
- HYPRE\_Int [HYPRE\\_StructPCGGetFinalRelativeResidualNorm](#) (HYPRE\_StructSolver solver, HYPRE\_↵ Real \*norm)
- HYPRE\_Int [HYPRE\\_StructPCGGetResidual](#) (HYPRE\_StructSolver solver, void \*\*residual)
- HYPRE\_Int [HYPRE\\_StructDiagScaleSetup](#) (HYPRE\_StructSolver solver, HYPRE\_StructMatrix A, HYPRE\_StructVector y, HYPRE\_StructVector x)
- HYPRE\_Int [HYPRE\\_StructDiagScale](#) (HYPRE\_StructSolver solver, HYPRE\_StructMatrix HA, HYPRE\_StructVector Hy, HYPRE\_StructVector Hx)

### Struct GMRES Solver

*These routines should be used in conjunction with the generic interface in [Krylov Solvers](#).*

- HYPRE\_Int [HYPRE\\_StructGMRESCreate](#) (MPI\_Comm comm, HYPRE\_StructSolver \*solver)
- HYPRE\_Int [HYPRE\\_StructGMRESDestroy](#) (HYPRE\_StructSolver solver)

- HYPRE\_Int HYPRE\_StructGMRESSetup (HYPRE\_StructSolver solver, HYPRE\_StructMatrix A, HYPRE\_StructVector b, HYPRE\_StructVector x)
- HYPRE\_Int HYPRE\_StructGMRESSolve (HYPRE\_StructSolver solver, HYPRE\_StructMatrix A, HYPRE\_StructVector b, HYPRE\_StructVector x)
- HYPRE\_Int HYPRE\_StructGMRESSetTol (HYPRE\_StructSolver solver, HYPRE\_Real tol)
- HYPRE\_Int HYPRE\_StructGMRESSetAbsoluteTol (HYPRE\_StructSolver solver, HYPRE\_Real tol)
- HYPRE\_Int HYPRE\_StructGMRESSetMaxIter (HYPRE\_StructSolver solver, HYPRE\_Int max\_iter)
- HYPRE\_Int HYPRE\_StructGMRESSetKDim (HYPRE\_StructSolver solver, HYPRE\_Int k\_dim)
- HYPRE\_Int HYPRE\_StructGMRESSetPrecond (HYPRE\_StructSolver solver, HYPRE\_PtrToStructSolverFcn precondition, HYPRE\_PtrToStructSolverFcn precondition\_setup, HYPRE\_StructSolver precondition\_solver)
- HYPRE\_Int HYPRE\_StructGMRESSetLogging (HYPRE\_StructSolver solver, HYPRE\_Int logging)
- HYPRE\_Int HYPRE\_StructGMRESSetPrintLevel (HYPRE\_StructSolver solver, HYPRE\_Int level)
- HYPRE\_Int HYPRE\_StructGMRESGetNumIterations (HYPRE\_StructSolver solver, HYPRE\_Int \*num\_↵ iterations)
- HYPRE\_Int HYPRE\_StructGMRESGetFinalRelativeResidualNorm (HYPRE\_StructSolver solver, HYPRE\_Real \*norm)
- HYPRE\_Int HYPRE\_StructGMRESGetResidual (HYPRE\_StructSolver solver, void \*\*residual)

### Struct FlexGMRES Solver

These routines should be used in conjunction with the generic interface in [Krylov Solvers](#).

- HYPRE\_Int HYPRE\_StructFlexGMRESCreate (MPI\_Comm comm, HYPRE\_StructSolver \*solver)
- HYPRE\_Int HYPRE\_StructFlexGMRESDestroy (HYPRE\_StructSolver solver)
- HYPRE\_Int HYPRE\_StructFlexGMRESSetup (HYPRE\_StructSolver solver, HYPRE\_StructMatrix A, HYPRE\_StructVector b, HYPRE\_StructVector x)
- HYPRE\_Int HYPRE\_StructFlexGMRESSolve (HYPRE\_StructSolver solver, HYPRE\_StructMatrix A, HYPRE\_StructVector b, HYPRE\_StructVector x)
- HYPRE\_Int HYPRE\_StructFlexGMRESSetTol (HYPRE\_StructSolver solver, HYPRE\_Real tol)
- HYPRE\_Int HYPRE\_StructFlexGMRESSetAbsoluteTol (HYPRE\_StructSolver solver, HYPRE\_Real tol)
- HYPRE\_Int HYPRE\_StructFlexGMRESSetMaxIter (HYPRE\_StructSolver solver, HYPRE\_Int max\_iter)
- HYPRE\_Int HYPRE\_StructFlexGMRESSetKDim (HYPRE\_StructSolver solver, HYPRE\_Int k\_dim)
- HYPRE\_Int HYPRE\_StructFlexGMRESSetPrecond (HYPRE\_StructSolver solver, HYPRE\_PtrToStructSolverFcn precondition, HYPRE\_PtrToStructSolverFcn precondition\_setup, HYPRE\_StructSolver precondition\_solver)
- HYPRE\_Int HYPRE\_StructFlexGMRESSetLogging (HYPRE\_StructSolver solver, HYPRE\_Int logging)
- HYPRE\_Int HYPRE\_StructFlexGMRESSetPrintLevel (HYPRE\_StructSolver solver, HYPRE\_Int level)
- HYPRE\_Int HYPRE\_StructFlexGMRESGetNumIterations (HYPRE\_StructSolver solver, HYPRE\_Int \*num\_ iterations)
- HYPRE\_Int HYPRE\_StructFlexGMRESGetFinalRelativeResidualNorm (HYPRE\_StructSolver solver, HYPRE\_Real \*norm)
- HYPRE\_Int HYPRE\_StructFlexGMRESGetResidual (HYPRE\_StructSolver solver, void \*\*residual)
- HYPRE\_Int HYPRE\_StructFlexGMRESSetModifyPC (HYPRE\_StructSolver solver, HYPRE\_PtrToModifyPCFcn modify\_pc)

### Struct LGMRES Solver

These routines should be used in conjunction with the generic interface in [Krylov Solvers](#).

- HYPRE\_Int HYPRE\_StructLGMRESCreate (MPI\_Comm comm, HYPRE\_StructSolver \*solver)
- HYPRE\_Int HYPRE\_StructLGMRESDestroy (HYPRE\_StructSolver solver)
- HYPRE\_Int HYPRE\_StructLGMRESSetup (HYPRE\_StructSolver solver, HYPRE\_StructMatrix A, HYPRE\_StructVector b, HYPRE\_StructVector x)
- HYPRE\_Int HYPRE\_StructLGMRESSolve (HYPRE\_StructSolver solver, HYPRE\_StructMatrix A, HYPRE\_StructVector b, HYPRE\_StructVector x)
- HYPRE\_Int HYPRE\_StructLGMRESSetTol (HYPRE\_StructSolver solver, HYPRE\_Real tol)
- HYPRE\_Int HYPRE\_StructLGMRESSetAbsoluteTol (HYPRE\_StructSolver solver, HYPRE\_Real tol)
- HYPRE\_Int HYPRE\_StructLGMRESSetMaxIter (HYPRE\_StructSolver solver, HYPRE\_Int max\_iter)
- HYPRE\_Int HYPRE\_StructLGMRESSetKDim (HYPRE\_StructSolver solver, HYPRE\_Int k\_dim)
- HYPRE\_Int HYPRE\_StructLGMRESSetAugDim (HYPRE\_StructSolver solver, HYPRE\_Int aug\_dim)
- HYPRE\_Int HYPRE\_StructLGMRESSetPrecond (HYPRE\_StructSolver solver, HYPRE\_PtrToStructSolverFcn precondition, HYPRE\_PtrToStructSolverFcn precondition\_setup, HYPRE\_StructSolver precondition\_solver)
- HYPRE\_Int HYPRE\_StructLGMRESSetLogging (HYPRE\_StructSolver solver, HYPRE\_Int logging)

- HYPRE\_Int [HYPRE\\_StructLGMRESSetPrintLevel](#) (HYPRE\_StructSolver solver, HYPRE\_Int level)
- HYPRE\_Int [HYPRE\\_StructLGMRESGetNumIterations](#) (HYPRE\_StructSolver solver, HYPRE\_Int \*num\_↵\_iterations)
- HYPRE\_Int [HYPRE\\_StructLGMRESGetFinalRelativeResidualNorm](#) (HYPRE\_StructSolver solver, HYPRE\_Real \*norm)
- HYPRE\_Int [HYPRE\\_StructLGMRESGetResidual](#) (HYPRE\_StructSolver solver, void \*\*residual)

### Struct BiCGSTAB Solver

*These routines should be used in conjunction with the generic interface in [Krylov Solvers](#).*

- HYPRE\_Int [HYPRE\\_StructBiCGSTABCreate](#) (MPI\_Comm comm, HYPRE\_StructSolver \*solver)
- HYPRE\_Int [HYPRE\\_StructBiCGSTABDestroy](#) (HYPRE\_StructSolver solver)
- HYPRE\_Int [HYPRE\\_StructBiCGSTABSetup](#) (HYPRE\_StructSolver solver, HYPRE\_StructMatrix A, HYPRE\_StructVector b, HYPRE\_StructVector x)
- HYPRE\_Int [HYPRE\\_StructBiCGSTABSolve](#) (HYPRE\_StructSolver solver, HYPRE\_StructMatrix A, HYPRE\_StructVector b, HYPRE\_StructVector x)
- HYPRE\_Int [HYPRE\\_StructBiCGSTABSetTol](#) (HYPRE\_StructSolver solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_StructBiCGSTABSetAbsoluteTol](#) (HYPRE\_StructSolver solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_StructBiCGSTABSetMaxIter](#) (HYPRE\_StructSolver solver, HYPRE\_Int max\_iter)
- HYPRE\_Int [HYPRE\\_StructBiCGSTABSetPrecond](#) (HYPRE\_StructSolver solver, HYPRE\_PtrToStructSolverFcn precondition, HYPRE\_PtrToStructSolverFcn precondition\_setup, HYPRE\_StructSolver precondition\_solver)
- HYPRE\_Int [HYPRE\\_StructBiCGSTABSetLogging](#) (HYPRE\_StructSolver solver, HYPRE\_Int logging)
- HYPRE\_Int [HYPRE\\_StructBiCGSTABSetPrintLevel](#) (HYPRE\_StructSolver solver, HYPRE\_Int level)
- HYPRE\_Int [HYPRE\\_StructBiCGSTABGetNumIterations](#) (HYPRE\_StructSolver solver, HYPRE\_Int \*num\_↵\_iterations)
- HYPRE\_Int [HYPRE\\_StructBiCGSTABGetFinalRelativeResidualNorm](#) (HYPRE\_StructSolver solver, HYPRE\_Real \*norm)
- HYPRE\_Int [HYPRE\\_StructBiCGSTABGetResidual](#) (HYPRE\_StructSolver solver, void \*\*residual)

### Struct Hybrid Solver

- HYPRE\_Int [HYPRE\\_StructHybridCreate](#) (MPI\_Comm comm, HYPRE\_StructSolver \*solver)
- HYPRE\_Int [HYPRE\\_StructHybridDestroy](#) (HYPRE\_StructSolver solver)
- HYPRE\_Int [HYPRE\\_StructHybridSetup](#) (HYPRE\_StructSolver solver, HYPRE\_StructMatrix A, HYPRE\_StructVector b, HYPRE\_StructVector x)
- HYPRE\_Int [HYPRE\\_StructHybridSolve](#) (HYPRE\_StructSolver solver, HYPRE\_StructMatrix A, HYPRE\_StructVector b, HYPRE\_StructVector x)
- HYPRE\_Int [HYPRE\\_StructHybridSetTol](#) (HYPRE\_StructSolver solver, HYPRE\_Real tol)
- HYPRE\_Int [HYPRE\\_StructHybridSetConvergenceTol](#) (HYPRE\_StructSolver solver, HYPRE\_Real cf\_tol)
- HYPRE\_Int [HYPRE\\_StructHybridSetDSCGMaxIter](#) (HYPRE\_StructSolver solver, HYPRE\_Int ds\_max\_↵\_its)
- HYPRE\_Int [HYPRE\\_StructHybridSetPCGMaxIter](#) (HYPRE\_StructSolver solver, HYPRE\_Int pre\_max\_its)
- HYPRE\_Int [HYPRE\\_StructHybridSetTwoNorm](#) (HYPRE\_StructSolver solver, HYPRE\_Int two\_norm)
- HYPRE\_Int [HYPRE\\_StructHybridSetStopCrit](#) (HYPRE\_StructSolver solver, HYPRE\_Int stop\_crit)
- HYPRE\_Int [HYPRE\\_StructHybridSetRelChange](#) (HYPRE\_StructSolver solver, HYPRE\_Int rel\_change)
- HYPRE\_Int [HYPRE\\_StructHybridSetSolverType](#) (HYPRE\_StructSolver solver, HYPRE\_Int solver\_type)
- HYPRE\_Int [HYPRE\\_StructHybridSetRecomputeResidual](#) (HYPRE\_StructSolver solver, HYPRE\_Int recompute\_residual)
- HYPRE\_Int [HYPRE\\_StructHybridGetRecomputeResidual](#) (HYPRE\_StructSolver solver, HYPRE\_Int \*recompute\_residual)
- HYPRE\_Int [HYPRE\\_StructHybridSetRecomputeResidualP](#) (HYPRE\_StructSolver solver, HYPRE\_Int recompute\_residual\_p)
- HYPRE\_Int [HYPRE\\_StructHybridGetRecomputeResidualP](#) (HYPRE\_StructSolver solver, HYPRE\_Int \*recompute\_residual\_p)
- HYPRE\_Int [HYPRE\\_StructHybridSetKDim](#) (HYPRE\_StructSolver solver, HYPRE\_Int k\_dim)
- HYPRE\_Int [HYPRE\\_StructHybridSetPrecond](#) (HYPRE\_StructSolver solver, HYPRE\_PtrToStructSolverFcn precondition, HYPRE\_PtrToStructSolverFcn precondition\_setup, HYPRE\_StructSolver precondition\_solver)
- HYPRE\_Int [HYPRE\\_StructHybridSetLogging](#) (HYPRE\_StructSolver solver, HYPRE\_Int logging)
- HYPRE\_Int [HYPRE\\_StructHybridSetPrintLevel](#) (HYPRE\_StructSolver solver, HYPRE\_Int print\_level)
- HYPRE\_Int [HYPRE\\_StructHybridGetNumIterations](#) (HYPRE\_StructSolver solver, HYPRE\_Int \*num\_↵\_its)

- HYPRE\_Int [HYPRE\\_StructHybridGetDSCGNumIterations](#) (HYPRE\_StructSolver solver, HYPRE\_Int \*ds\_num\_its)
- HYPRE\_Int [HYPRE\\_StructHybridGetPCGNumIterations](#) (HYPRE\_StructSolver solver, HYPRE\_Int \*pre\_its)
- HYPRE\_Int [HYPRE\\_StructHybridGetFinalRelativeResidualNorm](#) (HYPRE\_StructSolver solver, HYPRE\_Real \*norm)
- HYPRE\_Int [HYPRE\\_StructHybridSetPCGAbsoluteTolFactor](#) (HYPRE\_StructSolver solver, HYPRE\_Real pcg\_atolf)

### Struct LOBPCG Eigensolver

These routines should be used in conjunction with the generic interface in [Eigensolvers](#).

- HYPRE\_Int [HYPRE\\_StructSetupInterpreter](#) (mv\_InterfaceInterpreter \*i)
- HYPRE\_Int [HYPRE\\_StructSetupMatvec](#) (HYPRE\_MatvecFunctions \*mv)

### Struct Solvers

- #define [HYPRE\\_MODIFYPC](#)
- #define [HYPRE\\_SOLVER\\_STRUCT](#)
- typedef struct hypre\_StructSolver\_struct \* [HYPRE\\_StructSolver](#)
- typedef HYPRE\_Int(\* [HYPRE\\_PtrToStructSolverFcn](#)) (HYPRE\_StructSolver, HYPRE\_StructMatrix, HYPRE\_StructVector, HYPRE\_StructVector)
- typedef struct hypre\_Solver\_struct \* [HYPRE\\_Solver](#)
- typedef HYPRE\_Int(\* [HYPRE\\_PtrToModifyPCFcn](#)) (HYPRE\_Solver, HYPRE\_Int, HYPRE\_Real)

## 4.8 HYPRE\_struct\_mv.h File Reference

### Macros

- #define [HYPRE\\_StructVector\\_defined](#)

### Typedefs

- typedef struct hypre\_StructVector\_struct \* [HYPRE\\_StructVector](#)
- typedef struct hypre\_CommPkg\_struct \* [HYPRE\\_CommPkg](#)

### Functions

- HYPRE\_Int [HYPRE\\_StructMatrixGetGrid](#) (HYPRE\_StructMatrix matrix, HYPRE\_StructGrid \*grid)
- HYPRE\_Int [HYPRE\\_StructVectorSetNumGhost](#) (HYPRE\_StructVector vector, HYPRE\_Int \*num\_ghost)
- HYPRE\_Int [HYPRE\\_StructVectorSetConstantValues](#) (HYPRE\_StructVector vector, HYPRE\_Complex values)
- HYPRE\_Int [HYPRE\\_StructVectorGetMigrateCommPkg](#) (HYPRE\_StructVector from\_vector, HYPRE\_StructVector to\_vector, HYPRE\_CommPkg \*comm\_pkg)
- HYPRE\_Int [HYPRE\\_StructVectorMigrate](#) (HYPRE\_CommPkg comm\_pkg, HYPRE\_StructVector from\_vector, HYPRE\_StructVector to\_vector)
- HYPRE\_Int [HYPRE\\_CommPkgDestroy](#) (HYPRE\_CommPkg comm\_pkg)

### Struct Vectors

- `HYPRE_Int HYPRE_StructVectorCreate` (`MPI_Comm comm`, `HYPRE_StructGrid grid`, `HYPRE_StructVector *vector`)
- `HYPRE_Int HYPRE_StructVectorDestroy` (`HYPRE_StructVector vector`)
- `HYPRE_Int HYPRE_StructVectorInitialize` (`HYPRE_StructVector vector`)
- `HYPRE_Int HYPRE_StructVectorSetValues` (`HYPRE_StructVector vector`, `HYPRE_Int *index`, `HYPRE_Complex value`)
- `HYPRE_Int HYPRE_StructVectorAddToValues` (`HYPRE_StructVector vector`, `HYPRE_Int *index`, `HYPRE_Complex value`)
- `HYPRE_Int HYPRE_StructVectorSetBoxValues` (`HYPRE_StructVector vector`, `HYPRE_Int *ilower`, `HYPRE_Int *iupper`, `HYPRE_Complex *values`)
- `HYPRE_Int HYPRE_StructVectorAddToBoxValues` (`HYPRE_StructVector vector`, `HYPRE_Int *ilower`, `HYPRE_Int *iupper`, `HYPRE_Complex *values`)
- `HYPRE_Int HYPRE_StructVectorSetBoxValues2` (`HYPRE_StructVector vector`, `HYPRE_Int *ilower`, `HYPRE_Int *iupper`, `HYPRE_Int *vilower`, `HYPRE_Int *viupper`, `HYPRE_Complex *values`)
- `HYPRE_Int HYPRE_StructVectorAddToBoxValues2` (`HYPRE_StructVector vector`, `HYPRE_Int *ilower`, `HYPRE_Int *iupper`, `HYPRE_Int *vilower`, `HYPRE_Int *viupper`, `HYPRE_Complex *values`)
- `HYPRE_Int HYPRE_StructVectorAssemble` (`HYPRE_StructVector vector`)
- `HYPRE_Int HYPRE_StructVectorGetValues` (`HYPRE_StructVector vector`, `HYPRE_Int *index`, `HYPRE_Complex *value`)
- `HYPRE_Int HYPRE_StructVectorGetBoxValues` (`HYPRE_StructVector vector`, `HYPRE_Int *ilower`, `HYPRE_Int *iupper`, `HYPRE_Complex *values`)
- `HYPRE_Int HYPRE_StructVectorGetBoxValues2` (`HYPRE_StructVector vector`, `HYPRE_Int *ilower`, `HYPRE_Int *iupper`, `HYPRE_Int *vilower`, `HYPRE_Int *viupper`, `HYPRE_Complex *values`)
- `HYPRE_Int HYPRE_StructVectorPrint` (`const char *filename`, `HYPRE_StructVector vector`, `HYPRE_Int all`)

## Struct Grids

- `typedef struct hypre_StructGrid_struct * HYPRE_StructGrid`
- `HYPRE_Int HYPRE_StructGridCreate` (`MPI_Comm comm`, `HYPRE_Int ndim`, `HYPRE_StructGrid *grid`)
- `HYPRE_Int HYPRE_StructGridDestroy` (`HYPRE_StructGrid grid`)
- `HYPRE_Int HYPRE_StructGridSetExtents` (`HYPRE_StructGrid grid`, `HYPRE_Int *ilower`, `HYPRE_Int *iupper`)
- `HYPRE_Int HYPRE_StructGridAssemble` (`HYPRE_StructGrid grid`)
- `HYPRE_Int HYPRE_StructGridSetPeriodic` (`HYPRE_StructGrid grid`, `HYPRE_Int *periodic`)
- `HYPRE_Int HYPRE_StructGridSetNumGhost` (`HYPRE_StructGrid grid`, `HYPRE_Int *num_ghost`)

## Struct Stencils

- `typedef struct hypre_StructStencil_struct * HYPRE_StructStencil`
- `HYPRE_Int HYPRE_StructStencilCreate` (`HYPRE_Int ndim`, `HYPRE_Int size`, `HYPRE_StructStencil *stencil`)
- `HYPRE_Int HYPRE_StructStencilDestroy` (`HYPRE_StructStencil stencil`)
- `HYPRE_Int HYPRE_StructStencilSetElement` (`HYPRE_StructStencil stencil`, `HYPRE_Int entry`, `HYPRE_Int *offset`)

## Struct Matrices

- `typedef struct hypre_StructMatrix_struct * HYPRE_StructMatrix`
- `HYPRE_Int HYPRE_StructMatrixCreate` (`MPI_Comm comm`, `HYPRE_StructGrid grid`, `HYPRE_StructStencil stencil`, `HYPRE_StructMatrix *matrix`)
- `HYPRE_Int HYPRE_StructMatrixDestroy` (`HYPRE_StructMatrix matrix`)
- `HYPRE_Int HYPRE_StructMatrixInitialize` (`HYPRE_StructMatrix matrix`)
- `HYPRE_Int HYPRE_StructMatrixSetValues` (`HYPRE_StructMatrix matrix`, `HYPRE_Int *index`, `HYPRE_Int nentries`, `HYPRE_Int *entries`, `HYPRE_Complex *values`)
- `HYPRE_Int HYPRE_StructMatrixAddToValues` (`HYPRE_StructMatrix matrix`, `HYPRE_Int *index`, `HYPRE_Int nentries`, `HYPRE_Int *entries`, `HYPRE_Complex *values`)



- HYPRE\_Int [HYPRE\\_StructMatrixSetConstantValues](#) (HYPRE\_StructMatrix matrix, HYPRE\_Int nentries, HYPRE\_Int \*entries, HYPRE\_Complex \*values)
- HYPRE\_Int [HYPRE\\_StructMatrixAddToConstantValues](#) (HYPRE\_StructMatrix matrix, HYPRE\_Int nentries, HYPRE\_Int \*entries, HYPRE\_Complex \*values)
- HYPRE\_Int [HYPRE\\_StructMatrixSetBoxValues](#) (HYPRE\_StructMatrix matrix, HYPRE\_Int \*ilower, HYPRE\_Int \*iupper, HYPRE\_Int nentries, HYPRE\_Int \*entries, HYPRE\_Complex \*values)
- HYPRE\_Int [HYPRE\\_StructMatrixAddToBoxValues](#) (HYPRE\_StructMatrix matrix, HYPRE\_Int \*ilower, HYPRE\_Int \*iupper, HYPRE\_Int nentries, HYPRE\_Int \*entries, HYPRE\_Complex \*values)
- HYPRE\_Int [HYPRE\\_StructMatrixSetBoxValues2](#) (HYPRE\_StructMatrix matrix, HYPRE\_Int \*ilower, HYPRE\_Int \*iupper, HYPRE\_Int nentries, HYPRE\_Int \*entries, HYPRE\_Int \*vilower, HYPRE\_Int \*viupper, HYPRE\_Complex \*values)
- HYPRE\_Int [HYPRE\\_StructMatrixAddToBoxValues2](#) (HYPRE\_StructMatrix matrix, HYPRE\_Int \*ilower, HYPRE\_Int \*iupper, HYPRE\_Int nentries, HYPRE\_Int \*entries, HYPRE\_Int \*vilower, HYPRE\_Int \*viupper, HYPRE\_Complex \*values)
- HYPRE\_Int [HYPRE\\_StructMatrixAssemble](#) (HYPRE\_StructMatrix matrix)
- HYPRE\_Int [HYPRE\\_StructMatrixGetValues](#) (HYPRE\_StructMatrix matrix, HYPRE\_Int \*index, HYPRE\_Int nentries, HYPRE\_Int \*entries, HYPRE\_Complex \*values)
- HYPRE\_Int [HYPRE\\_StructMatrixGetBoxValues](#) (HYPRE\_StructMatrix matrix, HYPRE\_Int \*ilower, HYPRE\_Int \*iupper, HYPRE\_Int nentries, HYPRE\_Int \*entries, HYPRE\_Complex \*values)
- HYPRE\_Int [HYPRE\\_StructMatrixGetBoxValues2](#) (HYPRE\_StructMatrix matrix, HYPRE\_Int \*ilower, HYPRE\_Int \*iupper, HYPRE\_Int nentries, HYPRE\_Int \*entries, HYPRE\_Int \*vilower, HYPRE\_Int \*viupper, HYPRE\_Complex \*values)
- HYPRE\_Int [HYPRE\\_StructMatrixSetSymmetric](#) (HYPRE\_StructMatrix matrix, HYPRE\_Int symmetric)
- HYPRE\_Int [HYPRE\\_StructMatrixSetConstantEntries](#) (HYPRE\_StructMatrix matrix, HYPRE\_Int nentries, HYPRE\_Int \*entries)
- HYPRE\_Int [HYPRE\\_StructMatrixSetNumGhost](#) (HYPRE\_StructMatrix matrix, HYPRE\_Int \*num\_ghost)
- HYPRE\_Int [HYPRE\\_StructMatrixPrint](#) (const char \*filename, HYPRE\_StructMatrix matrix, HYPRE\_Int all)
- HYPRE\_Int [HYPRE\\_StructMatrixMatvec](#) (HYPRE\_Complex alpha, HYPRE\_StructMatrix A, HYPRE\_StructVector x, HYPRE\_Complex beta, HYPRE\_StructVector y)

## 4.8.1 Macro Definition Documentation

### 4.8.1.1 HYPRE\_StructVector\_defined

```
#define HYPRE_StructVector_defined
```

## 4.8.2 Typedef Documentation

### 4.8.2.1 HYPRE\_CommPkg

```
typedef struct hypre_CommPkg_struct* HYPRE_CommPkg
```

### 4.8.2.2 HYPRE\_StructVector

```
typedef struct hypre_StructVector_struct* HYPRE_StructVector
```

## 4.8.3 Function Documentation

### 4.8.3.1 HYPRE\_CommPkgDestroy()

```
HYPRE_Int HYPRE_CommPkgDestroy (
    HYPRE_CommPkg comm_pkg )
```

### 4.8.3.2 HYPRE\_StructMatrixGetGrid()

```
HYPRE_Int HYPRE_StructMatrixGetGrid (
    HYPRE_StructMatrix matrix,
    HYPRE_StructGrid * grid )
```

### 4.8.3.3 HYPRE\_StructVectorGetMigrateCommPkg()

```
HYPRE_Int HYPRE_StructVectorGetMigrateCommPkg (
    HYPRE_StructVector from_vector,
    HYPRE_StructVector to_vector,
    HYPRE_CommPkg * comm_pkg )
```

### 4.8.3.4 HYPRE\_StructVectorMigrate()

```
HYPRE_Int HYPRE_StructVectorMigrate (
    HYPRE_CommPkg comm_pkg,
    HYPRE_StructVector from_vector,
    HYPRE_StructVector to_vector )
```

### 4.8.3.5 HYPRE\_StructVectorSetConstantValues()

```
HYPRE_Int HYPRE_StructVectorSetConstantValues (
    HYPRE_StructVector vector,
    HYPRE_Complex values )
```

### 4.8.3.6 HYPRE\_StructVectorSetNumGhost()

```
HYPRE_Int HYPRE_StructVectorSetNumGhost (
    HYPRE_StructVector vector,
    HYPRE_Int * num_ghost )
```